RedFalcon Watercraft JSON configuration files can be found in the **<game>\Profile\RFWatercraft** folder. It is important to note that the default versions of these JSON configuration files are only generated when the boats are spawned into game. If you just installed the mod, don't be concerned if you can't find the folder or files, you'll need to log into your server and spawn all of the boat models to generate the default JSON configuration files.

This behavior is a by-product of the feature that allows JSON configuration file updates to take effect immediately the next time that you spawn a boat into the server. This allows for easy config tunings (trying a series of changes to get it 'just right' for you) without having to do a server restart every time.

There are 2 types of JSON configuration files, one is called **MasterConfig.json** and settings here affect all boats in the mod. The other JSON configuration files are for each boat model (notice per model, not per retexture). They follow this naming convention: **{boat class name}_Config.json** such as **RFWC_CarpBoat_Config.json**.

MasterConfig.json settings:

Master_ConfigVersion

This is used by the mod itself to track the configuration schema being used (so that if I add new settings, the mod will know to update your config files). **DO NOT ALTER THIS SETTING.**

HUD_ForceMetric

Valid settings: 1 or 0
Default: 0
Forces all measurements on the HUD to use the metric system as opposed to what is defined for the individual helicopter models

HUD_ForceImperial

Valid settings: 1 or 0
Default: 0
Forces all measurements on the HUD to use the imperial system as opposed to what is defined for the individual helicopter models

HUD_Allow1PP

Valid settings: 1 or 0
Default: 1
Allow the HUD to be displayed in the 1st Person Point of view

HUD_Allow3PP

Valid settings: 1 or 0
Default: 1
Allow the HUD to be displayed in the 3rd Person Point of view

Control_Grounded

Valid settings: 1 or 0
Default: 0
When enabled (1), grounds all boats on the server by preventing them from being started. Note that changing this setting does require a server restart. This can be useful for non-heli based events on a server where you want to temporarily disable all of them.

Sound_EngineVolume

Valid settings: percentage
Default: 100.0
Controls the volume of the boat engines while running, expressed as a percentage of the default volume. This will affect all of the boats on the server.

Damage_AllowWeaponDamage

Valid settings: 1 or 0
Default: 1
Enables/disables the ability for a helicopter to get damaged by having weapons fired at it

{boat class name}_Config.json config settings

Boat_ConfigVersion

This is used by the mod itself to track the configuration schema being used (so that if I add new settings, the mod will know to update your config files). **DO NOT ALTER THIS SETTING.**

Boat_FuelCapacity

Valid settings: liters
Total fuel capacity of a helicopter in liters

Boat_FuelConsumptionRate

Valid settings: liters per minute
The amount of fuel that a helicopter uses while the engine is running, in liters per minute

Heli_MinimumDraught

Valid settings: depth in Meters
Defines the minimum depth that the boat will need to operate, measured in meters..

Boat_MaximumSpeed

Valid settings: speed in Knots (nautical miles per hour)
Limits the maximum that a boat can go. It is important to interpret this as “can’t go faster than” rather than “can go up to this speed” as this is a governor, not thrust control. You will find that setting this higher doesn’t necessarily mean that the boat can go faster, it just means that the boat is prevented from going faster.

Boat_SpeedFactor

Valid settings: percentage
Sets a Speed Factor to determine how fast the boat can boat, expressed as a percentage of the base design of the boat. For example, 200.0 will increase the speed of the boat by 200%. Note that you may also have to adjust Boat_MaximumSpeed, as that config acts as a limiter.

Flight_AerodynamicDrag

Valid settings: number
Sets the amount of hydrodynamic drag applied to the boat, causing it to gradually slow down.