

CMakeLists.txt

```

1  # Generated Cmake Pico project file
2  # U13157005 吳翊弘
3  cmake_minimum_required (VERSION 3.13)
4
5  set (CMAKE_C_STANDARD 11)
6  set (CMAKE_CXX_STANDARD 17)
7
8  set (CMAKE_EXPORT_COMPILE_COMMANDS ON)
9
10 # Initialise pico_sdk from installed location
11 # (note this can come from environment, CMake cache etc)
12
13 # == DO NOT EDIT THE FOLLOWING LINES for the Raspberry Pi Pico VS Code Extension to work ==
14 if(WIN32)
15     set (USERHOME $ENV{USERPROFILE})
16 else()
17     set (USERHOME $ENV{HOME})
18 endif()
19 set (sdkVersion 2.2.0)
20 set (toolchainVersion 14_2_Rel1)
21 set(picotoolVersion 2.2.0-a4)
22 set (picoVscode ${USERHOME}/.pico-sdk/cmake/pico-vscode.cmake)
23 if (EXISTS ${picoVscode})
24     include(${picoVscode})
25 endif()
26 # =====
27
28 set (PICO_BOARD pico CACHE STRING "Board type")
29
30 # Pull in Raspberry Pi Pico SDK (must be before project)
31 include(pico_sdk_import.cmake)
32
33 # 【修改點】在此處加入 ASM，讓專案能夠識別與編譯組合語言 (.S) 檔案
34 project(hello_usb C CXX ASM)
35
36 # Initialise the Raspberry Pi Pico SDK
37 pico_sdk_init()
38
39 if (TARGET tinyusb_device)
40
41     # 【修改點】將 hello_usb.c 與 movaddsubshift.S 一併納入編譯
42     add_executable(hello_usb
43         #hello_usb.c
44         movaddsubshift.S
45     )
46
47     # pull in common dependencies
48     target_link_libraries (hello_usb pico_stdlib)
49
50     # enable usb output, disable uart output
51     pico_enable_stdio_usb (hello_usb 1)

```

```
52     pico_enable_stdio_uart(hello_usb 0)
53
54     # create map/bin/hex/uf2 file etc.
55     pico_add_extra_outputs (hello_usb)
56
57 elseif (PICO_ON_DEVICE)
58     message("Skipping hello_usb because TinyUSB submodule is not initialized in the SDK")
59 endif()
```