

CMakeLists.txt

```

1  # Generated Cmake Pico project file
2  #
3  # U13157005 吳翊弘
4  #
5  cmake_minimum_required(VERSION 3.13)
6
7  set(CMAKE_C_STANDARD 11)
8  set(CMAKE_CXX_STANDARD 17)
9  set(CMAKE_EXPORT_COMPILE_COMMANDS ON)
10
11 # Initialise pico_sdk from installed location
12 # (note this can come from environment, CMake cache etc)
13
14 # == DO NOT EDIT THE FOLLOWING LINES for the Raspberry Pi Pico VS Code Extension to work ==
15 if(WIN32)
16     set(USERHOME $ENV{USERPROFILE})
17 else()
18     set(USERHOME $ENV{HOME})
19 endif()
20 set(sdkVersion 2.2.0)
21 set(toolchainVersion 14_2_Rel1)
22 set(picotoolVersion 2.2.0-a4)
23 set(picoVscode ${USERHOME}/.pico-sdk/cmake/pico-vscode.cmake)
24 if (EXISTS ${picoVscode})
25     include(${picoVscode})
26 endif()
27 # =====
28 set(PICO_BOARD pico CACHE STRING "Board type")
29
30 # Pull in Raspberry Pi Pico SDK (must be before project)
31 include(pico_sdk_import.cmake)
32
33 project(hello_usb C CXX ASM)
34
35 # Initialise the Raspberry Pi Pico SDK
36 pico_sdk_init()
37
38 # Add executable. Default name is the project name, version 0.1
39
40 if (TARGET tinyusb_device)
41     add_executable(hello_usb
42         # hello_usb.c
43         ControlFlow.S
44     )
45
46     # pull in common dependencies
47     target_link_libraries(hello_usb pico_stdlib)
48
49     # enable usb output, disable uart output
50     pico_enable_stdio_usb(hello_usb 1)
51     pico_enable_stdio_uart(hello_usb 0)

```

```
52  
53     # create map/bin/hex/uf2 file etc.  
54     pico_add_extra_outputs(hello_usb)  
55  
56     # add url via pico_set_program_url  
57 elseif(PICO_ON_DEVICE)  
58     message("Skipping hello_usb because TinyUSB submodule is not initialized in the SDK")  
59 endif()  
60
```