

Pi Pico 1

子二甲 U13157005 吳翊弘

File Edit Selection View Go Run Terminal Help

hello_usb

Sign In

EXPLORER

HELLO_USB

.vscode

build

hello_usb

.gitignore

CMakeLists.txt

hello_usb.c 1

HelloWorld.S

pico_sdk_import.cmake

CMakeLists.txt

HelloWorld.S

hello_usb.c 1

```
1  /**
2  * Copyright (c) 2020 Raspberry Pi (Trading) Ltd.
3  *
4  * U13157005 吳翊弘 2026/07/03
5  * SPDX-License-Identifier: BSD-3-Clause
6  *
7  * /
8
9  #include <stdio.h>
10 #include "pico/stdlib.h"
11
12 int main() {
13     stdio_init_all();
14     while (true) {
15         printf("Hello, world!\n");
16         sleep_ms(1000);
17     }
18 }
19
```

PROBLEMS 1 OUTPUT DEBUG CONSOLE TERMINAL PORTS MEMORY XRTOS SERIAL MONITOR

+ Open an additional monitor

Monitor Mode Serial View Mode Text Port COM5 - USB 序列裝置 (COM5) Baud rate 115200

Line ending None Stop Monitoring

Hello World 2357101 U13157005 吳翊弘
Hello World 2357102 U13157005 吳翊弘
Hello World 2357103 U13157005 吳翊弘
Hello World 2357104 U13157005 吳翊弘
Hello World 2357105 U13157005 吳翊弘

Type in a message to send to the serial port.

Send as Text Send Ctrl + C

OUTLINE

TIMELINE

Launchpad 1 0

Ln 19, Col 1 Spaces: 4 UTF-8 CRLF C Compile Run Pico SDK: 2.2.0 Board: pico Pico

Build with Agent

AI responses may be inaccurate

Generate Agent Instructions to onboard AI onto your codebase.

+ C hello_usb.c

Describe what to build

+ Models

File Edit Selection View Go Run Terminal Help

Sign In

EXPLORER

HELLO_USB
 > .vscode
 > build
 > hello_usb
 .gitignore
 CMakeLists.txt
 hello_usb.c
 HelloWorld.S
 pico_sdk_import.cmake

1
2
3
4
5
6
7
8
9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24
25
26

1 @
2 @ Assembler program print out "Hello World"
3 @ using the Pico SDK.
4 @
5 @ R0 - first parameter to printf
6 @ R1 - second parameter to printer
7 @ R7 - index counter
8 @
9
10 .thumb_func @ Necessary because sdk uses BLX
11 .global main @ Provide program starting address to linker
12
13 main:
14 MOV R7, #0 @ initialize counter to 0
15 BL stdio_init_all @ initialize uart or usb
16 loop:
17 LDR R0, =helloworld @ load address of helloworld string
18 ADD R7, #1 @ Increment counter
19 MOV R1, R7 @ Move the counter to second parameter
20 BL printf @ Call pico_printf
21 B loop @ loop forever
22
23 .data
24 .align 4 @ necessary alignment
25 helloworld: .asciz "Hello World %d U13157005 吳翊弘\n"
26

PROBLEMS OUTPUT DEBUG CONSOLE TERMINAL PORTS MEMORY XRTOS SERIAL MONITOR

+ Open an additional monitor

Monitor Mode Serial View Mode Text Port COM5 - USB 序列裝置 (COM5) Baud rate 115200

Line ending None Stop Monitoring

Hello World 2822882 U13157005 吳翊弘
Hello World 2822883 U13157005 吳翊弘
Hello World 2822884 U13157005 吳翊弘
Hello World 2822885 U13157005 吳翊弘
Hello World 2822886 U13157005 吳翊弘
Hello World 2822887 U13157005 吳翊弘

Type in a message to send to the serial port.

Build with Agent
AI responses may be inaccurate
[Generate Agent Instructions](#) to onboard AI onto your codebase.

+ HelloWorld.S

Describe what to build

+ Models

Send Ctrl + C

Compile Run Pico SDK: 2.2.0 Board: pico

complete program to print "Hello World!" and viewed it in m

Raspberry Pi. In Chapter 3, we will look in more detail at the

OUTLINE
TIMELINE

Launchpad 1 0

Ln 25

U13157005
吳翊弘
電子工程系
上學期 11/7 18 樓
下學期
悠遊卡 EASYCARD 悠遊卡 820 547019 0