


dk_bspal_deserializer.h File Reference

```
#include <stdint.h>
```

Include dependency graph for dk_bspal_deserializer.h:



This graph shows which files directly or indirectly include this file:

[Go to the source code of this file.](#)

Macros

```
#define DESERIALIZER_DEINIT ((uint8_t)0)
    Library provides fixed-width integer types and macros. More...

#define DESERIALIZER_INIT ((uint8_t)1)

#define DESERIALIZER_STOP ((uint8_t)0)

#define DESERIALIZER_START ((uint8_t)1)

#define DESERIALIZER_LINK_STATUS ((uint8_t)0)

#define DESERIALIZER_ERROR_STATUS ((uint8_t)1)

#define DESERIALIZER_TEST_PATTERN ((uint8_t)0)
```

Functions

```
void dk_bspal_deserializer_init (void)
    API to register context for logging. More...

void dk_bspal_deserializer_deinit (void)
    API to unregister context. More...

int32_t dk_bspal_deserializer_configure (uint8_t p_config_cmd_U8)
    API to configure the deserializer device. More...

int32_t dk_bspal_deserializer_streaming_control (uint8_t p_control_cmd_U8)
    API to control deserializer streaming. More...

int32_t dk_bspal_deserializer_get_status (uint8_t p_status_type_U8, int32_t *p_status_val_S32)
    API to retrieve the status of the deserializer. More...

int32_t dk_bspal_deserializer_test_pattern (uint8_t p_control_cmd_U8)
    API to start test pattern of deserializer device. More...
```

Macro Definition Documentation

◆ DESERIALIZER_DEINIT

#define DESERIALIZER_DEINIT ((uint8_t)0)

Library provides fixed-width integer types and macros.

IOCTL constants

◆ DESERIALIZER_ERROR_STATUS

#define DESERIALIZER_ERROR_STATUS ((uint8_t)1)

◆ DESERIALIZER_INIT

```
#define DESERIALIZER_INIT ((uint8_t)1)
```

◆ DESERIALIZER_LINK_STATUS

```
#define DESERIALIZER_LINK_STATUS ((uint8_t)0)
```

◆ DESERIALIZER_START

```
#define DESERIALIZER_START ((uint8_t)1)
```

◆ DESERIALIZER_STOP

```
#define DESERIALIZER_STOP ((uint8_t)0)
```

◆ DESERIALIZER_TEST_PATTERN

```
#define DESERIALIZER_TEST_PATTERN ((uint8_t)0)
```

Function Documentation

◆ dk_bspal_deserializer_configure()

```
int32_t dk_bspal_deserializer_configure ( uint8_t p_config_cmd_U8 )
```

API to configure the deserializer device.

Parameters

[in] **p_config_cmd_U8** Configuration command (e.g., INIT, DEINIT).

Returns

EOK (0) on success, or -1 on failure.

Here is the call graph for this function:



◆ dk_bspal_deserializer_deinit()

```
void dk_bspal_deserializer_deinit ( void )
```

API to unregister context.

◆ dk_bspal_deserializer_get_status()

```
int32_t dk_bspal_deserializer_get_status ( uint8_t p_status_type_U8,  
                                           int32_t* p_status_val_S32  
                                           )
```

API to retrieve the status of the deserializer.

Parameters

[in] **p_status_type_U8** Type of status to retrieve (e.g., LINK STATUS, ERROR STATUS).

[out] **p_status_val_S32** Pointer to store the retrieved status value.

Returns

EOK (0) on success, or -1 on failure.

Here is the call graph for this function:



◆ dk_bspal_deserializer_init()

```
void dk_bspal_deserializer_init ( void )
```

API to register context for logging.

◆ dk_bspal_deserializer_streaming_control()

```
int32_t dk_bspal_deserializer_streaming_control ( uint8_t p_control_cmd_U8 )
```

API to control deserializer streaming.


Parameters

[in] **p_control_cmd_U8** Control command (e.g., START, STOP).

Returns

EOK (0) on success, or -1 on failure.

Here is the call graph for this function:



◆ dk_bspal_deserializer_test_pattern()

```
int32_t dk_bspal_deserializer_test_pattern ( uint8_t p_control_cmd_U8 )
```

API to start test pattern of deserializer device.

Returns

EOK (0) on success, or -1 on failure

Here is the call graph for this function:

