


dk_bspal_serializer.h File Reference

```
#include <stdint.h>
```

Include dependency graph for dk_bspal_serializer.h:



This graph shows which files directly or indirectly include this file:

[Go to the source code of this file.](#)

Macros

- #define **SERIALIZER_DEINIT** ((uint8_t)0)
Library provides fixed-width integer types and macros. [More...](#)
- #define **SERIALIZER_INIT** ((uint8_t)1)
- #define **SERIALIZER_STOP** ((uint8_t)0)
- #define **SERIALIZER_START** ((uint8_t)1)
- #define **SERIALIZER_LINK_STATUS** ((uint8_t)0)
- #define **SERIALIZER_ERROR_STATUS** ((uint8_t)1)

Functions

- int32_t **dk_bspal_serializer_configure** (uint8_t p_config_cmd_U8)
API to configure the serializer device. [More...](#)
- int32_t **dk_bspal_serializer_streaming_control** (uint8_t p_control_cmd_U8)

API to control serializer streaming. [More...](#)

int32_t [dk_bspal_serializer_get_status](#) (uint8_t p_status_type_U8, int32_t *p_status_val_S32)

API to retrieve the status of the serializer. [More...](#)

Macro Definition Documentation

◆ **SERIALIZER_DEINIT**

```
#define SERIALIZER_DEINIT ((uint8_t)0)
```

Library provides fixed-width integer types and macros.

◆ **SERIALIZER_ERROR_STATUS**

```
#define SERIALIZER_ERROR_STATUS ((uint8_t)1)
```

◆ **SERIALIZER_INIT**

```
#define SERIALIZER_INIT ((uint8_t)1)
```

◆ **SERIALIZER_LINK_STATUS**

```
#define SERIALIZER_LINK_STATUS ((uint8_t)0)
```

◆ **SERIALIZER_START**

```
#define SERIALIZER_START ((uint8_t)1)
```

◆ **SERIALIZER_STOP**

```
#define SERIALIZER_STOP ((uint8_t)0)
```

Function Documentation

◆ dk_bspal_serializer_configure()

```
int32_t dk_bspal_serializer_configure ( uint8_t p_config_cmd_U8 )
```

API to configure the serializer device.


Parameters

[in] **p_config_cmd_U8** Configuration command (e.g., INIT, DEINIT).


Returns

EOK (0) on success, or -1 on failure.

Here is the call graph for this function:



Here is the caller graph for this function:



◆ dk_bspal_serializer_get_status()

```
int32_t dk_bspal_serializer_get_status ( uint8_t  p_status_type_U8,  
                                         int32_t * p_status_val_S32  
                                         )
```

API to retrieve the status of the serializer.

Parameters

[in] **p_status_type_U8** Type of status to retrieve (e.g., LINK STATUS, ERROR STATUS).

[out] **p_status_val_S32** Pointer to store the retrieved status value.


Returns

EOK (0) on success, or -1 on failure.

Here is the call graph for this function:



Here is the caller graph for this function:



◆ dk_bspal_serializer_streaming_control()

```
int32_t dk_bspal_serializer_streaming_control ( uint8_t p_control_cmd_U8 )
```

API to control serializer streaming.

Parameters

[in] **p_control_cmd_U8** Control command (e.g., START, STOP).


Returns

EOK (0) on success, or -1 on failure.

Here is the call graph for this function:



Here is the caller graph for this function:



Generated by [doxygen](#) 1.9.4