

H20.80:MC Monitor									
MC Monitor									
0	NL	FOR	[W]Var DW00020 ---	[W]Init 00000	[W]Max 00015	[W]Step 00001			
1	NL			EXPRESSION					
	2			'I' = 'DW00020' * 2 I = DW00020 * 2; 'J' = 'DW00020' * 0x80 J = DW00020 * 0x80;					
FB Speed									
2	NL						STORE	[WLFQD]Src OL8010j ---	[WLFQD]Dest ML00600i ---
3	NL						STORE	[WLFQD]Src OL8810j STR1Y1~Speed reference	[WLFQD]Dest ML00632i ---
4	NL						STORE	[WLFQD]Src OLA010j CX~Speed reference	[WLFQD]Dest ML00664i ---
5	NL						STORE	[WLFQD]Src OLA810j SCHY1~Speed reference	[WLFQD]Dest ML00696i ---
6	NL						STORE	[WLFQD]Src OLB010j BKPBY1~Speed reference	[WLFQD]Dest ML00728i ---
7	NL						STORE	[WLFQD]Src OLB810j ---	[WLFQD]Dest ML00760i ---
8	NL						STORE	[WLFQD]Src OLC010j ---	[WLFQD]Dest ML00792i ---
FB Address									
9	NL						STORE	[WLFQD]Src IL8016j A1~Machine coordinate feedback Po	[WLFQD]Dest ML53920i ---
10	NL						STORE	[WLFQD]Src IL8816j STR1Y1~Machine coordinate feedb-	[WLFQD]Dest ML53952i ---
11	NL						STORE	[WLFQD]Src ILA016j CX~Machine coordinate feedback po	[WLFQD]Dest ML53984i ---
12	NL						STORE	[WLFQD]Src ILA816j SCHY1~Machine coordinate feedback-	[WLFQD]Dest ML54016i ---
13	NL						STORE	[WLFQD]Src ILB016j BKPBY1~Machine coordinate feedb-	[WLFQD]Dest ML54048i ---
14	NL						STORE	[WLFQD]Src ILB816j ---	[WLFQD]Dest ML54080i ---
15	NL						STORE	[WLFQD]Src ILC016j SCH1~Machine coordinate feedback-	[WLFQD]Dest ML54112i ---
FB Torque									
16	NL						STORE	[WLFQD]Src IL8042j ---	[WLFQD]Dest ML54160i ---
17	NL						STORE	[WLFQD]Src IL8842j STR1Y1~Feedback torque/thrust	[WLFQD]Dest ML54192i ---
18	NL						STORE	[WLFQD]Src ILA042j CX~Feedback torque/thrust	[WLFQD]Dest ML54224i ---
19	NL						STORE	[WLFQD]Src ILA842j SCHY1~Feedback torque/thrust	[WLFQD]Dest ML54256i ---
20	NL						STORE	[WLFQD]Src ILB042j BKPBY1~Feedback torque/thrust	[WLFQD]Dest ML54288i ---
21	NL						STORE	[WLFQD]Src ILB842j ---	[WLFQD]Dest ML54320i ---
22	NL						STORE	[WLFQD]Src ILC042j ---	[WLFQD]Dest ML54352i ---

