

```

00001      ** DL Register Area - 120Word
00002      **
00003      ** DW00000 - DW00009 (PLS Use)
00004      ** DW00010 - DW00039 (Bit Use)
00005      ** DW00040 - DW00089 (Word Use)
00006      ** DW00090 - DW00119 (Timer)
00007      ****
00008
00009      "# Program Name      : [Move] Cutter Z
00010      "# Functionior      :
00011      "# Call Program     :
00012      "# Sub Program      :
00013      "# Func Program     :
00014
00015      VAR;
00016      " Scribe Z
00017 00000      LONG IDX_CZ = 34;
00018      END_VAR;
00019
00020 00001      PLD [CZ];
00021 00002      VEL [CZ]ML43412;
00022
00023 00003      DW00002 = MW04842          " Motion Code Write
00024 00004      IOW DW00002 <> 0;
00025
00026 00005      SFORK   DW00002 == 1 ? LBL01      " #1 [CZ] Upper Cutter Z Standby Positon
00027                DW00002 == 2 ? LBL02      " #2
00028                DW00002 == 3 ? LBL03      " #3 [CZ] Upper Cutter Z Loadcell Positon
00029                DW00002 == 4 ? LBL04      " #4
00030                DW00002 == 5 ? LBL05      " #5
00031                DW00002 == 6 ? LBL06      " #6
00032                DW00002 == 7 ? LBL07      " #7
00033                DEFAULT      ? LBL100;
00034
00035 00006      LBL01:
00036
00037 00007                MW15540 = 1;          " Torque Setting
00038 00008                MW15525 = 9;          " Speed Setting
00039 00009                MSEE MPS254;
00040
00041 00010                ML16068 = ML15750      " [CZ] Cutter Z Moving Position Writ
00042 00011                MOV [CZ]ML16068;
00043 00012                IOW MB046020 == 1      " [CZ] Cutter Z Standby Pos Check
00044
00045 00013                JOINTO LBL0X;
00046
00047 00014      LBL02:
00048 00015                JOINTO LBL0X;
00049
00050 00016      LBL03:
00051
00052 00017                ML16068 = ML43454      " [CZ] Cutter Z Moving Position Writ
00053 00018                MOV [CZ] ML16068
00054 00019                IOW MB046026 == 1      " [CZ] Cutter Z Loadcell Pos Chea
00055
00056 00020                JOINTO LBL0X;
00057
00058 00021      LBL04:
00059 00022                JOINTO LBL0X;
00060
00061 00023      LBL05:
00062 00024                JOINTO LBL0X;
00063
00064 00025      LBL06:
00065 00026                JOINTO LBL0X;
00066
00067 00027      LBL07:
00068 00028                JOINTO LBL0X;
00069
00070 00029      LBL100:
00071 00030                JOINTO LBL0X;
00072 00031      LBL0X: SJOINT;
00073
00074 00032      SFORK   DW00002 == 11 ? LBL11      " #11
00075                DW00002 == 12 ? LBL12      " #12 [CZ] Cutter Z Wheel Change Align Pos (Unuse)
00076                DW00002 == 13 ? LBL13      " #13
00077                DW00002 == 14 ? LBL14      " #14
00078                DW00002 == 15 ? LBL15      " #15
00079                DW00002 == 16 ? LBL16      " #16
00080                DW00002 == 17 ? LBL17      " #17
00081                DEFAULT      ? LBL101;
00082
00083 00033      LBL11:
00084 00034                JOINTO LBL1X;
00085
00086 00035      LBL12:
00087

```

```

00088 00036      IF !MB0000F == 1;
00089 00037          ML16068 = ML43470 - 300      " [CZ] Cutter Z Moving Position Write
00090 00038          MOV [CZ]ML16068;
00091
00092          " Torque Setting
00093 00039          MW15520 = 13;      " Torque Setting
00094 00040          MW15525 = 1;      " Axis Select
00095 00041          MSEE MPS253;      " CZ Torque Set
00096
00097 00042          ML16068 = ML43470 + ML26252      " [CZ] CX Wheel Cleaning Position
00098
00099 00043          ML04852 = ML10800[IDX_CZ];
00100 00044          ML04854 = ML11000[IDX_CZ];
00101 00045          ML04856 = ML11200[IDX_CZ];
00102
00103 00046          ML04850 = ML43412 * 60;
00104
00105 00047          FMX tML04852;
00106 00048          IAC tML04854;
00107 00049          IDC tML04856;
00108
00109 00050          MVS [CZ]ML16068 FML04850;
00110 00051      IEND;
00111
00112 00052          ML16068 = ML43470      " CZ Wheel Cleaning Position
00113 00053          MOV [CZ] ML16068
00114
00115 00054          JOINTO LBL1X;
00116
00117 00055      LBL13:
00118 00056          JOINTO LBL1X;
00119
00120 00057      LBL14:
00121 00058          JOINTO LBL1X;
00122
00123 00059      LBL15:
00124 00060          JOINTO LBL1X;
00125
00126 00061      LBL16:
00127 00062          JOINTO LBL1X;
00128
00129 00063      LBL17:
00130 00064          JOINTO LBL1X;
00131
00132 00065      LBL101:
00133 00066          JOINTO LBL1X;
00134 00067      LBL1X: SJOINT;
00135
00136 00068      SFORK      DW00002 == 21 ? LBL21      "
00137                  DW00002 == 22 ? LBL22      "
00138                  DW00002 == 23 ? LBL23      "
00139                  DW00002 == 24 ? LBL24      "
00140                  DW00002 == 25 ? LBL25      "
00141                  DW00002 == 26 ? LBL26      "
00142                  DW00002 == 27 ? LBL27      "
00143                  DEFAULT      ? LBL102;
00144
00145 00069      LBL21:
00146 00070          JOINTO LBL2X;
00147
00148 00071      LBL22:
00149 00072          JOINTO LBL2X;
00150
00151 00073      LBL23:
00152 00074          JOINTO LBL2X;
00153
00154 00075      LBL24:
00155 00076          JOINTO LBL2X;
00156
00157 00077      LBL25:
00158 00078          JOINTO LBL2X;
00159
00160 00079      LBL26:
00161 00080          JOINTO LBL2X;
00162
00163 00081      LBL27:
00164 00082          JOINTO LBL2X;
00165
00166 00083      LBL102:
00167 00084          JOINTO LBL2X;
00168 00085      LBL2X: SJOINT;
00169
00170 00086      SFORK      DW00002 == 31 ? LBL31      "
00171                  DW00002 == 32 ? LBL32      "
00172                  DW00002 == 33 ? LBL33      "
00173                  DW00002 == 34 ? LBL34      "
00174                  DW00002 == 35 ? LBL35      "

```

```

00175          DW00002 == 36 ? LBL36      "
00176          DW00002 == 37 ? LBL37      "
00177          DEFAULT      ? LBL103;
00178
00179 00087      LBL31:
00180 00088          JOINTO LBL3X;
00181
00182 00089      LBL32:
00183 00090          JOINTO LBL3X;
00184
00185 00091      LBL33:
00186 00092          JOINTO LBL3X;
00187
00188 00093      LBL34:
00189 00094          JOINTO LBL3X;
00190
00191 00095      LBL35:
00192 00096          JOINTO LBL3X;
00193
00194 00097      LBL36:
00195 00098          JOINTO LBL3X;
00196
00197 00099      LBL37:
00198 00100          JOINTO LBL3X;
00199
00200 00101      LBL103:
00201 00102          JOINTO LBL3X;
00202 00103      LBL3X: SJOINT;
00203
00204 00104      SFORK   DW00002 == 41 ? LBL41      " All Cutter Z Standby Pos
00205                  DW00002 == 42 ? LBL42      " All Cutter Z Current Pos
00206                  DW00002 == 43 ? LBL43      " Cutter Z All Surface - 500um Before Position
00207                  DW00002 == 44 ? LBL44      " Cutter Z All Surface Position
00208                  DW00002 == 45 ? LBL45      " Cutter Z All Wheel Cleaning Pos
00209                  DW00002 == 46 ? LBL46      "
00210                  DW00002 == 47 ? LBL47      "
00211                  DW00002 == 48 ? LBL48      "
00212                  DW00002 == 49 ? LBL49      " Cutter Z All Surface - 500um Before Position(OffsetSet)
00213                  DW00002 == 50 ? LBL50      " Cutter Z Auto Offset Cutting Position(OffsetSet)
00214                  DEFAULT      ? LBL104;
00215
00216 00105      LBL41:
00217
00218 00106          MW15520 = 1;      " Torque Setting
00219 00107          MW15525 = 9;      " Axis Select
00220 00108          MSEE MPS253;      " CZ Torque Set
00221
00222 00109          MW15540 = 1;      " Position Setting
00223 00110          MSEE MPS254;      " CZ Position Set
00224
00225 00111          ML16068 = ML15750      " [CZ] Upper Cutter Z Moving Position Write
00226
00227 00112          IOW MB045778 == 1      " Cutter Z Move Permission
00228 00113          MOV [CZ]ML16068;
00229 00114          IOW MB045740 == 1
00230
00231 00115          JOINTO LBL4X;
00232
00233 00116      LBL42:
00234
00235 00117          ML04852 = ML10800[IDX_CZ] * 2;
00236 00118          ML04854 = ML11000[IDX_CZ];
00237 00119          ML04856 = ML11200[IDX_CZ];
00238
00239 00120          ML04850 = ML43412 * 2 * 60;
00240
00241 00121          FMX tML04852;
00242 00122          IAC tML04854;
00243 00123          IDC tML04856;
00244
00245 00124          MW15540 = 9;      " Position Setting
00246 00125          MW15525 = 9;      " Axis Select
00247 00126          MSEE MPS254;      " CZ Position Set
00248
00249 00127          ML16068 = ML15750      " [CZ] Upper Cutter Z Moving Position Write
00250
00251 00128          IOW MB045778 == 1      " All CZ Move Permission
00252
00253 00129          MVS [CZ]ML16068 FML04850 PFN;
00254
00255 00130          JOINTO LBL4X;
00256
00257 00131      LBL43:
00258
00259 00132          ML04852 = ML10800[IDX_CZ] * 2;
00260 00133          ML04854 = ML11000[IDX_CZ];
00261 00134          ML04856 = ML11200[IDX_CZ];

```

```

00262
00263 00135      ML04850 = ML43412 * 2 * 60;
00264
00265 00136      FMX tML04852;
00266 00137      IAC tML04854;
00267 00138      IDC tML04856;
00268
00269 00139      MW15520 = 1;          " Torque Setting
00270 00140      MW15525 = 9;          " Axis Select
00271 00141      MSEE MPS253;      " CZ Torque Set
00272
00273 00142      MW15540 = 7;          " Position Setting
00274 00143      MW15525 = 9;          " Axis Select
00275 00144      MSEE MPS254;      " CZ Position Set
00276
00277 00145      ML16068 = ML15750      " [CZ] Upper Cutter Z Moving Position Write
00278
00279 00146      IOW MB045778 == 1      " Cutter Z Move Permission
00280
00281 00147      MVS [CZ]ML16068 FML04850;
00282
00283 00148      JOINTO LBL4X;
00284
00285 00149      LBL44:
00286
00287 00150      ML04852 = ML10800[IDX_CZ] * 2;
00288 00151      ML04854 = ML11000[IDX_CZ];
00289 00152      ML04856 = ML11200[IDX_CZ];
00290
00291 00153      IF ML43432 <> 0;
00292 00154          ML04850 = ML43432 * 2 * 60;
00293 00155      ELSE;
00294 00156          ML04850 = ML43412 * 2 * 60
00295 00157      IEND;
00296
00297 00158      FMX tML04852;
00298 00159      IAC tML04854;
00299 00160      IDC tML04856;
00300
00301 00161      MW15520 = 8;          " Torque Setting
00302 00162      MW15525 = 9;          " Axis Select
00303 00163      MSEE MPS253;      " CZ Torque Set
00304
00305 00164      MW15540 = 8;          " Position Setting
00306 00165      MW15525 = 9;          " Axis Select
00307 00166      MSEE MPS254;      " CZ Position Set
00308
00309 00167      ML16068 = ML15750      " [CZ] Upper Cutter Z Moving Position Write
00310
00311 00168      IOW MB045778 == 1      " Cutter Z Move Permission
00312
00313 00169      MVS [CZ]ML16068 FML04850;
00314
00315 00170      JOINTO LBL4X;
00316
00317 00171      LBL45:
00318
00319 00172      ML04852 = ML10800[IDX_CZ] * 1.414;
00320 00173      ML04854 = ML11000[IDX_CZ];
00321 00174      ML04856 = ML11200[IDX_CZ];
00322
00323 00175      IF ML43432 <> 0;
00324 00176          ML04850 = ML43432 * 1.414 * 60;
00325 00177      ELSE;
00326 00178          ML04850 = ML43412 * 1.414 * 60
00327 00179      IEND;
00328
00329 00180      FMX tML04852;
00330 00181      IAC tML04854;
00331 00182      IDC tML04856;
00332
00333 00183      MW15540 = 8;          " Torque Setting
00334 00184      MW15525 = 5;          " Speed Setting
00335 00185      MSEE MPS254;
00336
00337 00186      MW15520 = 10;         " Torque Setting
00338 00187      MW15525 = 5;          " Speed Setting
00339 00188      MSEE MPS253;
00340
00341 00189      ML16068 = ML43470      " [CZ] Upper Cutter Z Moving Position Write
00342
00343 00190      MVS [CZ]ML16068 FML04850;
00344
00345 00191      IOW MB04604A == 1      " Cutter All Z Wheel Cleaning Check
00346
00347 00192      JOINTO LBL4X;
00348

```

```

00349 00193      LBL46:
00350 00194          MW15520 = 1;                " Torque Setting
00351 00195          MW15525 = 9;                " Axis Select
00352 00196          MSEE MPS253;              " CZ Torque Set
00353
00354 00197          ML15750 = ML43446          " CZ
00355
00356 00198          ML16068 = ML15750          " [CZ] Upper Cutter Z Moving Position Wri
00357
00358 00199          IOW MB045778 == 1          " Cutter Z Move Permission
00359 00200          MOV [CZ]ML16068;
00360 00201          IOW MB045743 == 1;
00361 00202          JOINTO LBL4X;
00362
00363 00203      LBL47:
00364 00204          JOINTO LBL4X;
00365
00366 00205      LBL48:
00367 00206          JOINTO LBL4X;
00368
00369 00207      LBL49:
00370
00371 00208          ML04852 = ML10800[IDX_CZ] * 1.414;
00372 00209          ML04854 = ML11000[IDX_CZ];
00373 00210          ML04856 = ML11200[IDX_CZ];
00374
00375 00211          ML04850 = ML43412 * 1.414 * 60;
00376
00377 00212          FMX tML04852;
00378 00213          IAC tML04854;
00379 00214          IDC tML04856;
00380
00381 00215          MW15520 = 1;                " Torque Setting
00382 00216          MW15525 = 9;                " Axis Select
00383 00217          MSEE MPS253;              " CZ Torque Set
00384
00385 00218          MW15540 = 7;                " Position Setting
00386 00219          MW15525 = 9;                " Axis Select
00387 00220          MSEE MPS254;              " CZ Position Set
00388
00389 00221          ML16068 = ML15750          " [CZ] Upper Cutter Z Moving Position Write
00390
00391 00222          IOW MB045778 == 1          " Cutter Z Move Permission
00392
00393 00223          MVS [CZ]ML16068 FML04850;
00394
00395 00224          JOINTO LBL4X;
00396
00397 00225      LBL50:
00398
00399 00226          ML04852 = ML10800[IDX_CZ] * 1.414;
00400 00227          ML04854 = ML11000[IDX_CZ];
00401 00228          ML04856 = ML11200[IDX_CZ];
00402
00403 00229          IF ML43432 <> 0;
00404 00230              ML04850 = ML43432 * 1.414 * 60;
00405 00231          ELSE;
00406 00232              ML04850 = ML43412 * 1.414 * 6(
00407 00233          IEND;
00408 00234          FMX tML04852;
00409 00235          IAC tML04854;
00410 00236          IDC tML04856;
00411
00412 00237          MW15520 = 10;                " Torque Setting
00413 00238          MW15525 = 9;                " Axis Select
00414 00239          MSEE MPS253;              " CZ Torque Set
00415
00416 00240          MW15540 = 10;                " Position Setting
00417 00241          MW15525 = 9;                " Axis Select
00418 00242          MSEE MPS254;              " CZ Position Se
00419
00420 00243          ML16068 = ML15750          " [CZ] Upper Cutter Z Moving Position Write
00421
00422 00244          IOW MB045778 == 1          " Cutter Z Move Permissic
00423
00424 00245          MVS [CZ]ML16068 FML04850;
00425
00426 00246          JOINTO LBL4X;
00427
00428 00247      LBL104:
00429 00248          JOINTO LBL4X;
00430 00249      LBL4X: SJOINT;
00431
00432 00250          MW04842 = 0;                " Motion Code Reset
00433
00434 00251      RET;

```