

```

00001 *****
00002 ** DL Register Area - 120Word
00003 **
00004 ** DW00000 - DW00009 (PLS Use)
00005 ** DW00010 - DW00039 (Bit Use)
00006 ** DW00040 - DW00089 (Word Use)
00007 ** DW00090 - DW00119 (Timer)
00008 *****
00009
00010 "# Program Name : Break Pusher Bar Receive (Unuse)
00011 "# Function :
00012 "# Call Program :
00013 "# Sub Program :
00014 "# Func Program
00015
00016 VAR;
00017 00000 LONG IDX_BKPBY1 = 64;
00018 00001 LONG IDX_BKPBY2 = 65;
00019 00002 LONG IDX_BKPBZ1 = 66;
00020 00003 LONG IDX_BKPBZ2 = 67;
00021 END_VAR;
00022
00023 00004 MSEE MPS270; " Break Pusher Bar Speed, Position Updat
e Set
00024
00025 " Break Pusher Bar Receive Before Position Check
00026 00005 IOW MB51011 & MB51020 == 1;
00027
00028 " Break Pusher Bar No Commanc
00029 00006 IOW MB050694 == 1;
00030
00031 " Cutter X Wait
00032 00007 IOW MB045741 == 1;
00033
00034 00008 IF MB000023 == 1;
00035 00009 MB045159 = 1; " Step Mode Next Fla
00036 00010 IOW (!MB21684D | MB20544E) | MB045013 == " Step Mode
00037 00011 MB045159 = 0; " Step Mode Next Fla
00038 00012 IEND;
00039
00040 " PTP 1 Cycle
00041 " Inner Bit Reset
00042 00013 DW00001 = 0;
00043 " Break Pusher Bar Receive Position Move
00044 00014 PFORK BKPBY1 BKPZ1;
00045
00046 BKPBY1:
00047 " Break Pusher Bar Y
00048 00015 IOW DB00011 == 1 " Break Pusher Bar Z & Break Pusher Bar
T Receive Position Moving Complete
00049 00016 IOW MB50790 & MB50791 == 1 " Cutting Table ↔ Break Pusher Bar Int
ference Check
00050 " Break Table ↔ Break Pusher Bar Inter
ference Check
00051 00017 ML16128 = ML72802 " Break Pusher Bar Y Moving Position Wri
te
00052
00053 00018 IOW MB50760 == 1 " [BKPBY] Standby Position Permission
00054
00055 00019 MOV [BKPBY1]ML16128 [BKPBY2]ML1612; " Break Pusher Bar Y Pos. Moving
00056 00020 IOW MB51000 == 1 " Break Pusher Bar Y Standby Position Co
mplete Check
00057
00058 00021 DB00010 = 1; " Break Pusher Bar Y Standby Position Mo
ving Complete
00059
00060 00022 JOINTO Label10X
00061
00062 BKPZ1:
00063 " Break Pusher Bar Z
00064 00023 IF MB51010 == 0;
00065
00066 00024 ML16132 = ML73202 " Break Pusher Bar Z1 Moving Position Wr
ite
00067
00068 00025 IOW MB50770 == 1 " Break Pusher Bar Z Standby Position Mo
ving Permission
00069
00070 00026 MOV [BKPZ1]ML16132 [BKPZ2]ML1613; " Break Pusher Bar Z Pos. Moving
00071 00027 IOW MB51020 == 1 " Break Pusher Bar Z Standby Position Co
mplete Check
00072 00028 IEND;
00073
00074 00029 IOW MB51020 == 1 " Break Pusher Bar Z Standby Position Co
mplete Check
00075
00076 00030 DB00011 = 1; " Break Pusher Bar Z Receive Position Mo

```

```

      ving Complet;
00077 00031      JOINTO Label10X;
00078
00079 00032      Label10X: PJOINT;
00080
00081 00033  RET;
```

			MPS261 : Break Pusher Bar Receive (Unuse)	P00002
--	--	--	---	--------