Diploma in Lightroom

Edit with Speed

Batch Editing Photos in Lightroom

One of the greatest things about using Lightroom to edit is the ability to apply the same settings from one photo to several others with the same lighting and exposure! This means that you can quickly and efficiently edit a session with just the click of a button.

How to Apply Edits to Multiple Photos

Once you have a photo edited just the way you like, you can add those same edits to other images from your session with the same lighting and exposure.

1. Highlight the image that you just finished editing.
2. Control/Command + Click on any other images you want to apply these settings to.
3. With multiple photos selected, choose Settings>Sync Settings from your menus.
4. Make sure the settings you want to sync are checked.

5. The changes should now be applied to all the photos you had selected.



If you want to copy and paste the adjustments to a photo per time, make sure to use the copy and paste buttons



Make sure to activate the 'auto sync' option to get faster results! First, select all your photos and use this switch below to activate the function



Edit Watermarks

In this section you can edit the text for the watermark.

In any module, choose Edit > Edit Watermarks (Windows) or Lightroom > Edit Watermarks (Mac OS).



In the box underneath the image you can see the simple watermark, you can now select that and delete it, and write anything you like. The most common thing to do is put the copyright symbol, ©, with your name or business name after it. To make the copyright character on Windows simply press the Alt key and type the number 0169, on a Mac press Option+G.

There are various sliders in the Watermark editor as well.

One allows you to change the opacity of the watermark. How opaque you make it is up to you. I like to make mine so that you can barely see it. A lot of people looking at images can find watermarks distracting, so it is something you should keep in mind when you are adding them to your images.

There are different things you can do to adjust the watermark, for example changing its position. There is also a size slider to make it bigger or smaller.

Add a Logo or Unique Watermark

In the same window that we have been using, go back to the top and select **graphic**. Directly underneath you will see Image Options where you can load your file. You can make the same changes in regards to size, opacity and location as you did with the text watermark. Make sure to use a PNG file if you want your logo to be transparent. PNG files can be created with Photoshop and they are transparent files that won't cover your photo.



Exporting your pictures

In Lightroom, you don't save photos in the traditional sense. Instead,
you *export* photos. You can export photos in various file formats suitable for a wide range of uses.
For example, you can:

- Export photos as JPEGs to share online or as TIFFs for a print publication.
- Export to a folder on a computer or to an attached or networked drive, such as a Flash drive.
- Burn the photos to a disc after exporting so you can share them on a CD or DVD.

When exporting, you can choose a photo's filename, colour space, pixel dimensions, and resolution. You can save export settings as pre-sets for reuse.

To export photos from Lightroom to a computer, hard drive, or Flash drive, follow these basic steps:

1. **Select the photos to export.**

Select photos from the Grid view or the Filmstrip

2. **Open the Export dialog box.**

Choose File > Export, or click the Export button in the Library module. Then, choose Export To > Hard Drive in the pop-up menu at the top of the Export dialog box.



The top of the Export dialog box indicates how many photos will be exported. Expandable panels provide options to rename files, select a file format, and more.

To export to a Flash drive, choose Export To > Hard Drive, and in the Export Location panel, choose Export To > Specific Folder. Then, click Choose and navigate to the Flash drive.

3. **(Optional) Choose an export pre-set.**

Lightroom has several pre-sets to make it easier to export photos to disk in specific file formats. For example, the For Email pre-set generates a 72-dpi JPEG image and automatically sends the email from Lightroom. If desired, select a pre-set from the left side of the Export dialog box and skip to step 6.

4. **Specify export options.**

Specify a destination folder, naming conventions, and other options in the various Export dialog box panels.
For example, use the File Settings panel to choose a format for your exported photos —
JPEG, PDF, TIFF, DNG, or the original format — and choose a colour space.
In the Image Sizing panel, specify how to size the image — dimensions and resolution.



The File Settings and Image Sizing panels in the Export dialog box

5. **(Optional) Save your export settings.**

To save your export settings for reuse, click Add at the bottom of the Pre-set panel on the left side of the Export dialog box.

6. **Click Export.**