




 R1

```
R1#
R1#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 50.0.0.0 255.0.0.0
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.50
R1(config)#exit
R1#
*Aug 11 16:15:33.985: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

 VPC-1

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.
```

```
VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.
```

```
Press '?' to get help.
```

```
Executing the startup file
```

```
VPC-1> ip dhcp
DDORA IP 50.0.0.51/8 GW 50.0.0.1
```

```
VPC-1> █
```



Welcome to Virtual PC Simulator, version 1.3 (0.8.1)

Dedicated to Daling.

Build time: May 7 2022 15:27:29

Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)

Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)

All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.

Source code and license can be found at vpcs.sf.net.

For more information, please visit wiki.freecode.com.cn.

Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp

DDORA IP 50.0.0.52/8 GW 50.0.0.1

VPC-2> █

 R2

```
R2#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#ip dhcp pool SALES
R2(dhcp-config)#network 192.168.2.0 255.255.255.0
R2(dhcp-config)#default-router 192.168.2.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#lease 1 2 3
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.50
R2(config)#exit
R2#
*Aug 11 16:42:53.209: %SYS-5-CONFIG_I: Configured from console by console
R2#interface ethernet0/0
    ^
% Invalid input detected at '^' marker.

R2#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#interface ethernet0/0
R2(config-if)#ip helper-address 172.16.0.1
R2(config-if)#
```

 VPC-4

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.
```

```
VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.
```

```
Press '?' to get help.
```

```
Executing the startup file
```

```
VPC-4> ip dhcp
DDORA IP 192.168.2.52/24 GW 192.168.2.1
```

```
VPC-4> █
```

