






 R1

```
R1(config)#exit
R1#
*Aug 12 10:00:55.867: %SYS-5-CONFIG_I: Configured from console by console
R1#config t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool PRODUCTION
R1(dhcp-config)#network 212.25.0.0 255.255.255.0
R1(dhcp-config)#default-router 212.25.0.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 212.25.0.1 212.25.0.50
R1(config)#exit
R1#
*Aug 12 10:07:47.903: %SYS-5-CONFIG_I: Configured from console by console
R1#config t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool MGMT
R1(dhcp-config)#network 129.23.0.0 255.255.0.0
R1(dhcp-config)#default-router 129.23.0.1
R1(dhcp-config)#dns-server
% Incomplete command.
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 129.23.0.1 129.23.0.50
R1(config)#exit
R1#
*Aug 12 10:13:22.490: %SYS-5-CONFIG_I: Configured from console by console
R1#config t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 29.0.0.0 255.0.0.0
R1(dhcp-config)#default-router 29.0.0.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 29.0.0.1 29.0.0.50
R1(config)#exit
R1#
*Aug 12 10:16:33.179: %SYS-5-CONFIG_I: Configured from console by console
R1#
```





```
R3(config-if)#exit
R3(config)#exit
R3#
*Aug 12 10:28:36.828: %SYS-5-CONFIG_I: Configured from console by console
R3#config t
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#interface ethernet0/1
R3(config-if)#ip helper-address 172.50.0.1
R3(config-if)#
```



 R4

```
R4#interface ethernet0/1
```

```
^
```

```
% Invalid input detected at '^' marker.
```


```
R4#configure terminal
```

```
Enter configuration commands, one per line.  End with CNTL/Z.
```

```
R4(config)#interface ethernet0/1
```

```
R4(config-if)#ip helper-address 172.50.0.1
```

```
R4(config-if)#
```



 R5

```
R5#configure t
Enter configuration commands, one per line.  End with CNTL/Z.
R5(config)#interface ethernet0/1
R5(config-if)#ip helper-address 172.50.0.1
R5(config-if)#
```