


PNETLab | Topology
Ask Gemini
labs.surennetwork.com/legacy/topology
Gmail
YouTube
Adobe Acrobat
ROUTER
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#
ROUTER(config)#int e 0/0
ROUTER(config-if)#ip add 50.0.0.1 255.0.0.0
ROUTER(config-if)#no sh
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#s
*Oct 15 12:43:56.308: %SYS-5-CONFIG_I: Configured from console by
ROUTER#sh ip int br
Interface IP-Address OK? Method Status
ocol
Ethernet0/0 50.0.0.1 YES manual up
Ethernet0/1 unassigned YES TFTP down
Ethernet0/2 unassigned YES TFTP down
Ethernet0/3 unassigned YES TFTP down
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
QEMU (Win)
All Control Panel Items ▸ Network Connections ▸
Search Network Connections
Local Area Connecti
General
Connection
IPv4 Connectivity:
IPv6 Connectivity:
Media State:
Duration:
Speed:
Details...
Activity
Bytes:
Properties
Local Area Connection Properties
Networking
Authentication
Connect using:
Intel(R) PRO/1000 MT Network Co
This connection uses the following items:
QoS Packet Scheduler
File and Printer Sharing for Micro
Cisco IP Communicator driver for
Internet Protocol Version 6 (TCP
Internet Protocol Version 4 (TCP
Link-Layer Topology Discovery
Link-Layer Topology Discovery
Install...
Uninstall
Description
Transmission Control Protocol/Internet
wide area network protocol that provid
across diverse interconnected network
OK
Cancel
Internet Protocol Version 4 (TCP/IPv4) Properties
General
You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.
Obtain an IP address automatically
Use the following IP address:
IP address: 50 . 0 . 0 . 10
Subnet mask: 255 . 0 . 0 . 0
Default gateway:
Obtain DNS server address automatically
Use the following DNS server addresses:
Preferred DNS server:
Alternate DNS server:
Validate settings upon exit
Advanced...
OK
Cancel
12:52 PM
Router Configuration
Physical
01 : 00 : 00
START

ROUTER
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#username sang password sara
ROUTER(config)#line console 0
ROUTER(config-line)#login local
ROUTER(config-line)#exit
ROUTER(config)#enable secret sara
ROUTER(config)#exit
ROUTER#
*Oct 15 12:59:13.169: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#exit
ROUTER con0 is now available


ROUTER
ROUTER con0 is now available
Press RETURN to get started.
User Access Verification
Username: sang
Password:
ROUTER>en
Password:
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#line vty 0 4
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#password sara
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
*Oct 15 13:01:10.774: %SYS-5-CONFIG_I: Configured from console by sang on console
ROUTER#
ROUTER#

PNETLab | Top


Router Config

Ask Gemini

labs.surennetwork.com/legacy/topology

Gmail YouTube Adobe Acrobat

Notifications



Router Configuration

Physical

01 : 00 : 00

START

QEMU (Win)

Computer

Kiwi Syslog Server Co...

50.0.0.1 - PuTTY

```
User Access Verification

Password:
ROUTER>en
Password:
ROUTER#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#exit
ROUTER#
ROUTER#
```