

```
ROUTER#
ROUTER#
ROUTER#
ROUTER#
ROUTER#conf
ROUTER#conf
ROUTER#configure ter
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#inter
ROUTER(config)#inter
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#ip address 50.0.0.1
% Incomplete command.

ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0
ROUTER(config-if)#no shut
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Aug 17 16:59:09.778: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Prot
oob1					
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	unassigned	YES	TFTP	down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

```
ROUTER#
```

```
ROUTER(config)#username console password console
ROUTER(config)#line console 0
ROUTER(config-line)#password testconsole
ROUTER(config-line)#login
ROUTER(config-line)#ex
% Ambiguous command: "ex"
ROUTER(config-line)#exit
ROUTER(config)#line vty 0 4
ROUTER(config-line)#tran
ROUTER(config-line)#transport tel
ROUTER(config-line)#transport teln
ROUTER(config-line)#transport telnet input
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#password telnet
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
*Aug 17 17:48:32.522: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
Interface                IP-Address      OK? Method Status  Prot
ocol
Ethernet0/0               50.0.0.1        YES manual up      up
Ethernet0/1               unassigned      YES TFTP  down    down
Ethernet0/2               unassigned      YES TFTP  down    down
Ethernet0/3               unassigned      YES TFTP  down    down
ROUTER#
```

ie)
e port)
ne & password)
d test console)

ivilege mode)



ROUTER

```
ROUTER#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#inter
ROUTER(config)#interface ethe
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#ex
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#username console password console
ROUTER(config)#line console 0
ROUTER(config-line)#password testconsole
ROUTER(config-line)#login
ROUTER(config-line)#ex
% Ambiguous command: "ex"
ROUTER(config-line)#exit
ROUTER(config)#line vty 0 4
ROUTER(config-line)#tran
ROUTER(config-line)#transport tel
ROUTER(config-line)#transport teln
ROUTER(config-line)#transport telnet input
^
% Invalid input detected at '^' marker.

ROUTER(config-line)#transport input telent
^
% Invalid input detected at '^' marker.

ROUTER(config-line)#password telnet
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
*Aug 17 17:48:32.522: %SYS-5-CONFIG_I: Configured from console by console
```



QEMU (Win)



C:\ Telnet 50.0.0.1

User Access Verification

Password:

ROUTER>en

Password:

ROUTER#_

Tftp632

5:45 AM