

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

I2C2 Mode and Configuration

Mode

I2C I2C

Configuration

Reset Configuration

NVIC Settings

DMA Settings

GPIO Settings

Parameter Settings

User Constants

Configure the below parameters :

Search (Ctrl+F)

Master Features

I2C Speed Mode

Standard Mode

I2C Clock Speed (Hz)

100000

Slave Features

Clock No Stretch Mode

Disabled

Primary Address Length selection

7-bit

Dual Address Acknowledged

Disabled

Primary slave address


0

General Call address detection

Disabled

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Slave Mode

Trigger Source

☒ Internal Clock

Channel1

Channel2

Channel3

Channel4

Combined Channels

☐ XOR activation

☐ One Pulse Mode

Configuration

Reset Configuration

☒ User Constants☒ NVIC Settings☒ DMA Settings☒ Parameter Settings

Configure the below parameters :

Search (Ctrl+F)

Counter Settings

Prescaler (PSC - 16 bits value) 7199

Counter Mode Up

Counter Period (AutoReload Regist.. 4999

Internal Clock Division (CKD) No Division

auto-reload preload Disable


Trigger Output (TRGO) Parameters

Master/Slave Mode (MSM bit) Disable (Trigger input effect not delayed)

Trigger Event Selection Reset (UG bit from TIMx_EGR)

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Slave Mode DisableTrigger Source Disable☒ Internal ClockChannel1 DisableChannel2 DisableChannel3 DisableChannel4 DisableCombined Channels Disable☐ XOR activation☐ One Pulse Mode

Configuration


Reset Configuration

☒ User Constants☒ NVIC Settings☒ DMA Settings☒ Parameter Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM2 Mode and Configuration

Mode

Slave Mode

Trigger Source

Clock Source

Channel1

Channel2

Channel3

Channel4

Combined Channels

☐ Use ETR as Clearing Source☐ XOR activation☐ One Pulse Mode

Configuration

Reset Configuration

NVIC Settings

DMA Settings

GPIO Settings


Parameter Settings

User Constants

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM2 global interrupt	☐	0	0

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

GPIO Mode and Configuration

Configuration

Group By Peripherals



GPIO



I2C



TIM

Search Signals

Search (Ctrl+F)

☐ Show only Modified Pins

Pin N...	Signal on...	GPIO out...	GPIO mo...	GPIO Pul...	Maximum...	User Label	Modified
PA3	n/a	n/a	Input mode	Pull-up	n/a		☒
PA4	n/a	n/a	Input mode	Pull-up	n/a		☒
PA5	n/a	n/a	Input mode	Pull-up	n/a		☒

 Select Pins from table to configure them. Multiple selection is Allowed.

Pinout view

System view

