PlanetFixedModel

5.3

Generated by Doxygen 1.8.14

# **Contents**

1	Mod	lule Index	1
	1.1	Modules	1
2	Nam	nespace Index	3
	2.1	Namespace List	3
3	Hier	archical Index	5
	3.1	Class Hierarchy	5
4	Data	a Structure Index	7
	4.1	Data Structures	7
5	File	Index	9
	5.1	File List	9
6	Mod	lule Documentation	11
	6.1	Models	11
		6.1.1 Detailed Description	11
	6.2	Utils	12
		6.2.1 Detailed Description	12
	6.3	PlanetFixed	13
		6.3.1 Detailed Description	13
	6.4	NorthEastDown	14
		6.4.1 Detailed Description	14
	6.5	PlanetFixedPosn	15
		6.5.1 Detailed Description	15

ii CONTENTS

7	Nam	espace	Documer	ntation	17
	7.1	jeod N	amespace	Reference	17
		7.1.1	Detailed	Description	17
8	Data	Struct	ure Docur	mentation	19
	8.1	jeod::A	ltLatLong	State Class Reference	19
		8.1.1	Detailed	Description	19
		8.1.2	Construc	ctor & Destructor Documentation	20
			8.1.2.1	AltLatLongState()	20
			8.1.2.2	~AltLatLongState()	20
		8.1.3	Member	Function Documentation	20
			8.1.3.1	get_data()	20
			8.1.3.2	set_data()	20
		8.1.4	Friends A	And Related Function Documentation	21
			8.1.4.1	init_attrjeodAltLatLongState	21
			8.1.4.2	InputProcessor	21
		8.1.5	Field Do	cumentation	21
			8.1.5.1	altitude	21
			8.1.5.2	latitude	22
			8.1.5.3	longitude	22
	8.2	jeod::N	lorthEastD	Oown Class Reference	22
		8.2.1	Detailed	Description	23
		8.2.2	Member	Enumeration Documentation	23
			8.2.2.1	AltLatLongType	23
		8.2.3	Construc	ctor & Destructor Documentation	24
			8.2.3.1	NorthEastDown() [1/2]	24
			8.2.3.2	~NorthEastDown()	24
			8.2.3.3	NorthEastDown() [2/2]	24
		8.2.4	Member	Function Documentation	24
			8.2.4.1	build_ned_orientation()	24
			8.2.4.2	operator=()	25

CONTENTS

		8.2.4.3	set_ned_trans_states()	. 25
		8.2.4.4	update_from_cart()	. 25
		8.2.4.5	update_from_ellip()	. 26
		8.2.4.6	update_from_spher()	. 27
	8.2.5	Friends A	And Related Function Documentation	. 27
		8.2.5.1	init_attrjeodNorthEastDown	. 27
		8.2.5.2	InputProcessor	. 27
	8.2.6	Field Do	cumentation	. 28
		8.2.6.1	altlatlong_type	. 28
		8.2.6.2	ned_frame	. 28
8.3	jeod::F	PlanetFixed	dMessages Class Reference	. 28
	8.3.1	Detailed	Description	. 29
	8.3.2	Construc	ctor & Destructor Documentation	. 29
		8.3.2.1	PlanetFixedMessages() [1/2]	. 29
		8.3.2.2	PlanetFixedMessages() [2/2]	. 29
	8.3.3	Member	Function Documentation	. 29
		8.3.3.1	operator=()	. 29
	8.3.4	Friends A	And Related Function Documentation	. 30
		8.3.4.1	init_attrjeodPlanetFixedMessages	. 30
		8.3.4.2	InputProcessor	. 30
	8.3.5	Field Do	cumentation	. 30
		8.3.5.1	domain_error	. 30
		8.3.5.2	invalid_request	. 30
8.4	jeod::F	PlanetFixed	dPosition Class Reference	. 31
	8.4.1	Detailed	Description	. 32
	8.4.2	Construc	ctor & Destructor Documentation	. 32
		8.4.2.1	PlanetFixedPosition()	. 32
		8.4.2.2	~PlanetFixedPosition()	. 32
	8.4.3	Member	Function Documentation	. 32
		8.4.3.1	cart_to_ellip()	. 33

iv CONTENTS

			8.4.3.2	cart_to_spher()	33
			8.4.3.3	ellip_to_cart()	33
			8.4.3.4	get_elliptic_parameters()	33
			8.4.3.5	initialize()	33
			8.4.3.6	spher_to_cart()	34
			8.4.3.7	update_from_cart()	34
			8.4.3.8	update_from_ellip()	34
			8.4.3.9	update_from_spher()	35
		8.4.4	Friends A	And Related Function Documentation	35
			8.4.4.1	init_attrjeodPlanetFixedPosition	35
			8.4.4.2	InputProcessor	35
		8.4.5	Field Doo	cumentation	36
			8.4.5.1	cart_coords	36
			8.4.5.2	ellip_coords	36
			8.4.5.3	Max_iteration_limit	36
			8.4.5.4	planet	37
			8.4.5.5	Small_radius_limit	37
			8.4.5.6	sphere_coords	37
9	Eilo	Dooum	entation		39
3	9.1			e.cc File Reference	
	9.1	9.1.1		Description	
	9.2			e.hh File Reference	
	9.2	9.2.1		Description	
	9.3			ns.hh File Reference	
	9.3	9.3.1		Description	
	9.4			•	40
	9.4	9.4.1		n.cc File Reference	
	9.5			Description	
	9.5	9.5.1			
	0.6			Description	
	9.6			ssages.cc File Reference	
		9.6.1		Description	
		9.6.2	9.6.2.1	efinition Documentation	
	9.7	planet		MAKE_PLANETFIXED_MESSAGE_CODE	42
	9.7	9.7.1		Description	
	0.0				
	9.8	9.8.1		Sn.cc File Reference	42
	0.0			•	
	9.9	9.9.1		Sn.hh File Reference	
		ا .y. ا	Detailed	Description	43
In	dev				45

# **Module Index**

# 1.1 Modules

Here is a list of all modules:

Models	11
Utils	12
PlanetFixed	13
NorthEastDown	14
PlanetFixedPosn	15

2 Module Index

# Namespace Index

2.1	Namespace	Liat	ŀ.
<i>/</i>	Namesnace	1 18	ı
<b>6</b>	HUIIICONUCC		

Here is a lis	st of all namespaces with brief descriptions:	
jeod	Namespace jeod	17

4 Namespace Index

# **Hierarchical Index**

# 3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

jeod::AltLatLongState								 												19
jeod::PlanetFixedMessage	s .							 											2	28
jeod::PlanetFixedPosition								 											3	31
jeod::NorthEastDown																			. :	22

6 Hierarchical Index

# **Data Structure Index**

# 4.1 Data Structures

Here are the data structures with brief descriptions:

jeod::AltLatLongState	
Specifies positional state in planetary altitude, latitude, and longitude	19
jeod::NorthEastDown	
Defines a local North-East-Down reference frame	22
jeod::PlanetFixedMessages	
Specifies the message IDs used in the gravity model	28
jeod::PlanetFixedPosition	
Contains various representations of position with respect to a planet	31

8 Data Structure Index

# File Index

# 5.1 File List

Here is a list of all files with brief descriptions:

alt_lat_long_state.cc	
AltLatLongState class methods	39
alt_lat_long_state.hh	
Basic orthogonal Altitude-Latitude-Longitude state definition	39
class_declarations.hh	
Forward declarations of classes defined in planet-fixed position model header files	40
north_east_down.cc	
NorthEastDown class methods	40
north_east_down.hh	
Implementation of the North-East-Down reference frame	41
planet_fixed_messages.cc	
Implement the class PlanetFixedMessages	41
planet_fixed_messages.hh	
Define the class PlanetFixedMessages, the class that specifies the message IDs used in the	
planet-fixed model	42
planet_fixed_posn.cc	
Define PlanetFixedPosition class methods	42
planet_fixed_posn.hh	
Planet centered fixed position model: alternate coordinate system definitions and transforma-	
tions to those coordinate systems	43

10 File Index

# **Module Documentation**

6.1 Models

Modules

• Utils

6.1.1 Detailed Description

12 Module Documentation

# 6.2 Utils

# Modules

PlanetFixed

# 6.2.1 Detailed Description

6.3 PlanetFixed

# 6.3 PlanetFixed

# Modules

- NorthEastDown
- PlanetFixedPosn

# 6.3.1 Detailed Description

14 Module Documentation

# 6.4 NorthEastDown

# **Files**

• file north\_east\_down.hh

Implementation of the North-East-Down reference frame.

• file north\_east\_down.cc

NorthEastDown class methods.

# **Namespaces**

• jeod

Namespace jeod.

# 6.4.1 Detailed Description

6.5 PlanetFixedPosn 15

## 6.5 PlanetFixedPosn

## **Files**

• file alt\_lat\_long\_state.hh

Basic orthogonal Altitude-Latitude-Longitude state definition.

· file class\_declarations.hh

Forward declarations of classes defined in planet-fixed position model header files.

· file planet\_fixed\_messages.hh

Define the class PlanetFixedMessages, the class that specifies the message IDs used in the planet-fixed model.

• file planet\_fixed\_posn.hh

Planet centered fixed position model: alternate coordinate system definitions and transformations to those coordinate systems.

• file alt\_lat\_long\_state.cc

AltLatLongState class methods.

• file planet\_fixed\_messages.cc

Implement the class PlanetFixedMessages.

• file planet\_fixed\_posn.cc

Define PlanetFixedPosition class methods.

## **Namespaces**

• jeod

Namespace jeod.

# 6.5.1 Detailed Description

16 Module Documentation

# **Namespace Documentation**

# 7.1 jeod Namespace Reference

Namespace jeod.

## **Data Structures**

· class AltLatLongState

Specifies positional state in planetary altitude, latitude, and longitude.

class NorthEastDown

Defines a local North-East-Down reference frame.

• class PlanetFixedMessages

Specifies the message IDs used in the gravity model.

• class PlanetFixedPosition

Contains various representations of position with respect to a planet.

# 7.1.1 Detailed Description

Namespace jeod.

# **Data Structure Documentation**

# 8.1 jeod::AltLatLongState Class Reference

Specifies positional state in planetary altitude, latitude, and longitude.

```
#include <alt_lat_long_state.hh>
```

#### **Public Member Functions**

- AltLatLongState ()=default
- virtual ~AltLatLongState ()=default
- void set\_data (double alt, double lat, double lon)

Allow user to set member data.

void get\_data (double &alt, double &lat, double &lon)

Allow user to get member data.

#### **Data Fields**

• double altitude {}

An object's height above the reference surface of the local GravBody.

double latitude {}

An object's north-south angular offset from the local GravBody's reference equator.

• double longitude {}

An object's east-west angular offset from the local GravBody's reference prime meridian.

#### **Friends**

- · class InputProcessor
- void init\_attrjeod\_\_AltLatLongState ()

## 8.1.1 Detailed Description

Specifies positional state in planetary altitude, latitude, and longitude.

Definition at line 77 of file alt\_lat\_long\_state.hh.

## 8.1.2 Constructor & Destructor Documentation

## 8.1.2.1 AltLatLongState()

```
jeod::AltLatLongState::AltLatLongState ( ) [default]
```

### 8.1.2.2 ~AltLatLongState()

```
virtual jeod::AltLatLongState::~AltLatLongState ( ) [virtual], [default]
```

#### 8.1.3 Member Function Documentation

#### 8.1.3.1 get\_data()

Allow user to get member data.

#### **Parameters**

out	alt_out	Altitude
		Units: M
out	lat_out	Longitude
		Units: r
out	lon_out	Latitude
		Units: r

Definition at line 55 of file alt\_lat\_long\_state.cc.

References altitude, latitude, and longitude.

#### 8.1.3.2 set\_data()

Allow user to set member data.

#### **Parameters**

in	alt	Altitude
		Units: M
in	lat	Longitude
		Units: r
in	lon	Latitude
		Units: r

Definition at line 41 of file alt\_lat\_long\_state.cc.

References altitude, latitude, and longitude.

Referenced by jeod::PlanetFixedPosition::update\_from\_ellip(), and jeod::PlanetFixedPosition::update\_from\_complex spher().

#### 8.1.4 Friends And Related Function Documentation

### 8.1.4.1 init\_attrjeod\_\_AltLatLongState

```
void init_attrjeod__AltLatLongState ( ) [friend]
```

#### 8.1.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 79 of file alt\_lat\_long\_state.hh.

### 8.1.5 Field Documentation

### 8.1.5.1 altitude

```
double jeod::AltLatLongState::altitude {}
```

An object's height above the reference surface of the local GravBody.

trick\_units(m)

Definition at line 84 of file alt\_lat\_long\_state.hh.

Referenced by jeod::PlanetFixedPosition::cart\_to\_ellip(), jeod::PlanetFixedPosition::cart\_to\_spher(), jeod::Planet $\leftarrow$  FixedPosition::ellip\_to\_cart(), get\_data(), set\_data(), jeod::PlanetFixedPosition::spher\_to\_cart(), jeod::Planet $\leftarrow$  FixedPosition::update\_from\_ellip(), and jeod::PlanetFixedPosition::update\_from\_spher().

#### 8.1.5.2 latitude

```
double jeod::AltLatLongState::latitude {}
```

An object's north-south angular offset from the local GravBody's reference equator.

trick units(rad)

Definition at line 90 of file alt lat long state.hh.

Referenced by jeod::NorthEastDown::build\_ned\_orientation(), jeod::PlanetFixedPosition::cart\_to\_ellip(), jeod::PlanetFixedPosition::cart\_to\_spher(), jeod::PlanetFixedPosition::ellip\_to\_cart(), get\_data(), set\_data(), jeod::PlanetFixedPosition::update\_from\_ellip(), and jeod::PlanetFixed $\leftarrow$  Position::update\_from\_spher().

#### 8.1.5.3 longitude

```
double jeod::AltLatLongState::longitude {}
```

An object's east-west angular offset from the local GravBody's reference prime meridian.

trick\_units(rad)

Definition at line 96 of file alt\_lat\_long\_state.hh.

Referenced by jeod::NorthEastDown::build\_ned\_orientation(), jeod::PlanetFixedPosition::cart\_to\_ellip(), jeod::PlanetFixedPosition::cart\_to\_spher(), jeod::PlanetFixedPosition::ellip\_to\_cart(), get\_data(), set\_data(), jeod::PlanetFixedPosition::update\_from\_ellip(), and jeod::PlanetFixed $\leftarrow$  Position::update\_from\_spher().

The documentation for this class was generated from the following files:

- alt\_lat\_long\_state.hh
- alt\_lat\_long\_state.cc

# 8.2 jeod::NorthEastDown Class Reference

Defines a local North-East-Down reference frame.

```
#include <north_east_down.hh>
```

Inheritance diagram for jeod::NorthEastDown:



### **Public Types**

• enum AltLatLongType { undefined = -1, spherical, elliptical }

Specifies whether the latitude is spherical or elliptical.

#### **Public Member Functions**

- NorthEastDown ()=default
- ~NorthEastDown () override=default
- NorthEastDown (const NorthEastDown &)=delete
- NorthEastDown & operator= (const NorthEastDown &)=delete
- void update from cart (const double cart[3]) override

Update from Cartesian position input.

void update\_from\_spher (const AltLatLongState &spher) override

Update from Spherical position input.

• void update\_from\_ellip (const AltLatLongState &ellip) override

Update from Elliptical position input.

virtual void build ned orientation ()

Build NED frame state based on current reference point information.

• virtual void set\_ned\_trans\_states (const double pos[3], const double vel[3])

Build NED frame state based on current reference point information.

#### **Data Fields**

· RefFrame ned frame

The local North-East-Down reference frame, centered at the reference point stored in the ellip\_coords, sphere\_coords, and cart\_coords data fields inherited from PlanetFixedPosition.

AltLatLongType altlatlong\_type {undefined}

Is reference point specified in spherical or elliptical coords?

### **Friends**

- class InputProcessor
- void init\_attrjeod\_\_NorthEastDown ()

#### **Additional Inherited Members**

## 8.2.1 Detailed Description

Defines a local North-East-Down reference frame.

Definition at line 81 of file north\_east\_down.hh.

#### 8.2.2 Member Enumeration Documentation

### 8.2.2.1 AltLatLongType

enum jeod::NorthEastDown::AltLatLongType

Specifies whether the latitude is spherical or elliptical.

#### Enumerator

undefined	
spherical	
elliptical	

Definition at line 95 of file north\_east\_down.hh.

#### 8.2.3 Constructor & Destructor Documentation

```
8.2.3.1 NorthEastDown() [1/2]

jeod::NorthEastDown::NorthEastDown ( ) [default]

8.2.3.2 ~NorthEastDown()

jeod::NorthEastDown::~NorthEastDown ( ) [override], [default]

8.2.3.3 NorthEastDown() [2/2]

jeod::NorthEastDown::NorthEastDown (
```

const NorthEastDown & ) [delete]

### 8.2.4 Member Function Documentation

```
8.2.4.1 build_ned_orientation()
```

```
void jeod::NorthEastDown::build_ned_orientation ( ) [virtual]
```

Build NED frame state based on current reference point information.

Definition at line 83 of file north\_east\_down.cc.

References altlatlong\_type, jeod::PlanetFixedPosition::ellip\_coords, elliptical, jeod::PlanetFixedMessages::invalid  $\leftarrow$  \_request, jeod::AltLatLongState::latitude, jeod::AltLatLongState::longitude, ned\_frame, jeod::PlanetFixedPosition  $\leftarrow$  ::sphere\_coords, and spherical.

#### 8.2.4.2 operator=()

#### 8.2.4.3 set\_ned\_trans\_states()

Build NED frame state based on current reference point information.

#### **Parameters**

in	pos	Cartesian position, PCPF Units: M
in	vel	Cartesian velocity, PCPF
		Units: M/s

Definition at line 136 of file north\_east\_down.cc.

References ned\_frame, and jeod::PlanetFixedPosition::update\_from\_cart().

### 8.2.4.4 update\_from\_cart()

Update from Cartesian position input.

#### **Parameters**

in	cart	Cartesian coords, PCPF
		Units: M

Reimplemented from jeod::PlanetFixedPosition.

Definition at line 51 of file north\_east\_down.cc.

References jeod::PlanetFixedPosition::cart\_coords, ned\_frame, and jeod::PlanetFixedPosition::update\_from\_cart().

# 8.2.4.5 update\_from\_ellip()

Update from Elliptical position input.

#### **Parameters**

in	ellip	Elliptical AltLatLong position
----	-------	--------------------------------

Reimplemented from jeod::PlanetFixedPosition.

Definition at line 73 of file north\_east\_down.cc.

References jeod::PlanetFixedPosition::cart\_coords, ned\_frame, and jeod::PlanetFixedPosition::update\_from\_ $\leftarrow$  ellip().

#### 8.2.4.6 update\_from\_spher()

Update from Spherical position input.

#### **Parameters**

in	spher	Spherical AltLatLong position
----	-------	-------------------------------

Reimplemented from jeod::PlanetFixedPosition.

Definition at line 62 of file north\_east\_down.cc.

#### 8.2.5 Friends And Related Function Documentation

#### 8.2.5.1 init attrjeod NorthEastDown

```
void init_attrjeod__NorthEastDown ( ) [friend]
```

### 8.2.5.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 83 of file north\_east\_down.hh.

#### 8.2.6 Field Documentation

#### 8.2.6.1 altlatlong\_type

AltLatLongType jeod::NorthEastDown::altlatlong\_type {undefined}

Is reference point specified in spherical or elliptical coords?

trick\_units(-)

Definition at line 112 of file north\_east\_down.hh.

Referenced by build\_ned\_orientation().

### 8.2.6.2 ned\_frame

RefFrame jeod::NorthEastDown::ned\_frame

The local North-East-Down reference frame, centered at the reference point stored in the ellip\_coords, sphere\_← coords, and cart\_coords data fields inherited from PlanetFixedPosition.

trick\_units(-)

Definition at line 90 of file north\_east\_down.hh.

Referenced by build\_ned\_orientation(),  $set_ned_trans_states()$ ,  $update_from_cart()$ ,  $update_from_ellip()$ , and  $update_from_spher()$ .

The documentation for this class was generated from the following files:

- north\_east\_down.hh
- north\_east\_down.cc

# 8.3 jeod::PlanetFixedMessages Class Reference

Specifies the message IDs used in the gravity model.

```
#include <planet_fixed_messages.hh>
```

## **Public Member Functions**

- PlanetFixedMessages ()=delete
- PlanetFixedMessages (const PlanetFixedMessages &)=delete
- PlanetFixedMessages & operator= (const PlanetFixedMessages &)=delete

#### **Static Public Attributes**

- static const char \* invalid\_request = "environment/planet\_fixed/" "invalid\_request" Issued when a selection such as an enum value is invalid.
- static const char \* domain\_error = "environment/planet\_fixed/" "domain\_error" Issued when a value is invalid such as an overly small radius.

### **Friends**

- class InputProcessor
- void init\_attrjeod\_\_PlanetFixedMessages ()

### 8.3.1 Detailed Description

Specifies the message IDs used in the gravity model.

Definition at line 83 of file planet\_fixed\_messages.hh.

#### 8.3.2 Constructor & Destructor Documentation

#### 8.3.2.1 PlanetFixedMessages() [1/2]

```
jeod::PlanetFixedMessages::PlanetFixedMessages ( ) [delete]
```

# 8.3.2.2 PlanetFixedMessages() [2/2]

# 8.3.3 Member Function Documentation

### 8.3.3.1 operator=()

### 8.3.4 Friends And Related Function Documentation

### 8.3.4.1 init\_attrjeod\_\_PlanetFixedMessages

```
void init_attrjeod__PlanetFixedMessages ( ) [friend]
```

#### 8.3.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 85 of file planet fixed messages.hh.

#### 8.3.5 Field Documentation

#### 8.3.5.1 domain\_error

```
char const * jeod::PlanetFixedMessages::domain_error = "environment/planet_fixed/" "domain_←
error" [static]
```

Issued when a value is invalid such as an overly small radius.

trick\_units(-)

Definition at line 95 of file planet\_fixed\_messages.hh.

Referenced by jeod::PlanetFixedPosition::cart\_to\_ellip(), and jeod::PlanetFixedPosition::cart\_to\_spher().

#### 8.3.5.2 invalid\_request

```
char const * jeod::PlanetFixedMessages::invalid_request = "environment/planet_fixed/" "invalid←
_request" [static]
```

Issued when a selection such as an enum value is invalid.

trick\_units(-)

Definition at line 90 of file planet\_fixed\_messages.hh.

Referenced by jeod::NorthEastDown::build\_ned\_orientation().

The documentation for this class was generated from the following files:

- planet\_fixed\_messages.hh
- planet\_fixed\_messages.cc

# 8.4 jeod::PlanetFixedPosition Class Reference

Contains various representations of position with respect to a planet.

```
#include <planet_fixed_posn.hh>
```

Inheritance diagram for jeod::PlanetFixedPosition:



#### **Public Member Functions**

- PlanetFixedPosition ()=default
- virtual ~PlanetFixedPosition ()=default
- virtual void initialize (Planet \*planet\_in)

Initialize a PlanetFixedPosition object.

virtual void update\_from\_cart (const double cart[3])

Update from Cartesian position input.

virtual void update\_from\_spher (const AltLatLongState &spher)

Update from Spherical position input.

virtual void update\_from\_ellip (const AltLatLongState &ellip)

Update from Elliptical position input.

#### **Data Fields**

• AltLatLongState ellip\_coords

An object's current position in elliptical coordinates.

• AltLatLongState sphere\_coords

The same object's current position in spherical coordinates.

• double cart\_coords [3] {}

The planet-centered, planet-fixed position of the object.

Planet \* planet {}

The planet currently associated with this.

#### **Static Public Attributes**

static constexpr double Small\_radius\_limit {1e-60}

Limit of ratio of radial distance to planet equatorial radius below which planetary coordinates are deemed to be invalid.

• static constexpr int Max\_iteration\_limit {10}

Limit of number of iterations used to solve elliptic parameters.

#### **Protected Member Functions**

void cart\_to\_spher ()

Convert from cartesian to spherical position.

void cart\_to\_ellip ()

Convert from cartesian to elliptical position.

void spher\_to\_cart ()

Convert from spherical to cartesian position.

void ellip\_to\_cart ()

Convert from elliptical to cartesian position.

• int get\_elliptic\_parameters (double r, double z, double &f, double &h, int maxIters=Max\_iteration\_limit)

# **Friends**

- · class InputProcessor
- void init\_attrjeod\_\_PlanetFixedPosition ()

# 8.4.1 Detailed Description

Contains various representations of position with respect to a planet.

Definition at line 91 of file planet\_fixed\_posn.hh.

# 8.4.2 Constructor & Destructor Documentation

# 8.4.2.1 PlanetFixedPosition()

```
jeod::PlanetFixedPosition::PlanetFixedPosition ( ) [default]
```

#### 8.4.2.2 ~PlanetFixedPosition()

```
virtual jeod::PlanetFixedPosition::~PlanetFixedPosition ( ) [virtual], [default]
```

#### 8.4.3 Member Function Documentation

#### 8.4.3.1 cart\_to\_ellip()

```
void jeod::PlanetFixedPosition::cart_to_ellip ( ) [protected]
```

Convert from cartesian to elliptical position.

Definition at line 136 of file planet\_fixed\_posn.cc.

References jeod::AltLatLongState::altitude, cart\_coords, jeod::PlanetFixedMessages::domain\_error, ellip\_coords, get\_elliptic\_parameters(), jeod::AltLatLongState::latitude, jeod::AltLatLongState::longitude, and Small\_radius\_limit.

Referenced by update\_from\_cart(), and update\_from\_spher().

#### 8.4.3.2 cart\_to\_spher()

```
void jeod::PlanetFixedPosition::cart_to_spher ( ) [protected]
```

Convert from cartesian to spherical position.

Definition at line 94 of file planet fixed posn.cc.

References jeod::AltLatLongState::altitude, cart\_coords, jeod::PlanetFixedMessages::domain\_error, jeod::AltLat ← LongState::latitude, jeod::AltLatLongState::longitude, planet, Small radius limit, and sphere coords.

Referenced by update\_from\_cart(), and update\_from\_ellip().

#### 8.4.3.3 ellip\_to\_cart()

```
void jeod::PlanetFixedPosition::ellip_to_cart ( ) [protected]
```

Convert from elliptical to cartesian position.

Definition at line 208 of file planet\_fixed\_posn.cc.

References jeod::AltLatLongState::altitude, cart\_coords, ellip\_coords, jeod::AltLatLongState::latitude, jeod::AltLatLongState::AltTatLongState::A

Referenced by update from ellip().

# 8.4.3.4 get\_elliptic\_parameters()

Definition at line 238 of file planet\_fixed\_posn.cc.

References planet.

Referenced by cart\_to\_ellip().

#### 8.4.3.5 initialize()

Initialize a PlanetFixedPosition object.

#### **Parameters**

in	planet⊷	Associated planet
	_in	

Definition at line 50 of file planet\_fixed\_posn.cc.

References planet.

#### 8.4.3.6 spher\_to\_cart()

```
void jeod::PlanetFixedPosition::spher_to_cart ( ) [protected]
```

Convert from spherical to cartesian position.

Definition at line 188 of file planet\_fixed\_posn.cc.

References jeod::AltLatLongState::altitude, cart\_coords, jeod::AltLatLongState::latitude, jeod::AltLatLongState  $\leftarrow$  ::longitude, planet, and sphere\_coords.

Referenced by update\_from\_spher().

#### 8.4.3.7 update\_from\_cart()

Update from Cartesian position input.

#### **Parameters**

in	cart	Cartesian coords, PCPF
		Units: M

Reimplemented in jeod::NorthEastDown.

Definition at line 59 of file planet\_fixed\_posn.cc.

References cart\_coords, cart\_to\_ellip(), and cart\_to\_spher().

Referenced by jeod::NorthEastDown::set\_ned\_trans\_states(), and jeod::NorthEastDown::update\_from\_cart().

#### 8.4.3.8 update\_from\_ellip()

Update from Elliptical position input.

#### **Parameters**

Reimplemented in jeod::NorthEastDown.

Definition at line 83 of file planet\_fixed\_posn.cc.

References jeod::AltLatLongState::altitude, cart\_to\_spher(), ellip\_coords, ellip\_to\_cart(), jeod::AltLatLongState::latitude, jeod::AltLatLongState::longitude, and jeod::AltLatLongState::set\_data().

Referenced by jeod::NorthEastDown::update\_from\_ellip().

#### 8.4.3.9 update\_from\_spher()

Update from Spherical position input.

#### **Parameters**

	in	spher	Spherical AltLatLong position	
--	----	-------	-------------------------------	--

Reimplemented in jeod::NorthEastDown.

Definition at line 71 of file planet\_fixed\_posn.cc.

 $References\ jeod::AltLatLongState::altitude,\ cart\_to\_ellip(),\ jeod::AltLatLongState::latitude,\ jeod::AltLatLongState::set\_data(),\ spher\_to\_cart(),\ and\ sphere\_coords.$ 

Referenced by jeod::NorthEastDown::update\_from\_spher().

#### 8.4.4 Friends And Related Function Documentation

#### 8.4.4.1 init\_attrjeod\_\_PlanetFixedPosition

```
\label{lem:cond_planet} \mbox{void init\_attrjeod\_\_PlanetFixedPosition ( ) } \mbox{ [friend]}
```

#### 8.4.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 93 of file planet\_fixed\_posn.hh.

#### 8.4.5 Field Documentation

#### 8.4.5.1 cart\_coords

```
double jeod::PlanetFixedPosition::cart_coords[3] {}
```

The planet-centered, planet-fixed position of the object.

trick\_units(m)

Definition at line 130 of file planet\_fixed\_posn.hh.

Referenced by cart\_to\_ellip(), cart\_to\_spher(), ellip\_to\_cart(), spher\_to\_cart(), jeod::NorthEastDown::update\_ $\leftarrow$  from\_cart(), update\_from\_cart(), jeod::NorthEastDown::update\_from\_ellip(), and jeod::NorthEastDown::update\_ $\leftarrow$  from spher().

#### 8.4.5.2 ellip\_coords

```
AltLatLongState jeod::PlanetFixedPosition::ellip_coords
```

An object's current position in elliptical coordinates.

Per Vallado p. 140, elliptical latitude is the angle between the equatorial plane and the surface normal on the ellipsoid at the point of interest. Similarly, elliptical longitude is assumed to be the angle between the reference meridian and the surface normal on the ellipsoid at the point of interest.trick\_units(-)

Definition at line 116 of file planet\_fixed\_posn.hh.

Referenced by jeod::NorthEastDown::build\_ned\_orientation(), cart\_to\_ellip(), ellip\_to\_cart(), and update\_from\_ $\leftarrow$  ellip().

#### 8.4.5.3 Max\_iteration\_limit

```
constexpr int jeod::PlanetFixedPosition::Max_iteration_limit {10} [static]
```

Limit of number of iterations used to solve elliptic parameters.

```
trick_io(*o) trick_units(-)
```

Definition at line 104 of file planet\_fixed\_posn.hh.

#### 8.4.5.4 planet

```
Planet* jeod::PlanetFixedPosition::planet {}
```

The planet currently associated with this.

trick units(-)

Definition at line 135 of file planet\_fixed\_posn.hh.

Referenced by cart\_to\_spher(), ellip\_to\_cart(), get\_elliptic\_parameters(), initialize(), and spher\_to\_cart().

#### 8.4.5.5 Small\_radius\_limit

```
constexpr double jeod::PlanetFixedPosition::Small_radius_limit {1e-60} [static]
```

Limit of ratio of radial distance to planet equatorial radius below which planetary coordinates are deemed to be invalid.

trick\_io(\*o) trick\_units(-)

Definition at line 99 of file planet\_fixed\_posn.hh.

Referenced by cart\_to\_ellip(), and cart\_to\_spher().

#### 8.4.5.6 sphere\_coords

```
AltLatLongState jeod::PlanetFixedPosition::sphere_coords
```

The same object's current position in spherical coordinates.

Per Vallado p. 140, spherical latitude is the angle measured at the planet's center from the equatorial plane to the point of interest. Similarly, spherical longitude is also assumed to be the angle measured at the planet's center from the reference meridian to the point of interest.trick\_units(–)

Definition at line 125 of file planet\_fixed\_posn.hh.

Referenced by jeod::NorthEastDown::build\_ned\_orientation(), cart\_to\_spher(), spher\_to\_cart(), and update\_from  $\leftarrow$  \_spher().

The documentation for this class was generated from the following files:

- planet\_fixed\_posn.hh
- planet\_fixed\_posn.cc

# **Chapter 9**

# **File Documentation**

# 9.1 alt\_lat\_long\_state.cc File Reference

AltLatLongState class methods.

```
#include "../include/alt_lat_long_state.hh"
```

# **Namespaces**

• jeod

Namespace jeod.

# 9.1.1 Detailed Description

AltLatLongState class methods.

# 9.2 alt\_lat\_long\_state.hh File Reference

Basic orthogonal Altitude-Latitude-Longitude state definition.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

# **Data Structures**

• class jeod::AltLatLongState

Specifies positional state in planetary altitude, latitude, and longitude.

# **Namespaces**

• jeod

Namespace jeod.

40 File Documentation

# 9.2.1 Detailed Description

Basic orthogonal Altitude-Latitude-Longitude state definition.

# 9.3 class\_declarations.hh File Reference

Forward declarations of classes defined in planet-fixed position model header files.

#### **Namespaces**

• jeod

Namespace jeod.

# 9.3.1 Detailed Description

Forward declarations of classes defined in planet-fixed position model header files.

# 9.4 north\_east\_down.cc File Reference

NorthEastDown class methods.

```
#include <cmath>
#include <cstdio>
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/planet_fixed/planet_fixed_posn/include/planet_fixed_messages.
hh"
#include "../include/north_east_down.hh"
```

#### **Namespaces**

jeod

Namespace jeod.

# 9.4.1 Detailed Description

NorthEastDown class methods.

# 9.5 north\_east\_down.hh File Reference

Implementation of the North-East-Down reference frame.

```
#include "utils/ref_frames/include/ref_frame.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/planet_fixed/planet_fixed_posn/include/class_declarations.
hh"
#include "utils/planet_fixed/planet_fixed_posn/include/planet_fixed_posn.
hh"
```

#### **Data Structures**

· class jeod::NorthEastDown

Defines a local North-East-Down reference frame.

#### **Namespaces**

• jeod

Namespace jeod.

#### 9.5.1 Detailed Description

Implementation of the North-East-Down reference frame.

# 9.6 planet\_fixed\_messages.cc File Reference

Implement the class PlanetFixedMessages.

```
#include "utils/message/include/make_message_code.hh"
#include "../include/planet_fixed_messages.hh"
```

#### **Namespaces**

jeod

Namespace jeod.

#### Macros

#define MAKE\_PLANETFIXED\_MESSAGE\_CODE(id) JEOD\_MAKE\_MESSAGE\_CODE(PlanetFixed 
 Messages, "environment/planet\_fixed/", id)

42 File Documentation

# 9.6.1 Detailed Description

Implement the class PlanetFixedMessages.

#### 9.6.2 Macro Definition Documentation

#### 9.6.2.1 MAKE PLANETFIXED MESSAGE CODE

Definition at line 44 of file planet\_fixed\_messages.cc.

# 9.7 planet\_fixed\_messages.hh File Reference

Define the class PlanetFixedMessages, the class that specifies the message IDs used in the planet-fixed model.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

#### **Data Structures**

class jeod::PlanetFixedMessages

Specifies the message IDs used in the gravity model.

#### **Namespaces**

• jeod

Namespace jeod.

# 9.7.1 Detailed Description

Define the class PlanetFixedMessages, the class that specifies the message IDs used in the planet-fixed model.

# 9.8 planet\_fixed\_posn.cc File Reference

Define PlanetFixedPosition class methods.

```
#include <cmath>
#include <cstddef>
#include "environment/planet/include/planet.hh"
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "../include/planet_fixed_messages.hh"
#include "../include/planet_fixed_posn.hh"
```

#### **Namespaces**

· jeod

Namespace jeod.

#### 9.8.1 Detailed Description

Define PlanetFixedPosition class methods.

# 9.9 planet\_fixed\_posn.hh File Reference

Planet centered fixed position model: alternate coordinate system definitions and transformations to those coordinate systems.

```
#include "environment/planet/include/class_declarations.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "alt_lat_long_state.hh"
#include "environment/planet/include/planet.hh"
```

#### **Data Structures**

· class jeod::PlanetFixedPosition

Contains various representations of position with respect to a planet.

# **Namespaces**

• jeod

Namespace jeod.

#### 9.9.1 Detailed Description

Planet centered fixed position model: alternate coordinate system definitions and transformations to those coordinate systems.

44 File Documentation

# Index

~AltLatLongState	jeod::PlanetFixedPosition, 33
jeod::AltLatLongState, 20	InputProcessor
~NorthEastDown	jeod::AltLatLongState, 21
jeod::NorthEastDown, 24	jeod::NorthEastDown, 27
~PlanetFixedPosition	jeod::PlanetFixedMessages, 30
jeod::PlanetFixedPosition, 32	jeod::PlanetFixedPosition, 35
,	invalid_request
alt_lat_long_state.cc, 39	jeod::PlanetFixedMessages, 30
alt_lat_long_state.hh, 39	,
AltLatLongState	jeod, 17
jeod::AltLatLongState, 20	jeod::AltLatLongState, 19
AltLatLongType	~AltLatLongState, 20
jeod::NorthEastDown, 23	AltLatLongState, 20
altitude	altitude, 21
jeod::AltLatLongState, 21	get_data, 20
altlatlong_type	init_attrjeodAltLatLongState, 21
jeod::NorthEastDown, 28	InputProcessor, 21
•	latitude, 21
build_ned_orientation	longitude, 22
jeod::NorthEastDown, 24	set data, 20
	jeod::NorthEastDown, 22
cart_coords	~NorthEastDown, 24
jeod::PlanetFixedPosition, 36	AltLatLongType, 23
cart_to_ellip	altlatlong_type, 28
jeod::PlanetFixedPosition, 32	build_ned_orientation, 24
cart_to_spher	init_attrjeodNorthEastDown, 27
jeod::PlanetFixedPosition, 33	InputProcessor, 27
class_declarations.hh, 40	ned_frame, 28
	NorthEastDown, 24
domain_error	operator=, 24
jeod::PlanetFixedMessages, 30	set_ned_trans_states, 25
	update_from_cart, 25
ellip_coords	update_from_ellip, 25
jeod::PlanetFixedPosition, 36	update_from_spher, 27
ellip_to_cart	jeod::PlanetFixedMessages, 28
jeod::PlanetFixedPosition, 33	domain error, 30
ant data	init_attrjeodPlanetFixedMessages, 30
get_data	InputProcessor, 30
jeod::AltLatLongState, 20	invalid request, 30
get_elliptic_parameters	operator=, 29
jeod::PlanetFixedPosition, 33	PlanetFixedMessages, 29
init_attrjeod_AltLatLongState	jeod::PlanetFixedPosition, 31
jeod::AltLatLongState	~PlanetFixedPosition, 32
init attrjeod NorthEastDown	cart_coords, 36
jeod::NorthEastDown, 27	cart to ellip, 32
init attrieod PlanetFixedMessages	— — ··
jeod::PlanetFixedMessages, 30	cart_to_spher, 33 ellip coords, 36
init attrieod PlanetFixedPosition	•—
<del></del>	ellip_to_cart, 33
jeod::PlanetFixedPosition, 35	get_elliptic_parameters, 33
initialize	init_attrjeodPlanetFixedPosition, 35

46 INDEX

initialize, 33 InputProcessor, 35 Max_iteration_limit, 36 planet, 36 PlanetFixedPosition, 32 Small_radius_limit, 37 spher_to_cart, 34 sphere_coords, 37 update_from_cart, 34 update_from_ellip, 34 update_from_spher, 35	jeod::NorthEastDown, 25 jeod::PlanetFixedPosition, 34 update_from_ellip jeod::NorthEastDown, 25 jeod::PlanetFixedPosition, 34 update_from_spher jeod::NorthEastDown, 27 jeod::PlanetFixedPosition, 35 Utils, 12
latitude jeod::AltLatLongState, 21 longitude jeod::AltLatLongState, 22	
MAKE_PLANETFIXED_MESSAGE_CODE     planet_fixed_messages.cc, 42  Max_iteration_limit     jeod::PlanetFixedPosition, 36  Models, 11	
ned_frame jeod::NorthEastDown, 28 north_east_down.cc, 40 north_east_down.hh, 41 NorthEastDown, 14 jeod::NorthEastDown, 24	
operator= jeod::NorthEastDown, 24 jeod::PlanetFixedMessages, 29	
planet     jeod::PlanetFixedPosition, 36 planet_fixed_messages.cc, 41     MAKE_PLANETFIXED_MESSAGE_CODE, 42 planet_fixed_messages.hh, 42 planet_fixed_posn.cc, 42 planet_fixed_posn.hh, 43 PlanetFixed, 13 PlanetFixedMessages     jeod::PlanetFixedMessages, 29 PlanetFixedPosition     jeod::PlanetFixedPosition, 32 PlanetFixedPosn, 15	
set_data     jeod::AltLatLongState, 20 set_ned_trans_states     jeod::NorthEastDown, 25 Small_radius_limit     jeod::PlanetFixedPosition, 37 spher_to_cart     jeod::PlanetFixedPosition, 34 sphere_coords     jeod::PlanetFixedPosition, 37	

update\_from\_cart