




<Ubuntu – X-RDP>

<pre>root@root:~/.vnc# apt install xrdp -y Reading package lists... Done Building dependency tree... Done Reading state information... Done The following additional packages will be installed: libpipewire-0.3-modules-xrdp pipewire-module-xrdp xorgxrdp Suggested packages: gstreamer The following NEW packages will be installed: libpipewire-0.3-modules-xrdp pipewire-module-xrdp xorgxrdp xrdp 0 upgraded, 4 newly installed, 0 to remove and 12 not upgraded. Need to get 626 kB of archives: After this operation, 3,570 kB of additional disk space will be used. Get:1 http://archive.ubuntu.com/ubuntu noble/universe amd64 xrdp amd64 0.9.24-4 [536 kB] Get:2 http://archive.ubuntu.com/ubuntu noble/universe amd64 libpipewire-0.3-modules-xrdp amd64 0.2-2 [20.6 kB] Get:3 http://archive.ubuntu.com/ubuntu noble/universe amd64 pipewire-module-xrdp all 0.2-2 [3,008 B] Get:4 http://archive.ubuntu.com/ubuntu noble/universe amd64 xorgxrdp amd64 1:0.9.19-1 [65.3 kB] Fetched 626 kB in 2s (261 kB/s) Selecting previously unselected package xrdp. (Reading database ... 24059 files and directories currently installed.) Preparing to unpack .../xrdp_0.9.24-4_amd64.deb ... Unpacking xrdp (0.9.24-4) ... Selecting previously unselected package libpipewire-0.3-modules-xrdp:amd64. Preparing to unpack .../libpipewire-0.3-modules-xrdp_0.2-2_amd64.deb ... Unpacking libpipewire-0.3-modules-xrdp:amd64 (0.2-2) ... Selecting previously unselected package pipewire-module-xrdp. Preparing to unpack .../pipewire-module-xrdp_0.2-2_all.deb ... Unpacking pipewire-module-xrdp (0.2-2) ... Selecting previously unselected package xorgxrdp. Preparing to unpack .../xorgxrdp_1:0.9.19-1_amd64.deb ... Unpacking xorgxrdp (1:0.9.19-1) ... Setting up xrdp (0.9.24-4) ... Generating 2048 bit rsa key... ssl_gen_key_xrdp1 ok Saving to /etc/xrdp/rsakeys.ini Created symlink /etc/systemd/system/multi-user.target.wants/xrdp.service → /usr/lib/systemd/system/xrdp.service. Created symlink /etc/systemd/system/multi-user.target.wants/xrdp.service → /usr/lib/systemd/system/xrdp.service. Setting up libpipewire-0.3-modules-xrdp:amd64 (0.2-2) ... Setting up xorgxrdp (1:0.9.19-1) ... Setting up pipewire-module-xrdp (0.2-2) ... Processing triggers for man-db (2.12.0-4build2) ... Processing triggers for libc-bin (2.39-0ubuntu8.6) ... Scanning processes...</pre>	[1단계: xrdp 설치] apt install xrdp -y															
<pre>root@root:~/.vnc# systemctl start xrdp</pre>	[2단계: xrdp 켜기] root@root:~/.vnc# systemctl enable xrdp root@root:~/.vnc# systemctl start xrdp															
<pre>root@root:~/.vnc# adduser xrdp ssl-cert info: Adding user 'xrdp' to group 'ssl-cert' ... root@root:~/.vnc#</pre> <table><tr><td>tt1</td><td>ff02::1</td><td>ip6-allrouters</td><td>ip6-loopback</td><td>root</td></tr><tr><td>fe00::0</td><td>ff02::2</td><td>ip6-localhost</td><td>ip6-mcastprefix</td><td></td></tr><tr><td>ff00::0</td><td>ip6-allnodes</td><td>ip6-localnet</td><td>localhost</td><td></td></tr></table>	tt1	ff02::1	ip6-allrouters	ip6-loopback	root	fe00::0	ff02::2	ip6-localhost	ip6-mcastprefix		ff00::0	ip6-allnodes	ip6-localnet	localhost		[3단계: xrdp SSL 인증서 그룹에 xrdp추가] root@root:~/.vnc# adduser xrdp ssl-cert > Xrdp 서비스 사용자가 SSL 인증서에 접근할 수 있도록 ssl-cert 그룹에 추가합니다.
tt1	ff02::1	ip6-allrouters	ip6-loopback	root												
fe00::0	ff02::2	ip6-localhost	ip6-mcastprefix													
ff00::0	ip6-allnodes	ip6-localnet	localhost													
<pre>root@root:~# systemctl enable xrdp Synchronizing state of xrdp.service with SysV service script with /usr/lib/systemd/systemd-sysv-install. Executing: /usr/lib/systemd/systemd-sysv-install enable xrdp root@root:~# systemctl restart xrdp</pre>	[4단계: Xrdp 서버 재시작] root@root:~# systemctl enable xrdp root@root:~# systemctl restart xrdp															
<pre>root@root:~# echo "startplasma-x11" > ~/.xsession root@root:~# ls -al W</pre>	[선택: 데스크톱 환경 설정] echo "startplasma-x11" > ~/.xsession > (선택적 적용) Ubuntu에서 KDE Plasma 데스크톱 환경을 사용할 때 RDP 세션을 올바르게 시작하기 위해 필수적으로 필요한 설정															
 원격 데스크톱 연결	[클라이언트 확인1] 본인 PC(window)에서 원격 데스크톱 연결															

 원격 데스크톱 연결 컴퓨터(C): 172.16.254.6 사용자 이름: 지정 안 함 연결할 때 자격 증명을 묻는 메시지가 나타납니다. 옵션 표시(O) 연결(N) 도움말(H)	[클라이언트 확인2] 172.16.254.6 > 팀서버 IP로 접속
 원격 컴퓨터의 ID를 확인할 수 없습니다. 연결하시겠습니까? 보안 인증서 문제로 인해 원격 컴퓨터를 인증할 수 없습니다. 계속 진행하면 안전하지 않을 수 있습니다. 이름이 일치하지 않음 요청된 원격 컴퓨터: 172.16.254.6 원격 컴퓨터의 인증서에 있는 이름: root 인증서 오류 원격 컴퓨터의 인증서 유효성을 검사하는 동안 다음 오류가 발생했습니다. - 인증서에 있는 서버 이름이 잘못되었습니다. - 이 인증서는 신뢰할 수 있는 인증 기관에서 발급되지 않았습니다. 이러한 인증서 오류가 발생해도 연결하시겠습니까? ☐ 이 컴퓨터로의 연결을 다시 묻지 않음(O) 인증서 보기(V)... 예(Y) 아니요(N)	[클라이언트 확인3] 예(y)
 Login to root Session: Xorg username: root password: asd123!@ OK Cancel	[클라이언트 확인4] session : Xorg username : root password : asd123!@ > 위의 값입력하여 팀서버의 우분투 접속 확인!