曦智科技
PHOTONERA

LT-Simulator 授权激活用户操作流程

1. 用户首先需要从 LT-Simulator 技术支持人员获取 SN 授权码。

2. 激活授权码:（根据实际情况选取一种激活方式）
   运行环境可连通互联网，选择方式一：在线激活；
   运行环境不能连通互联网，选择方式二：离线激活。

   2.1. 方式一：在线激活

   2.1.1. 在 LT-Simulator docker 容器内执行以下操作：

   $ cd /workspace/bitanswer/

   $ ./lt-simulator__LicenseManager64

   # 根据提示依次输入字母 “A” -> “O”，然后输入 SN 授权码，回车后应激活授权成功。

   # 根据提示依次输入字母”H” -> “Q” -> “y” 退出激活程序

```
(moca_llm) root@6dcfe818166a:/workspace/bitanswer# ./lt-simulator__LicenseManager64

+-------------------------------------------------------------------+
|                License Management Tool (14.0.0.9)                 |
+-------------------------------------------------------------------+
|Product Info: lt-simulator                                         |
|Current Path: /Home                                                |
+-------------------------------------------------------------------+
|                    Not existed any SN locally !                   |
+-------------------------------------------------------------------+
|   <A>  Activate    Please get the SN from your supplier.          |
|   <S>  SetUrl      Set the address and port of the local service. |
|   <C>  CleanUrl    Clean the address and port of the local service.|
|   <D>  DevCode     Get device code.                               |
|   <Q>  Quit        Quit from the license management tool.         |
+-------------------------------------------------------------------+
| Tip: if you need to manage an existing SN, please enter the number;|
|if you need to execute other operations, please enter the letter.  |
+-------------------------------------------------------------------+
Please enter option: A

+-------------------------------------------------------------------+
|Current Path: /Home/Activate                                       |
+-------------------------------------------------------------------+
|   <O>  Online      Over the Internet.                             |
|   <F>  Offline     Unable to connect to the network.              |
|   <B>  Back        Back to previous page.                         |
|   <H>  Home        Back to Home page.                             |
+-------------------------------------------------------------------+
Please enter option: O
Enter SN: XXXXXXXXXXXXX
```

```
Press any key to continue...
|   <H>  Home        Back to Home page.                             |
+-------------------------------------------------------------------+
Please enter option: H
+-------------------------------------------------------------------+
|   <A>  Activate    Please get the SN from your supplier.          |
|   <S>  SetUrl      Set the address and port of the local service. |
|   <C>  CleanUrl    Clean the address and port of the local service.|
|   <D>  DevCode     Get device code.                               |
|   <Q>  Quit        Quit from the license management tool.         |
+-------------------------------------------------------------------+
| Tip: if you need to manage an existing SN, please enter the number;|
|if you need to execute other operations, please enter the letter.  |
+-------------------------------------------------------------------+
Please enter option: Q
Are you sure to quit? (y/n) y
Quit successfully!
```

2.2. 方式二：离线激活

对于运行环境不能直接联网的用户，可以使用离线操作方式进行激活。

2.2.1. 产生请求文件

在 LT-Simulator docker 容器内执行以下操作：

$ cd /workspace/bitanswer/

$ ./lt-simulator__LicenseManager64

根据提示依次输入字母 “A” -> “F”, -> “R”, 然后输入 SN 授权码，回车后产生一个.req 请求文件，此请求文件需导出到一台可以联网的机器（或将.req 文件内容 copy 到可以联网的机器）。

根据提示依次输入字母”H” -> “Q” -> “y” 退出激活程序

```
(moca_llm) root@d735b58aefd6:/workspace/bitanswer# ./lt-simulator__LicenseManager64

+-----------------------------------------------------------------+
|                License Management Tool (14.0.0.9)               |
+-----------------------------------------------------------------+
|Product Info: lt-simulator                                       |
|Current Path: /Home                                              |
+-----------------------------------------------------------------+
|                    Not existed any SN locally !                 |
+-----------------------------------------------------------------+
|   <A>  Activate    Please get the SN from your supplier.        |
|   <S>  SetUrl      Set the address and port of the local service.|
|   <C>  CleanUrl    Clean the address and port of the local service.|
|   <D>  DevCode     Get device code.                             |
|   <Q>  Quit        Quit from the license management tool.       |
+-----------------------------------------------------------------+
| Tip: if you need to manage an existing SN, please enter the number;|
|if you need to execute other operations, please enter the letter.|
+-----------------------------------------------------------------+
Please enter option: A

+-----------------------------------------------------------------+
|Current Path: /Home/Activate                                     |
+-----------------------------------------------------------------+
|   <O>  Online      Over the Internet.                           |
|   <F>  Offline     Unable to connect to the network.            |
|   <B>  Back        Back to previous page.                       |
|   <H>  Home        Back to Home page.                           |
+-----------------------------------------------------------------+
Please enter option: F

+-----------------------------------------------------------------+
|Current Path: /Home/Activate/Offline                             |
+-----------------------------------------------------------------+
|   <R>  Request     Get the activation request file.             |
|   <A>  Apply       Apply the activation file.                   |
|   <B>  Back        Back to previous page.                       |
|   <H>  Home        Back to Home page.                           |
+-----------------------------------------------------------------+
Please enter option: R
Enter SN: [redacted]
Get request file successfully! Please send it to ISV.
File name: /workspace/bitanswer/20251119084045[redacted].req
Press any key to continue...
```

2.2.2. 产生授权升级文件

用户可以选择一台可以联网的机器登录用户授权中心，根据请求文件以获得升级文件。

用户授权中心的网址是： https://user.bitanswer.cn/，需要输入授权码进行登录。

登录成功后，点击左侧的“离线升级”，有以下两种方式产生授权升级文件.

- 方式一：通过“选择文件”找到之前步骤产生的.req 请求文件，再点击“上传”，上传成功后，会生成升级文件；
- 方式二：点击“手工输入”，拷贝并粘贴输入之前产生的 .req 请求文件文本内容，点击“确认”，确认成功后，会生成升级文件；

可“下载”升级文件（.upd），或直接拷贝升级文件内容并保存成*.upd 文件到 LT-Simulator 容器内/workspace/bitanswer/下，以备后续进行导入。



2.2.3. 应用升级文件

在 LT-Simulator docker 容器内再次执行./lt-simulator__LicenseManager64,

根据提示依次输入字母“A”-> “F”-> “A”，输入升级文件(*.udp)的名称并回车，即可完成离线激活操作;

根据提示依次输入字母”H” -> “Q” -> “y” 退出激活程序.

离线操作会产生一个确认文件，在升级出错 时，可以通过该文件将出错信息反馈给技术支持。

```
(moca_llm) root@d735b58aefd6:/workspace/bitanswer# ./lt-simulator__LicenseManager64

+-----------------------------------------------------------------+
|                License Management Tool (14.0.0.9)               |
+-----------------------------------------------------------------+
|Product Info: lt-simulator                                       |
|Current Path: /Home                                              |
+-----------------------------------------------------------------+
|                    Not existed any SN locally !                 |
+-----------------------------------------------------------------+
|   <A>  Activate    Please get the SN from your supplier.        |
|   <S>  SetUrl      Set the address and port of the local service.|
|   <C>  CleanUrl    Clean the address and port of the local service.|
|   <D>  DevCode     Get device code.                             |
|   <Q>  Quit        Quit from the license management tool.       |
+-----------------------------------------------------------------+
| Tip: if you need to manage an existing SN, please enter the number;|
|if you need to execute other operations, please enter the letter.|
+-----------------------------------------------------------------+
Please enter option: A

+-----------------------------------------------------------------+
|Current Path: /Home/Activate                                     |
+-----------------------------------------------------------------+
|   <O>  Online      Over the Internet.                           |
|   <F>  Offline     Unable to connect to the network.            |
|   <B>  Back        Back to previous page.                       |
|   <H>  Home        Back to Home page.                           |
+-----------------------------------------------------------------+
Please enter option: F

+-----------------------------------------------------------------+
|Current Path: /Home/Activate/Offline                             |
+-----------------------------------------------------------------+
|   <R>  Request     Get the activation request file.             |
|   <A>  Apply       Apply the activation file.                   |
|   <B>  Back        Back to previous page.                       |
|   <H>  Home        Back to Home page.                           |
+-----------------------------------------------------------------+
Please enter option: A
Input file name: test_xxx.upd
Apply successfully!
The Update Confirm File has been generated in current directory.
File name: /workspace/bitanswer/20251118083953_confirm_code.rpt
Press any key to continue...
```

3. 授权升级、转移、删除

对于已经激活的授权码，输入要操作的授权码前面的编号，可以选择对授权码进行升级 （U）、转移（K）、删除（R）三个操作。升级、转移操作步骤参考前面的授权码激活。删除 是将选择的授权码的授权信息从本地删除，已经激活的授权码仍然被这台机器占用。如图：

```
+-----------------------------------------------------------------+
|                        License Management Tool                  |
+-----------------------------------------------------------------+
|Product Info: TestCAD2021                                        |
|Current Path: /Home                                              |
+-----------------------------------------------------------------+
|   No.  |        SN        |     Exp.Date     |    Attribute    | Status |
+--------+------------------+------------------+-----------------+--------+
|   <1>  |   ONTN****YT6Y   |                  |    Revocable    |        |
+-----------------------------------------------------------------+
|   <A>  Activate    Please get the SN from your supplier.        |
|   <D>  Dev-code    Get device code.                             |
|   <Q>  Quit        Quit from the license management tool.       |
+-----------------------------------------------------------------+
| Tip: if you need to manage an existing SN, please enter the number;|
|if you need to execute other operations, please enter the letter.|
+-----------------------------------------------------------------+
Please enter option: 1

+-----------------------------------------------------------------+
|Current Path: /Home/ONTN6YS3RA3NYT6Y                             |
+-----------------------------------------------------------------+
|   <U>  Update      Update SN.                                   |
|   <K>  Revoke      Revoke SN.                                   |
|   <R>  Remove      Remove SN.                                   |
|   <B>  Back        Back to previous page.                       |
|   <H>  Home        Back to Home page.                           |
+-----------------------------------------------------------------+
Please enter option:
```