

# ACI Desktop User Interface Manual

BASE24-eps<sup>™</sup>



**© 2007 by ACI Worldwide, Inc. All rights reserved.**

All information contained in this documentation, as well as the software described in it, is confidential and proprietary to ACI Worldwide, Inc., or one of its subsidiaries, is subject to a license agreement, and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this documentation may be reproduced, stored in a retrieval system, or transmitted in any form or by electronic, mechanical, recording, or any other means, without the prior written permission of ACI Worldwide, Inc., or one of its subsidiaries.

ACI, ACI Worldwide, and the ACI product names used in this documentation are trademarks or registered trademarks of ACI Worldwide, Inc., or one of its subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

# Contents

---

|                                                                 |            |
|-----------------------------------------------------------------|------------|
| <b>Preface</b> .....                                            | <b>vii</b> |
| <b>Conventions Used in This Manual</b> .....                    | <b>xi</b>  |
| <b>1: Introduction</b> .....                                    | <b>1-1</b> |
| Communication Security .....                                    | 1-3        |
| User Security .....                                             | 1-4        |
| ACI Desktop Modules List .....                                  | 1-4        |
| <b>2: Getting Started and Basic Functions</b> .....             | <b>2-1</b> |
| Enable SSL for the BASE24-eps .....                             | 2-2        |
| Additional Information on the RunDesktop.bat File .....         | 2-4        |
| Connection Information .....                                    | 2-5        |
| Log In (Log On) .....                                           | 2-5        |
| Connect to a Web Server .....                                   | 2-7        |
| Display Name of the User that is Logged On to the Desktop ..... | 2-8        |
| Change a Password .....                                         | 2-8        |
| Log Out (Log Off) and Exit .....                                | 2-9        |
| User Preferences .....                                          | 2-10       |
| General Preferences .....                                       | 2-10       |
| Error Notification Preferences .....                            | 2-13       |
| Sound Preferences .....                                         | 2-14       |
| Logging (Debug and Trace) Preferences .....                     | 2-15       |
| Snapshots .....                                                 | 2-17       |
| Display Framework Version Information .....                     | 2-18       |
| <b>3: User Configuration</b> .....                              | <b>3-1</b> |
| User Security Configuration Window Usage .....                  | 3-2        |
| User Profiles .....                                             | 3-3        |
| Roles .....                                                     | 3-3        |
| Passwords and Password Groups .....                             | 3-4        |
| Security Groups .....                                           | 3-5        |
| Distributed Security Administration (DSA) .....                 | 3-7        |
| Steps to Add a User .....                                       | 3-8        |

|                                                  |            |
|--------------------------------------------------|------------|
| <b>4: User Management</b>                        | <b>4-1</b> |
| Set the Status of a User                         | 4-2        |
| Active User Session Management                   | 4-3        |
| Terminate Active User Sessions (Log off a User)  | 4-4        |
| Password Management                              | 4-5        |
| User Status Window                               | 4-6        |
| User Status Detail Properties                    | 4-7        |
| User Status Detail Example                       | 4-8        |
| User Permissions Window                          | 4-9        |
| User Status Detail Properties                    | 4-10       |
| <b>5: User Auditing</b>                          | <b>5-1</b> |
| Audit Report XML Format                          | 5-2        |
| User Audit Activity Report Process               | 5-3        |
| Example Report on the ACI Desktop                | 5-7        |
| Automated User Auditing                          | 5-9        |
| <b>6: Version Checker</b>                        | <b>6-1</b> |
| <b>7: Online Help</b>                            | <b>7-1</b> |
| Access to JavaHelp from the ACI Desktop          | 7-2        |
| With Context                                     | 7-2        |
| Without Context                                  | 7-2        |
| JavaHelp Files                                   | 7-3        |
| JavaHelp Packages                                | 7-3        |
| Helpset File                                     | 7-4        |
| How Context is Implemented in JavaHelp           | 7-5        |
| Search the Helpset for a Text String             | 7-6        |
| Custom Help Content                              | 7-7        |
| Customization of HTML Content Files              | 7-8        |
| Change the Display of Content                    | 7-9        |
| Install JavaHelp for Stand-alone Use             | 7-10       |
| <b>A: BASE24-eps Window (UI) Information</b>     | <b>A-1</b> |
| <b>B: Desktop.cfg File</b>                       | <b>B-1</b> |
| <b>C: SSL Keystore Password Manager</b>          | <b>C-1</b> |
| Sample Passwords.bin File                        | C-2        |
| Run the Password Manager from the Command Prompt | C-3        |

**SSL Keystore Password Manager *continued***

|                                                                             |                |
|-----------------------------------------------------------------------------|----------------|
| Run the Password Manager from the PswdMgrUI Window. ....                    | C-5            |
| PswdMgrUI Window .....                                                      | C-5            |
| Add a New User-Defined Password Token .....                                 | C-6            |
| Delete a User-Defined Password Token .....                                  | C-6            |
| <b>D: Open Source Software License Agreements .....</b>                     | <b>D-1</b>     |
| JDOM Java XML API .....                                                     | D-1            |
| Copyright (c) 1999 The Apache Software Foundation. All rights reserved..... | D-2            |
| Apache Jakarta Commons Net 1.3                                              |                |
| Apache Xerces C++ 2.8.0                                                     |                |
| SourceForge Piccolo XML Parser for Java .....                               | D-3            |
| ICU License - ICU 1.8.1 and later .....                                     | D-3            |
| JAVA™ 2 RUNTIME ENVIRONMENT (J2RE), VERSION 1.3                             |                |
| JAVA™ AUTHENTICATION AND AUTHORIZATION SERVICE VERSION 1.0                  |                |
| JAVAHHELP™ VERSION 2.0 .....                                                | D-4            |
| Sun Java Graphics Repository .....                                          | D-5            |
| EXOLAB Castor, Exolab Core, Open JMS .....                                  | D-5            |
| The Legion of the Bouncy Castle .....                                       | D-6            |
| STLport.....                                                                | D-7            |
| MX4J .....                                                                  | D-8            |
| Jython .....                                                                | D-9            |
| JPython .....                                                               | D-9            |
| Jetty.....                                                                  | D-10           |
| JCheckTree .....                                                            | D-13           |
| JSpinner .....                                                              | D-13           |
| <b>Index .....</b>                                                          | <b>Index-1</b> |

*ACI Worldwide, Inc.*

# Preface

---

The ACI desktop is the user access to the following ACI applications for configuration, operation, and management functions:

- BASE24-eps
- Enhanced authorization for BASE24 applications
- Transaction Security Services (TSS)
- ACI Payments Manager
- SCM
- CMS

## Audience

This manual is written for all users of the ACI desktop, primarily system administration personnel.

## Prerequisites

Readers must know basic graphical user interface (GUI) functionality and procedures, such as using hyperlinks and buttons. The ACI desktop is organized by tasks (i.e., configure, system operations, and customer management) that require basic understanding of managing payment systems and applications.

## Software

This manual documents standard processing as of its publication date. Software that is not current and custom software modifications (CSMs) may result in processing that differs from the material presented in this manual.

## Manual Summary

**Section 1, “Introduction,”** provides an overview of the ACI desktop, windows, communication security, and information about default users. Also included is information about the user interface framework and user security.

**Section 2, “Getting Started and Basic Functions,”** describes how to log on and log off and perform other functions available from the File menu.

**Section 3, “User Configuration,”** provides an overview of user security, distributed security administration (DSA), and how to configure a user of the ACI desktop.

**Section 4, “User Management,”** describes how to manage and monitor users of the ACI desktop. Includes information about user status and user permission information available on the View menu.

**Section 5, “User Auditing,”** provides an overview of user auditing of the ACI desktop, including generating audit reports.

**Section 6, “Version Checker,”** describes how the Version Checker manages and updates ACI desktop versions.

**Section 7, “Online Help,”** describes the desktop online help (JavaHelp) and how to use online help. Provides information about localizing the ACI desktop and customizing online help.

**Appendix A, “BASE24-eps Window (UI) Information,”** provides a list of each APF-Admin window and for each window the task ID, permissions, help ID, impacted data sources, ACI desktop menu access information, and server messages.

**Appendix B, “Desktop.cfg File,”** provides key-value pair information about the Desktop.cfg file.

**Appendix C, “SSL Keystore Password Manager,”** provides information about using the Password Manager to manage SSL keystore passwords.

**Appendix D, “Open Source Software License Agreements,”** provides OSS license agreements applicable to the ACI desktop.



## Publication Identification

The following information appears at the bottom of each page to identify this manual:

- ❑ Publication date (Oct-2007)
- ❑ Release and version number (R1.0v07.4)
- ❑ Publication number (CF-CS000-01ES)

*ACI Worldwide Inc.*

# Conventions Used in This Manual

---



This manual uses the symbol shown at the left to alert to cross-industry best practices information for protecting sensitive data that is stored, processed, or transmitted in ACI applications. Carefully review such information to implement compliance to cross-industry best practices for securing data.


Refer to the product-specific Security Best Practices manual for more information about configuring an ACI product to comply with cross-industry best practices.

*ACI Worldwide, Inc.*

# 1: Introduction

---

The user interface of the ACI desktop consists of distinctive areas identified below.



- 1 – The **Title Bar** displays the name of the desktop.
- 2 – The **Menu Bar** provides access to available functions and application windows.
- 3 – The **Toolbar** contains buttons for common functions, such as logon, logoff, and online help.
- 4 – The **Navigation Tree** provides a hierarchical view of the menu bar.
- 5 – The **Application Area** contains opened application windows. Note that the text “LOGGING SENSITIVE DATA” is displayed if the debugging option on the User Preferences window is set, or if tracing of client messages exchanged with the server has been activated by a system administrator.

**6** – The **Status Pane** contains informational messages about the activity between the desktop and servers. Right click on this pane to see the full detail of a message. Left click to see a list of previously received messages.

**7** – The **Icon Area** provides informational icons. Place the cursor over an icon to display a popup message.

The key component of the ACI desktop is the **user interface framework**, which is a collection of Java classes, interface applications, rules, guidelines, recommendations, and styles that are used as a template for building and supporting ACI desktop applications. The components of the user interface framework include:

- User interface clients for which common functions, such as logging on and off the desktop, are available through the File menu
- Web servers, such as WebGate  
  
Each web server is responsible for managing communication among desktop clients. Multiple web servers can be available in groups and are configured for the desktop using the local.cfg file. By defining groups, users can select web servers as applicable.
- Version Checker for automatic client version checking and updating
- Online help that is context sensitive

These components communicate with each other and with applications running on the application host server using a variety technologies. XML messages are passed to application servers on the host using Transmission Control Protocol/Internet Protocol (TCP/IP).

Hypertext Transfer Protocol Secure Sockets Layer (HTTPS) is used for ACI desktops to communicate with web servers clients.

# Communication Security

Connections among ACI desktops, web servers, and application servers on the host can be configured to be secured using Secure Sockets Layer (SSL).

Certificates are used to authenticate servers to desktop clients, and optionally authenticate clients to servers. Public key cryptography is used to encrypt messages sent among clients and servers.

**Note:** SSL is configured using SSL specific properties defined using the Application Configuration window (**System Operations > Server Management > Application**). Refer to the *ACI Java Server Framework User Guide* for more information.

The following Java™ Archive files provide the support needed for SSL:

- Jcert.jar
- Jnet.jar
- Jsse.jar
- UIFSSLKeys.jar, which contains the default keystores.

Certificates and private keys used for encryption and authentication are maintained in protected files called keystores. These files vary by application and are identified by .sto.



**Note:** Custom communication developed and implemented for TCP/IP lines outside of the ACI desktop must be secured using SSL.

## User Security

User security (USEC server) consists of the authentication of users, authorization of user activity, management of active user sessions, and the logging of user activity. The `user.security.version` property provides the USEC server version.

For authentication, an individual must provide a user ID and password. This information is checked the user security database to determine whether the individual can access the application. This authentication includes the requirement that the user ID be defined in the user security database and the password must match that recorded for the ID. In addition, the user's security group and password group restrictions are checked.

User authorization is the validating of each activity initiated by a user. During user authorization the activity initiated by a user is compared to the user's security profile, which defines the functions (i.e., Delete, Save, and View) that a user can perform. A user can only perform those functions that have been assigned to the user's profile. This ensures that a user does not perform an activity not authorized by the user's security configuration.

See section 3 (User Configuration), section 4 (User Management), and section 5 (User Auditing) for more information.

## ACI Desktop Modules List

A `modules.lst` (modules list) is included with the install of the ACI desktop. This modules list is required because it contains module identifiers related to user interface windows, or more specifically, ACI desktop functionality. If additional functionality is added to the desktop after an install, the `modules.lst` file must be updated to include the new module ID(s) pertaining to the new functionality, and the desktop must be restarted to activate the new functionality.

On NSK systems, the `modules.lst` file is located in the `<eshome>/ESWeb/ESConfig` folder.


On Unix systems, the `modules.lst` file is located in the `<eshome>/install` folder.



## 2: Getting Started and Basic Functions

---

Each desktop session is started by running the **RunDesktop.bat** batch file, which is usually configured during installation to be accessed through a shortcut located on a client desktop or a menu. For example:



After the desktop establishes contact with the applicable servers and JAR files have been downloaded (see the next page for more information), the desktop displays the Log In window for entry of a user ID (name) and password. The desktop opens after a valid user ID (name) and password combination has been provided and authenticated. The file menu functions (e.g., Configure) and windows that are presented are dependent upon the user's configuration settings.

This section discusses logging on to the desktop, connecting to web servers, setting user preferences, sending desktop snapshots, and viewing version information.

## Enable SSL for the BASE24-eps

An SSL enabled desktop has the  lock image displayed at the lower right. Use the following procedure to enable SSL for a BASE24-eps desktop.

1. Access and open the desktop.cfg (local.cfg) file.
2. Add the following line to the [Desktop] section:

```
SSLEnabled=true
```

For example:

```
[Desktop]
.....
SSLEnabled=true
Host=TomcatServerName
.....
```

3. Add the https port entry in the hosts section, setting the port to the value configured in the server's webserver configuration file. In a default deployment this is the Tomcat server.xml file. (The servlet name and port may vary by product release; match the one used in your vanilla deployment).

```
[Hosts]

TomcatServerName=<tomcat_machine_name>:8443/ESServer/
ESGenericServlet
```

4. Add the following SSL section if not already present

```
[SSL]
#
# The provider and protocol handler package need to be
# specified unless otherwise defined in the java.security
# file. They should be set to sun's implementation(s).
# Provider=com.sun.net.ssl.internal.ssl.Provider
# ProtocolHandlerPkgs=com.sun.net.ssl.internal.www.protocol
#
# If auto update is true, the specified key store file below
# will automatically be extracted by locating it in any jar
# in the classpath. This typically would come from the
# UIFSSLKeys.jar. If the keystore should not be extracted
# upon startup, then set thisproperty to false.
#

KeyStoreAutoUpdate=true
KeyStorePassword=defaultDT
KeyStore=dtKS.sto
KeyStoreType=JKS
```

5. Import the server's certificate into the keystore.
6. Restart the Desktop. You should have:
  - ❑ No URL connections errors in the desktop.err file. This means that there was a HTTP SSL connection established between the desktop and Tomcat.
  - ❑ You should see a lock icon on the right hand bottom corner of the desktop application frame. This confirms that the desktop is started with `SSLEnabled=true`
  - ❑ Logon to the desktop and test.

## Additional Information on the RunDesktop.bat File

The install program names the RunDesktop.bat file. When the RunDesktop.bat is run, it starts up a JVM and launches the VersionChecker Client program which determines whether new and updated JAR files are available from the Server Repository (see section 6 for more information). When the Version Checker is completed, the batch file calls the DesktopLauncher.exe that starts up the Desktop. The DesktopLauncher.exe also accesses a file named DesktopLauncher.lax.

For support purposes, ACI does not recommend that the above files be renamed. However, if it is desired to rename the files, the following considerations apply:


- The RunDesktop.bat file can be renamed after install. Any shortcuts pointing to this file will need to be modified to reflect the name change.
- If the DesktopLauncher.exe file is renamed, the RunDesktop.bat file will need to be modified to reflect the name change. Also, the DesktopLauncher.lax will need to be renamed to the same name as the new name for DesktopLauncher.exe.

# Connection Information

This topic provides information for logging on, concurrent sessions, connecting to a web server, changing passwords, and logging off.

## Log In (Log On)


To log in, select the Log In function located on the File menu (**File > Log In**), the Log In button (  ) on the toolbar, or navigation tree.




After a successful logon (authenticated user) the desktop provides access to those applications (windows) that system administration has assigned to the user (i.e., the permissions and permission groups of the user's profile). Each session is assigned a unique session number used for authorization purposes.

In addition to the above, session and window (UI) timeout values are initiated and tracked during a session. A timeout is a defined period of inactivity. Timeout limits are defined in the Security Groups assigned to users.

If the user name and password are not correct or the user name has been disabled or does not have valid access at the time of login, the user is not given access to the desktop. In this case a security error message (shown below) is displayed. The error message is purposely vague so not to indicate which information (name or password or both) is incorrect.




A **security warning**, such as the example below, is displayed upon a successful logon if there were one or more unsuccessful logon attempts before the successful logon.




## Concurrent Sessions

The number of **concurrent active sessions** allowed for a user is limited to a maximum as defined in the Security Group of the user's profile. A possible scenario in which a user might have concurrent active sessions is by logging on from another terminal without logging off from an active session that was started at another terminal, or in a browser session.

This version of the Session Information dialog is displayed if a user has one or more existing active sessions when logging on, and this number of sessions is fewer than the maximum number as defined in the user's Security Group.



This version of the Session Information dialog is displayed if a user upon logon has already reached the maximum number of allowed active sessions defined in the user's Security Group.



## Connect to a Web Server

During startup, the ACI desktop attempts to connect to the default (or most recently used) web server. If multiple web servers are available, a user can access the Connection window (**File > Connection**) to select an alternate. The Connection window displays a selectable list of available web servers from which one can be selected.

If the one selected accesses a different shared user security database, any existing active sessions for the user are terminated. Also, the port used must be available (i.e., not used by another system or application); otherwise, a connection error is encountered.

A system administrator can configure the list of supported hosts using the host variable in the desktop.cfg file. See Appendix B.

## Display Name of the User that is Logged On to the Desktop


To obtain the name of the user currently logged on to the ACI desktop, mouse over the user icon (  ) that is located at the bottom right of the desktop. For example:



If this icon is not displayed, access the desktop.cfg file and set the **ShowLoggedOnUser** property, which is located in the [desktop] section of the file, to true. This property can be added if it is not present. The desktop will need to be restarted if a change is made to the desktop.cfg file.

## Change a Password

To change a password, log in to the desktop and select the Change Password function (**File > Change Password**) to display the Change Password window:



Certain password restrictions and requirements apply. See section 3 for more information.



## Log Out (Log Off) and Exit

To log out, select the Log Out function located either on the File menu (**File > Log Out**), the Log Out button (  ) on the toolbar, or navigation tree.

Logging out does not close the desktop. To close the desktop, select **File > Exit**.


**Note:** A user does not need to be logged in to exit. Also, if a user exits without logging out, the user is automatically logged out from the desktop.

## User Preferences

Each user can set desktop characteristics to desired preferences by accessing **File > Preferences**. These preferences are discussed below.

### General Preferences

Use the General tab of the User Preferences window to set the following user preferences.




Descriptions of general preferences are discussed below.

| Preference                     | Description                                                                                                                                                                                                                                                                                                |
|--------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Confirm Deletes                | Indicates whether the desktop displays a confirmation dialog box before a delete function is processed.                                                                                                                                                                                                    |
| Confirm non-editable row paste | Displays a dialog box indicating that an attempt was made to paste a copied table row onto a non-editable row.                                                                                                                                                                                             |
| Confirm non-matching row paste | Displays a dialog box indicating that an attempt was made to paste a copied table row onto a table row that has a different number of table cells.                                                                                                                                                         |
| Confirm Updates                | Indicates whether the desktop displays a confirmation dialog box that requires a response before an update function is processed.                                                                                                                                                                          |
| Currency Format Locale         | Sets whether the default currency is obtained from the desktop configuration or user configuration settings.                                                                                                                                                                                               |
| Frame Open Indicator           | Indicates whether a Frame Open Indicator is displayed in the desktop toolbar while a window is opening.                                                                                                                                                                                                    |
| Language                       | <p>Displays menu functions, dialog box text, messages, and field names in the selected language, if the selected language is defined in the properties file for a window.</p> <p>This also allows access to available localized online help (online help provided in a different language or dialect).</p> |
| Navigation Tree                | Sets whether the navigation tree is displayed upon desktop startup. If checked, the navigation tree is initially displayed. If not checked, it is initially hidden.                                                                                                                                        |

| Preference               | Description                                                                                                                                                                                                                                    |
|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| New Window Position      | Sets the position of a window when opened as follows: <ul style="list-style-type: none"><li>• Bottom</li><li>• Cascaded</li><li>• Centered</li><li>• Frame specified</li><li>• Left</li><li>• Right</li><li>• Top</li><li>• Top left</li></ul> |
| Pre-Show Frame           | Indicates whether a blank window is shown while a window is initializing (being opened).                                                                                                                                                       |
| Screen Print Orientation | Sets the default print orientation to either portrait or landscape.                                                                                                                                                                            |
| Status Pane              | Indicates whether the status pane is displayed.                                                                                                                                                                                                |
| Toolbar                  | Indicates whether the toolbar is displayed.                                                                                                                                                                                                    |

## Error Notification Preferences


Use the Error Notification tab to set error notification preferences.



| Preference   | Description                                                                                                                                  |
|--------------|----------------------------------------------------------------------------------------------------------------------------------------------|
| Border Color | Sets the border color of fields that are in error.                                                                                           |
| Status       | Indicates whether error text is displayed in the status pane of windows.                                                                     |
| Tooltip      | Indicates whether error messages are displayed in tooltip text. Tooltip text is text that appears in a pop-up window over a field or button. |
| Dialog       | Indicates whether error messages are displayed in a dialog box.                                                                              |
| Trap Focus   | Makes error messages modal, that is, a user is required to resolve an error before focus can be change to another window or tab.             |

## Sound Preferences

Use the Sound tab to set the sound played during certain events (as selected in the Events field).



| Preference | Description                                                                                                                                                                                                              |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Themes     | Sets the sound group to apply to the selected event(s). Themes are defined in the sound.cfg configuration file located in the desktop.jar. The theme selected is stored in the configuration file of the logged on user. |
| Events     | An event to be associated with a sound file.                                                                                                                                                                             |
| Location   | The location of the sound file, such as a .AU file (Java) and .WAV file (Windows), to associate with the selected event.                                                                                                 |

## Logging (Debug and Trace) Preferences



Per PCI requirements, the ACI desktop will not log sensitive data to a client's computer unless configured to do so using the Logging tab of the User Preferences window.

The screenshot shows the 'User Preferences' window with the 'Logging' tab selected. The window has a title bar with 'User Preferences' and standard window controls. Below the title bar are four tabs: 'General', 'Error Notification', 'Sound', and 'Logging'. The 'Logging' tab is active and contains the following text: 'Do not enable the following logs unless instructed to do so by your system administrator. Enabling these features may cause sensitive information to be logged on your computer.' Below this text are two sections. The first section is titled 'Client Debug Log' and contains the text 'Select this option to log debugging information associated with client application processing logic.' followed by a checkbox labeled 'Debugging enabled', which is currently unchecked. The second section is titled 'Client Message Trace Log' and contains the text 'Select one of the following options to log trace records detailing messages sent to and received from the server.' followed by four radio button options: 'Trace disabled' (selected), 'Trace message headers', 'Trace full message content', and 'Trace connection and full message content'. At the bottom of the window are three buttons: 'OK', 'Reset', and 'Cancel'.

Though the User Preferences window and the Logging tab are available from the File menu and can be altered before a user logs on to the ACI desktop, the changes are only activated after the user logs on to the desktop and the user is determined to have the permission to make the change. If the user does not have permission to set debugging and trace levels, the change is not made.

## Debugging



When the Debugging enabled option is selected, debug messages are written to DeskTop.dbg debug file and the text “LOGGING SENSITIVE DATA” is displayed on the background of the application area.

**Note:** An ACI desktop user can only enable debugging if the view function of the **allowPostLogonDebug** task ID has been associated with the user’s profile.

## Trace

Three options are provided on the Logging tab for enabling tracing:

- Trace message headers
- Trace full message content
- Trace connection and full message content



If one of the above options are selected, trace messages written to the DeskTop.log file and the text “LOGGING SENSITIVE DATA” is displayed on the background of the application area. By default and per settings in the LogScrubber.cfg file, the following information is scrubbed (i.e., information is masked with ‘\*’ characters):

- Passwords
- Client IP address
- Session information

**Note:** An ACI desktop user can only set the tracing level if the view function of the **allowPostLogonTrace** task ID has be associated with the a user’s profile.



# Snapshots

Use the Send Snapshot (**File > Send Snapshot**) function to send an E-mail message (using the Send Snapshot window shown below) about the desktop configuration and a log record (DeskTop.log) of desktop activity to system administrators. The DeskTop.log file is an ASCII text file that contains information about recent desktop activity that is pertinent to system administrators.

The configuration information is sent as a comma separated values (CSV) file that can be opened by many ASCII readers and spreadsheet applications. The configuration information contains the following information:


- User ID and machine (client workstation) ID
- JAR versions installed
- Local configuration settings
- Version Checker settings
- Global configuration settings
- User preferences
- Global preferences

## Display Framework Version Information

Access **Help > About** to display desktop version information as shown below:




Click **Versions** to display detailed version information as shown below:



### 3: User Configuration

---


The ACI desktop provides access to an integrated user security environment in which each user must be defined in a user security database. This section consists of two parts: an overview of user security and steps about how to add a user. It also discusses the user profile which is central to establishing a user's access level to the ACI desktop. Each profile defines the integral components of user security, some of which, such as security and password groups, can be shared among multiple users. The hierarchy of a user profile is shown below.



**Note:** The field filters are available for servers running USEC 1.2 or higher.

## User Security Configuration Window Usage

User profiles are maintained from the ACI desktop using various user security windows. The hierarchy of a user profile from the previous page is shown below with the names and usage of the user security windows added.



All user security windows are accessed at **Configure > User Security**. A comprehensive hierarchical view of the relationships among tasks IDs, permissions, permission groups, and roles can be accessed at **View > User Permissions**.

# User Profiles

Each user is assigned a **user profile** consisting of the following configuration components:

- User ID — A unique character string used to identify a user.
- General user information — Name and contact information about a user.
- Filters — Filter IDs directly assigned to the user (for USEC 1.2 mode or higher only)
- User status — A user's status can be automatically changed (i.e., disabled) in response to some action, such as too many bad logon attempts, or by security administrative personnel.
- Role(s) — One or more sets of permission groups.
- Security group — A unique ID that defines a set of common user security access restrictions.
- Password group — A unique ID that defines a set of common user password restrictions.

## Roles

A role defines the level of a user's access to the desktop. Each role identifies a job function, such as security administrator, system administrator, manager, and end user. Roles apply a set of permissions, tasks, and functions to users.

A role can contain one or more permission groups. A permission group can contain one or more permissions. Each permission is associated with a task (window application) and defines the functions (e.g., delete, save, send, and view) allowed for that task.

## Permission Groups

A permission group is a collection of selected permissions that is assigned a unique identifier (the permission group ID) and a description of the purpose or use of the group.

## Permissions

Permissions define specific access to a window. Each permission consists of a single task (task ID), the functions that can be performed within the task, a unique ID (the permission ID), and a description of the purpose or use of the permission.

## Field Filters (for USEC 1.2 mode or higher)

Field filters restrict a user's access to field values by defining either a single value, multiple values, or a range of values allowed.

**Note:** The filter IDs available vary by application. However, a common example is to restrict a user to see only data for a single institution.

## Task IDs

Each task consists of a unique identifier and a group of functions (e.g., delete, save, send, and view) and corresponds to a window on the ACI desktop. Available task IDs and functions for each task ID are provided on the Permissions tab of the User Security Role Configuration window and are used to create permission IDs. Task IDs can be used in multiple permissions.

## Passwords and Password Groups



A user's password is stored in the user security database in encrypted form using a Secure Hash Algorithm (SHA1) that is not reversible ensuring that passwords cannot be extracted in clear form from the database.

**Note:** When a new user is added, the option to force the new user to change his or her password on first use can be selected as described in step 4.4 later in this section.

Passwords comply with Payment Card Industry complex password requirements as follows:

- Passwords are case sensitive.
- Alphabetic, numeric, and special characters are permitted.
- Password history is maintained.
- Passwords cannot be shared.

- Characters cannot be repeated sequentially. For example, a password with the string “BB” appearing anywhere in the password is not valid.
- The password cannot be the same as the user ID. For example, a user with the ID “enduser02” cannot use “enduser02” as the password.
- A user’s password must meet the requirements (discussed below) defined in the password group assigned to the user.

## Password Group Requirements

Password groups consist of password requirements that are imposed on all user passwords assigned the group. A password group consists of the following password requirements as configured using the Password Groups tab on the User Security Group Configuration window.

- The number of days prior to a password expiration on which the desktop displays a warning dialog prompting a user to change the password.
  - The maximum number of days a user can use a password.
  - The minimum password length (4 characters or more).
-  **Note:** Payment card cross-industry best practices specify a minimum length of 7 or more characters.
- The maximum password length.
  - The minimum number of numeric characters required in each password.
  - The minimum number of alphabetic characters required in each password.
  - The maximum number of old passwords retained for each user (users cannot use retained old passwords).
  - The maximum number of password changes allowed during a 24-hour period.

## Security Groups

Each user must be assigned one and only one security group. However, since a security group can be assigned to multiple users, the security group simplifies the management of user security, assigns passwords by group, and assists in implementing distributed security administration, which is discussed later in this section.

Each user security group consists of the following common user security access restrictions that apply to all users assigned the security group:

- The time each day a user can log on to the desktop.
- The time each day a user must be logged off the desktop and, after which, can no longer log on to the desktop.
- The days of the week on which a user can log on to the desktop.
- The maximum number of invalid logon attempts allowed for each user. If this value is reached, the user's status is disabled.
- The number of minutes, if set, after which the number of invalid logon attempts is reset to zero.
- The maximum number of active sessions allowed for a user.

When a user fails to log off correctly from the desktop or if a system outage occurs during a user's active session, the user security database still maintains a record of the active session. Therefore, if the maximum number of active sessions has been reached by a user attempting to log on to the desktop, the user is presented with an option to stop one or more of the active sessions.

- The number of seconds of user inactivity after which the user is automatically logged off the desktop (this is called a **session timeout**).
- The number of seconds of terminal inactivity after which the desktop is disabled and any logged on user is logged off (this is called a **UI timeout**).
- The number of days a user's ID can be inactive (not used) after which the user ID status is disabled.
- The password group ID defining password requirements applied to all users of the security group.




# Distributed Security Administration (DSA)

Each installation is configured with a system administrator and security administrator. The system administrator has access to all applications of the desktop. The security administrator has access to the user security windows. Distributed security administration involves the security administrator configuring other, lower-level, administrators that are assigned a limited set of permissions. Distributed security administration is enabled by setting the **OwnerIDSupport** property in the usec.cfg file to true.

Distributed security is implemented by the top-level security administrator by configuring applicable roles, assigning these roles as necessary to security groups, and assigning the security groups to other, lower-level, system administrators.

The top-level security administrator can set up tiers of other system administrators who are limited to a **security domain**, which is a set containing a security group, password group, roles, and permissions as defined by a security role ID. At this level, a role ID is used to restrict users within the domain to a defined set of permissions (including permission groups), tasks and filters. This methodology can be used to create system administrator groups and departments as shown in the illustration below.



For example, the system administrator assigned Role1 can create user profiles or groups of user profiles having roles that can contain only those permissions, permission groups, tasks, and filters defined for Role1. With distributed security administration, users, including administrators, cannot access the users and roles of other security domains.

## Steps to Add a User

**Note:** Some steps have additional steps (i.e., steps 3.1 – 3.3 and 4.1 – 4.5). Whether these additional steps are required depends on the extent to which a complete user security system has been configured.

- ❑ Step 1.0: Configure a Password Group
- ❑ Step 2.0: Configure a Security Group
- ❑ Step 3.0: Configure a User Role
  - Step 3.1: Configure Field Filters
  - Step 3.2: Configure Permissions
  - Step 3.3: Configure Permission Groups
- ❑ Step 4.0: Configure the User's Profile
  - Step 4.1: Set the User's Status
  - Step 4.2: Assign a Security Group
  - Step 4.3: Enter Information about the User
  - Step 4.4: Set the User's Password
  - Step 4.5: Assign Roles
  - Step 4.6: Assign Filters

**Usage Note:** To ensure that changes are implemented in the user security database, click Save (  ) each time a step has been completed.

**Tip:** If a new user is to be based on an existing user profile, that is, the password group, security group, and roles are already configured, go directly to step 4.0 and read the Tip provided in the step.

## Step 1.0: Configure a Password Group

Use the Password Group tab on the User Security Group Configuration window to configure a password group.

The screenshot shows the 'User Security Group Configuration' window with the 'Password Group' tab selected. The 'Password Gr...' dropdown is set to 'SysAdminPswdGrp'. The 'Description' field contains 'Default password params for system administrators.' Below this, there are two columns of settings, each with a label and a numeric input field with up/down arrows:

|                             |    |                      |   |
|-----------------------------|----|----------------------|---|
| Minimum Length              | 6  | Lifetime Days        | 0 |
| Maximum Length              | 16 | Old Password Cache   | 6 |
| Required Numeric Characters | 1  | Expire Pre-Warn Days | 0 |
| Required Alpha Characters   | 2  | Changes Per Day      | 6 |

In the example above, the password group **SysAdminPswdGrp** is shown. This group is described as the default password group for system administrators. The password requirements are set in the fields provided on the tab.

Password groups are assigned to users (their profiles) through security groups. Therefore, a password group must be assigned to a security group using the Security Group tab of the User Security Group Configuration window. The security group is then used in user profiles.

## Step 2.0: Configure a Security Group

Topics in this step to consider are listed below and are discussed on the following pages.

- ❑ UI and Session Timeout Considerations
- ❑ System Administration Role Filter (Owner ID)

Use the Security Group tab on the User Security Group Configuration window to configure a security group.

The screenshot shows the 'User Security Group Configuration' window with the 'Security Group' tab selected. The configuration is for the 'SysAdminSecurityGrp' security group. The description is 'Default security params for system administrators..'. The 'Password Group' is set to 'SysAdminPswdGrp' and the 'SysAdmin Profile' is empty. The 'Allowed Time and Days' section shows a time range from 08:00 am to 05:00 pm, with checkboxes for all days of the week (Sun, Mon, Tue, Wed, Thu, Fri, Sat) all checked. Below this, there are several settings with spinners: 'Bad Logins Allowed' is 4, 'Reset Bad Logins' is 300 seconds, 'Sessions Allowed' is 5, 'UI Timeout' is 1200 seconds, 'Inactive Days Allowed' is 60, and 'Session Timeout' is 0 seconds.

In the example above, the configuration for the **SysAdminSecurityGrp** security group is shown. This group defines standard authentication requirements for system administration user. The password group **SysAdminPswdGrp** is assigned to this security group. As a result, the password requirements defined by **SysAdminPswdGrp** apply to all users of this security group.

### ***UI and Session Timeout Considerations***

A security group defines both UI and session timeouts. These timeouts are defined in units of seconds using the Security Group tab of the User Security Group Configuration window.

A UI timeout occurs after a duration of desktop inactivity defined in the UI Timeout field. When a UI timeout event occurs, the user no longer has access to the desktop and any open windows; however, the user's session and the open windows are not closed but the desktop displays the Verify Password dialog in which the user must provide a valid password to restore access to the desktop and any open windows. The user also has the option to log out at this time.

**UI timeouts** only occur if the security group to which the user belongs has a configured UI timeout limit greater than zero. Entering a zero ('0') in the UI Timeout field implies no limit of desktop inactivity.

A session timeout occurs after a duration of desktop inactivity defined in the Session Timeout field. When a session timeout event occurs, the user is automatically logged off the desktop and the user must log on (open the Log In window and provide a valid user name and password combination) to obtain access to the desktop. Any windows open upon a session timeout are closed.

If the user's session expires while the Verify Password dialog is displayed and the user has not provided input, the user is still logged out and the user is no longer able to verify the password. All windows are closed, but the desktop remains open.

**Session timeouts** only occur if the security group to which the user belongs has a configured session timeout limit greater than zero. Entering a zero ('0') in the Session Timeout field implies no limit of desktop inactivity.

To use UI timeouts in an effective manner, the session timeout must be greater than the UI timeout. This is because if the session timeout is less than the UI timeout, users in the security group will be logged off the desktop (upon a session timeout event) prior to a UI timeout event.

A UI timeout event should occur first so that a user can be alerted and take necessary action to save work. Having a session timeout less than the UI timeout negates the purpose of the UI timeout.

### ***System Administration Role Filter (Owner ID)***


When the **OwnerIDSupport** property in the usec.cfg file is set to the true, the Security tab on the User Security Group Configuration window displays the SysAdmin Profile selectable field.

An existing role ID can be assigned to a security group using the SysAdmin Profile field. Since a role defines a set of permissions (permission groups), tasks IDs and field filters, the role ID at this level limits access to permissions and permission groups that can be configured for users by administrators assigned the security group. To assign a role ID as a filter for a security group, select the role ID in the SysAdmin Profile field.

If a system administration role profile is selected for a security group, only those permission groups, permissions, and tasks defined for the role are accessible to users assigned the security group.

### Step 3.0: Configure a User Role

To configure a user role, use the Roles tab on the User Security Role Configuration window.



**If the available permission groups meet existing needs**, enter or select the role ID in the Role field, add or modify the description of the purpose of the role, and select the applicable permissions groups (permission groups can be selected and deselected using the check boxes for each group), then go to Step 4.0: Configure the User's Profile. **Note:** Permissions not defined within your security domain are not available.

**If one or more permission groups need to be configured**, the following steps might also need to be performed.

- ❑ Step 3.1: Configure Field Filters
- ❑ Step 3.2: Configure Permissions
- ❑ Step 3.3: Configure Permission Groups

**Step 3.1: Configure Field Filters**

**Note:** The functionality of field filtering is the same among applications, but the implementation can vary.

Field filters are configured using the Filters tab on the User Security Role Configuration window, which is shown below, and are applied to a user's profile through permissions.

The screenshot shows the 'User Security Role Configuration' window with the 'Filters' tab selected. The window has a title bar with a red triangle icon and standard window controls. Below the title bar is a toolbar with icons for save, print, refresh, delete, and help. The main area contains the following fields and controls:

- Filter ID:** A dropdown menu with 'AllIssuer' selected.
- Field ID:** A dropdown menu with 'Issuer' selected.
- Description:** A text box containing 'All the issuers on the system.'
- Filter Type:** A group box containing three radio buttons: 'Range' (selected), 'Single Value', and 'Multi-Value'.
- Filter Settings:** A large rectangular area containing two text boxes: 'Begin Value' and 'End Value', both of which are empty.

Field filters consist of the following elements:

- ❑ Unique identification (the Filter ID field)
- ❑ Field ID
- ❑ A description of the purpose and use of the filter
- ❑ One or more field values, which can be a single value, multiple values, or a range of values.

The format of the Filter Settings area is dependent upon the filter type selected, whether Range, Single Value, or Multi-Value. In USEC 1.1 or earlier modes, the Filters tab is tied to the permission selected on the Permissions tab, and is only enabled when there is an applicable filter. In USEC 1.2 or higher modes, the filter is tied to the user or role.



If **Range** is selected, begin and end values must be entered:

The screenshot shows a dialog box titled "Filter Type" with three radio buttons: "Range" (selected), "Single Value", and "Multi-Value". Below the radio buttons is a section titled "Filter Settings" which contains two text input fields labeled "Begin Value" and "End Value".

**Caution:** Use of the Range function is discouraged because it slows processing, is difficult to audit, and allows the system to determine valid values rather than the security administrator. This function will be removed in future releases.

If **Single Value** is selected, a single filter value must be selected or entered:

The screenshot shows the same "Filter Type" dialog box, but now the "Single Value" radio button is selected. The "Filter Settings" section contains a single dropdown menu labeled "Filter Value".

The values available in the Filter Value field are those that have been configured using the applicable configuration window. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

**Tip:** Use the asterisk (“\*”) to select all current and future field values.

If **Multi-Value** is selected, values must be selected and moved from the All Field Values field to the Selected Field Values field.

To add or remove field values, use the following buttons provided on the tab to perform the desired task:

| Button                                                                              | Task                                                                                                    |
|-------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------|
|   | Add the selected field value(s) from the All Field Values field to the Selected Field Values field.     |
|  | Add all available field values from the All Field Values field to the Selected Field Values field.      |
|  | Remove the selected field(s) value from Selected Field Values field back to the All Field Values field. |
|  | Remove all field values from Selected Field Values field back to the All Field Values field.            |

To select a value, click on the value. Selected values have a modified background color. To select multiple values, press down the **Ctrl** key while selecting values.

The values shown in the All Field Values field are those that have been configured using the applicable configuration window. Use the asterisk (“\*”) to select all current and future field values. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

To add a value not available in the All Field Values field, enter the value in the text entry field to the right of the Filter Type area and click the Add Value button.

### Step 3.2: Configure Permissions

Use the Permissions tab on the User Security Role Configuration window to create permissions and permission group IDs.

The screenshot shows the 'User Security Role Configuration' window with the 'Permissions' tab selected. The window has a title bar with standard Windows controls. Below the title bar is a toolbar with icons for save, delete, and other actions. The main area contains four tabs: 'Roles', 'Permission Groups', 'Permissions' (selected), and 'Filters'. Below the tabs are three input fields: 'Permission ID' with a dropdown menu showing 'FullUSCtlPermission', 'Task ID' with a dropdown menu showing 'UserSecurityControl', and a 'Description' text box containing 'Full User Security Control permission set.'. Below these fields is a tree view under the heading 'Functions'. The tree view has a checkbox for 'Functions' which is checked, and four sub-items: 'ExpireAll', 'ExpireSelected', 'LogoutAll', and 'LogoutSelected', each with a checked checkbox. To the right of the tree view is a large empty rectangular area. At the bottom of the window is a status bar with an information icon and the text '3 - Permission read.'.

## Permission IDs

A new permission ID can be created (entered) or an existing permission ID can be selected. Permissions are available on the Permissions Group tab for selection when configuring a permission group.

The description is to state the purpose of the permission and any special information.

## Tasks IDs

Each task ID corresponds to an ACI desktop window. **Note:** Task IDs cannot be created using the ACI desktop.

## Functions

The functions that a user can perform on a window (task) are defined for each permission on the Permissions tab. A function is selected by entering a check mark in the functions check box. Functions include, but are not limited to, Delete, Save, Send, and View. The available functions vary by task ID.


## Field Filters

If a task ID refers to a window that contains a field or fields that are filterable, the Permissions tab will list the field ID(s) and provide a selectable list of filter IDs that can be selected and applied to the permission.

**Note:** The actual filterable fields varies by application. See the boxed note in step 3.1 for more information.

### Step 3.3: Configure Permission Groups

To configure a new or existing permission group, use the Permission Groups tab on the User Security Role Configuration window. This tab provides a Permission Group field in which a new permission group ID can be entered or an existing permission group can be selected.



Available permissions, as defined per your security domain, are provided on the tab. Permissions are added or removed from a permission group by selecting (entering a check mark) or deselecting (removing a check mark) in the appropriate checkbox.

## Permission Information

A description of each permission along with the Task ID assigned to the permission and the allowed functions can be displayed in the Permission Description section of the Permissions Groups tab. To display this information, right click on the desired permission and select Get Info on the pop-up menu.

## Step 4.0: Configure the User's Profile

To configure a new user (user profile), display the General tab of the User Security Profile Configuration window, enter the user's unique ID in the User ID field and perform the following steps:

- ❑ Step 4.1: Set the user's status
- ❑ Step 4.2: Assign a security group
- ❑ Step 4.3: Enter information about the user
- ❑ Step 4.4: Set the user's password
- ❑ Step 4.5: Assign roles to the user
- ❑ Step 4.6: Assign filters

**Tip:** To add a new user whose profile is based on an existing user profile, display the user profile that is to be used as a template and replace the text in the User ID field with the new user ID.

**Note:** When the Save button is clicked for a new user, the desktop displays the New User's Password window, which is described in Step 4.4.

**Step 4.1: Set the User's Status**

User status options:

|                 |                                                                                                              |
|-----------------|--------------------------------------------------------------------------------------------------------------|
| Active          | = Open and active.                                                                                           |
| Closed/Admin    | = Closed without incident.                                                                                   |
| Closed/Inactive | = Closed due to inactivity.                                                                                  |
| Disabled/Admin  | = Disabled, for security reasons, by authorized personnel.                                                   |
| Disabled/System | = Disabled automatically for security reasons<br>(e.g., maximum number of log on attempts has been reached). |
| Temporary       | = User can access the desktop for a predefined amount of time.                                               |

**Step 4.2: Assign a Security Group**

Security groups are provided in the selectable field next to the Security Group link. If a desired security group is not available, click on the link to access the User Security Group Configuration window to review existing security groups or configure a new security group. Only those security groups defined for your security domain are available.

**Step 4.3: Enter Information about the User**

Information about the user includes:

- ❑ Complete name information
- ❑ Contact information, such as phones, Fax and email address
- ❑ Employment information, such as department, manager and location

**Step 4.4: Set the User's Password**

To set a new user's password, click Save, after which the desktop displays the New User's Password window.

**Note:** The Password tab of the User Security Profile Configuration window is used for management of existing users, see the User Management section for more information.

For users assigned a status other than Temporary, the desktop displays the version of the New User's Password window shown below. Indicate whether the user must change the assigned password during the next logon (or first logon for a new user), and the start date on which the user can log on to the desktop.



The dialog box titled "New User's Password" has a blue title bar with a red triangle icon and a close button. It contains two password input fields labeled "New Password" and "Verify Password", both filled with asterisks. Below these is a checkbox labeled "Require password change" which is checked. Underneath is a date selection field labeled "New User Start" showing "Thursday, January 11, 2007". At the bottom are "Ok" and "Cancel" buttons.

When a new temporary user (i.e., user status being set to temporary) is created, the desktop displays the New User's Password window, shown below, for indicating whether the user must change the password on logging on, and for setting the start and expiration dates for which the user is active.




The dialog box titled "New User's Password" has a blue title bar with a red triangle icon and a close button. It contains two empty password input fields labeled "New Password" and "Verify Password". Below these is an unchecked checkbox labeled "Require password change". Underneath is a date selection field labeled "New User Start" showing "Thursday, January 11, 2007". Below that is another date selection field labeled "New User Expire" showing "Friday, January 11, 2008". At the bottom are "Ok" and "Cancel" buttons.



**Step 4.5: Assign Roles**

Use the Roles tab on the User Security Profile window to assign (and remove) the roles defined for a user.



This tab displays all the user roles available within your security domain on the ACI desktop. Roles not defined within your security domain are not displayed. User roles assigned to a user are shown in the User Roles field. Available user roles not assigned to a user are shown in the All Roles field. To add or remove user roles from a user profile, select the role or roles and use the buttons provided on the tab to perform the desired task. The buttons are:

| Button                                                                              | Task                                                                                                  |
|-------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------|
|  | Add the selected role(s) to the user profile (move from the All Roles field to the User Roles field). |
|  | Add all available roles to the user profile (move from the All Roles field to the User Roles field).  |

| Button                                                                            | Task                                                                                                       |
|-----------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------|
|  | Remove the selected role(s) from the user profile (move from the User Roles field to the All Roles field). |
|  | Remove all assigned roles from the user profile (move from the User Roles field to the All Roles field).   |


To select a role, click on the role. Selected roles have a modified background color. To select multiple roles, press down the **Ctrl** key while selecting roles.

If a particular role is not available or an existing role needs to be changed, click on the Configure Roles link to access the User Security Role Configuration window to configure a new or existing role.

**Note:** A user cannot change the role configuration for the profile (User ID) that was used to log on. In such situations, when the Roles tab is accessed for that User ID, the All Roles field and User Roles fields are inactive.

**Step 4.6: Assign Filters**

Use the Filters tab on the User Security Profile window to assign (and remove) the filters defined for a user.



To add or remove filters from a user profile, select the filter or filters and use the buttons provided on the tab to perform the desired task. The buttons are:

| Button                                                                              | Task                                                                                                                                                 |
|-------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------|
|  | Add the selected filter(s) to the user profile (move from the All Filters (Field ID) Filter ID field to the User Filters (FieldID) Filter ID field). |
|  | Add all available filters to the user profile (move from the All Filters (Field ID) Filter ID field to the User Filters (FieldID) Filter ID field).  |


| Button                                                                            | Task                                                                                                                                                      |
|-----------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
|  | Remove the selected filter(s) from the user profile (move from the User Filters (FieldID) Filter ID field to the All Filters (Field ID) Filter ID field). |
|  | Remove all assigned filters from the user profile (move from the User Filters (FieldID) Filter ID field to the All Filters (Field ID) Filter ID field).   |

## 4: User Management

---

Security administrators can set the status, display and terminate active sessions, and expire passwords by password group of users within the administrator's security domain. This activity is performed from the user security windows as described in this section.

The illustration below shows the user profile and includes the name of the applicable windows used to manage user profiles.



The User Security Profile Configuration window is used for configuring a user profile; however, it can be used to view a user's active sessions, to change an existing user's status and to manage a user's password.

The User Security Control Management window is used to view and manage the active sessions for all users. The window can also be used to expire passwords by password group.

To assist system administrators and other authorized users, two additional windows are available and are discussed in this section:

- User Status window
- User Permissions window

## Set the Status of a User

A user's status can be changed automatically if security and password group requirements have been violated. A user's status can also be changed by authorized users.

Use the General tab on the User Security Profile Configuration window to view and set a user's status.

**User Security Profile Configuration**

User ID: systemUser01

General | Roles | Filters | Password | Active Sessions

User Status: **Active** (dropdown menu open showing: Active, Closed/Admin, Closed/Inactive, Disabled/Admin, Disabled/System, Temporary)

Security Group: Level1SecurityGroup

First Name:

Middle Name:

Last Name:

Department:

Location:

Manager:

Email:

Work Phone:

Mobile Phone:

Fax:

Create Time: 1/11/07 1:00 PM

Last Login: 6/12/07 12:43 PM

Last Failed Login: 4/18/07 7:58 AM

Bad Login Tries: 1

Authorized users can assign the following status codes to a user:

- |                 |                                                                                                              |
|-----------------|--------------------------------------------------------------------------------------------------------------|
| Active          | = Open and active.                                                                                           |
| Closed/Admin    | = Closed without incident.                                                                                   |
| Closed/Inactive | = Closed due to inactivity.                                                                                  |
| Disabled/Admin  | = Disabled, for security reasons, by authorized personnel.                                                   |
| Disabled/System | = Disabled automatically for security reasons<br>(e.g., maximum number of log on attempts has been reached). |
| Temporary       | = User can access the desktop for a predefined amount of time.                                               |

# Active User Session Management

When a user has logged on to the desktop by providing a valid user ID and password, an active session is created for the user. An active session contains the following information:

- ❑ The user's ID.
- ❑ The unique session number assigned to the user's session.
- ❑ The workstation ID, such as a network ID or URL, from which the user has logged on to the desktop.
- ❑ The date and time the user began the session.
- ❑ The date and time the current session expires.


Information about active user sessions is available on two separate Active Sessions tabs. One tab is provided on the User Security Profile Configuration window and displays the active sessions for a selected user. The other Active Sessions tab is located on the User Security Control Management window and displays active user sessions for all users within a security administrator's security domain (security group to which the administrator has access).

Active User Session for a Selected User:

The screenshot shows a window titled "User Security Profile Configuration" with a blue header bar. Below the header is a toolbar with icons for save, print, refresh, and delete. A "User ID" dropdown menu is set to "systemUser01". Below this are five tabs: "General", "Roles", "Filters", "Password", and "Active Sessions". The "Active Sessions" tab is selected, displaying a table with two columns: "Workstation ID" and "Logged in time". The table has one row with the values "Network/URL" and "2007-6-12 12:43:11.39". Below the table is a "Password" label and a "Logout Selected" button. At the bottom of the tab area is a link labeled "All Active Sessions".

| Workstation ID | Logged in time        |
|----------------|-----------------------|
| Network/URL    | 2007-6-12 12:43:11.39 |

Active User Sessions for All Users:



**Note:** The active sessions of the application can change at any time; therefore, to update the list of active sessions, click Refresh (  ).

## Terminate Active User Sessions (Log off a User)

One or more active user sessions can be terminated (i.e., logged off) from either one of the two windows that are used to display active user sessions — the User Security Profile Configuration window and the User Security Control Management window. To log off one or more user sessions, display and select the user session(s) and click Logout Selected.



# Password Management

Authorized users can view a user's password change history, add or change a user's password, and expire the user's current password by accessing the Password tab on the User Security Profile window and selecting the user's ID.

To change a user's password, display the Password tab on the User Security Profile Configuration window and select the user ID. Enter the new password in both the New Password and Verify Password text boxes and click Save (  ). If the change is successful, a confirmation message appears in the status pane of the window. Otherwise, an appropriate error message is displayed.

To expire a user's password, display the Password tab on the User Security Profile Configuration window, select the user ID, and click Expire Password. If a user's password has been expired but a new password has not been defined, the user is prompted to create a new password on the next logon attempt.


Authorized users can access a table that shows the password groups that have been assigned to security groups, and can expire all user passwords of users assigned to a password group.

Use the Password Maintenance tab on the User Security Control Management window to view password group usage and expire password groups.

A summary of password changes for all users can be displayed on the User Status window (**View > User Status**) as discussed on the following page.

## User Status Window

The User Status window (**View > User Status**) lists summary information for users. Example User Status window:



When this window is accessed, a list of user IDs with user role and logon information is displayed.

This window allows quick identification of users with specific status exceptions and stale (i.e., idle) accounts. To identify such users, if the **More** button is active, click the button to retrieve additional users. The button remains active until all user accounts have been retrieved. The users can be sorted by logon information by clicking the **Last Logged In** column. Other columns can be used to sort the users by different criteria. A secondary sort can be obtained by holding down the CTRL key and selecting another column header.

To display a detail report for a user, select the row of the user and click **Detail**. The summary information displayed in the text area can be printed using the Print function available on the File menu.

## User Status Detail Properties



In support of PCI compliance, a recurring report of the information shown on this window can be configured using the following properties documented in the *Java Server Framework Reference Guide*:

report.userdetail.loc


report.userdetail.name

report.userdetail.timeperiod.hours

report.userdetail.starttime


## User Status Detail Example

Below is an example of the detail information available on the User Status window.



# User Permissions Window

The User Permissions window (**View > User Permissions**) provides hierarchical information for users, roles, permission groups, permissions, tasks, and field filters. Example User Permission window:



When this window is accessed, hierarchical user security information lists are provided and accessible on the various tabs of the window. For example, select the Tasks tab to identify all task IDs and the role, permissions, permission groups, and users assigned a given task.

**Note:** Distributed Security Administration filters do not apply to the information displayed on the User Permissions window. Therefore, user security access to the window should only be provided to System-level security administrators.

## User Status Detail Properties



In support of PCI compliance, a recurring report of the information shown on this window can be configured using the following properties documented in the ***Java Server Framework Reference Guide***:

report.userpermissions.loc

report.userpermissions.name

report.userpermissions.timeperiod.hours

report.userpermissions.starttime

## 5: User Auditing

---

User audit is the logging of user activity to a data source for the purpose of reporting and monitoring the user activity.

Whenever a user of the desktop initiates and completes an activity (e.g., logon, logoff, password changes, delete, or save) from a window, a message that contains information about the user activity is written to the User Audit Log data source.

The audit message sent to the log data source can be one of the following:

- Header information only about the changes to affected records
- Header information and detail information about the before and after data images of affected records

The application server writes audit messages directly to the USRAULOG data source or to the Audit\_Store\_and\_Forward data source depending on the middle ware capabilities of the hardware platform.

For information about enabling user auditing and setting the audit level for a desktop window, refer to the *ACI Java Server Framework Reference Guide* for information about audit properties, such as:

- `db.audit.db-service-name`
- `db.audited`
- `db.audited.db-service-name`

## Audit Report XML Format

The information stored in the extracted audit reports is in XML format. The following example is an XML-formatted message containing user activity information.

```
<?xml version="1.0" encoding="UTF-8" ?>
<AuditReport>
  <AuditDetails row="0">
    <Audit_LoggingRq>
      <TimeStamp>TimeStamp Info</TimeStamp>
      <ContextDescr>InsertRq</ContextDescr>
      <Ticket>
        <UserID>User Profile ID</UserID>
        <SessionNumber>1</SessionNumber>
        <TerminalID>OMAUUSER/ip_addr</TerminalID>
      </Ticket>
      <ActivityGroup>
        <ActivityType>Table Function</ActivityType>
        <TableGroup>
          <TableName>Table</TableName>
          <KeyGroup>
            <Column>
              <ColumnName>Table Element</ColumnName>
              <BeforeValue />
              <AfterValue>New Value</AfterValue>
            </Column>
            <Key>
              <KeyColumn>
                <ColumnName>Key</ColumnName>
                <AfterValue>New Value</AfterValue>
              </KeyColumn>
            </Key>
          </KeyGroup>
        </TableGroup>
      </ActivityGroup>
    </Audit_LoggingRq>
  </AuditDetails>
</AuditReport>
```


The root element of the XML message is `<AuditReport>` that includes one or more `<AuditDetails></AuditDetails>` sections. `<AuditDetails>` contains important information: a time stamp (`<TimeStamp>`), Context information (`<ContextDescr>`), ticket information (`<Ticket>`), and activity information (`<ActivityGroup>`). Information related to the user and the user's session is included in the ticket. Information about the activity performed and the data source (table) affected is included in the activity group.

**Note:** Use an XML reporting tool such as XML Spy, MS-Access 2002, or Crystal Reports to evaluate and format the XML information as well as to generate reports.



# User Audit Activity Report Process

Activity reports for selected users can be initiated by accessing User Audit on the View menu. User activity is extracted from the USRAULOG data source for a specified user ID between a start date and time and an end date and time. This information can be viewed on the ACI desktop or sent to a designated file.



The reports provide the following information:


- Date and time of action.
- User ID performing the action.
- Terminal location from which action was performed.
- Type of action performed.
- File and field name affected by the action, if applicable.
- Before and after image of data modification action, if full auditing is set.

The location where the report file is saved is specified by the **report.userauditlog.loc** environment attribute, which defines the directory location. See the previous page for an example report file.

Click **Next** to proceed.

## **Selection**

Below is the Selection step of the User Audit function.



1. Select whether to have the report sent to the screen or written to a file (the file name is specified in the next step window).
2. Click **Next**.

## Search Filter

Below is the Search Filter step of the User Audit function.

The screenshot shows a window titled "User Audit" with a sidebar on the left containing the following menu items: "Welcome", "Selection", "Search Filter" (which is highlighted with a blue arrow), and "Summary". The main area of the window is titled "Search Filter" and contains the following fields and instructions:


- Start date/time: A date field set to "October 24, 2007" and a time field set to "12:00:00 am CDT".
- End date/time: A date field set to "October 24, 2007" and a time field set to "02:25:16 pm CDT".
- User ID: A text field containing an asterisk (\*). Below it, a note says "(Specify '\*' to select all users.)".
- Extract file name: A text field containing "AudExt\_071024\_142836.xml". Below it, a note says "(The extracted report will be stored on the server.)".

At the bottom of the window, there are four buttons: "Back", "Next" (which is highlighted with a dashed border), "Cancel", and "Help".

1. Select the start and end date/time fields.
2. Enter a specific user ID or an asterisk ( \* ) to report on all users.
3. Select the file name of the extract XML report file.
4. Click **Next**.

## Summary

Below is the Summary of the User Audit function.



1. Review the summary information provided.
2. If the summary information is incorrect, click **Back** to step back through the process to make changes.
3. If the summary information is correct, click **Finish** to begin building the report, whether for screen or written to file.

## Example Report on the ACI Desktop

When a report is completed, the results are shown in the Audit Report Viewer for which an example is shown on the following page.

If the **More** button is active, click the button to retrieve additional users. Note that the **More** button remains active until all user accounts have been retrieved. The user information displayed in the table can be sorted using the column headers. Additional column headers can be selected by pressing the **Ctrl** key.

To display detail information for a user, select a summary role and click the **Detail** button. Double clicking in a summary row also initiates the display of detail information for a user.

**Audit Report Viewer**

Audit Summary

| # | Local Date/Time   | User ID      | Workstation   | Activity Type | Activity Detail   | Result | Service        |
|---|-------------------|--------------|---------------|---------------|-------------------|--------|----------------|
| 1 | Sep 21, 2007 1... | systemuser01 | oma2ui1       | Logoff        | USEC              |        |                |
| 2 | Sep 21, 2007 2... | systemuser   | SystemProcess | View          | SecurityReport... |        | USERSECURIT... |
| 3 | Sep 21, 2007 ...  | systemuser03 | oma2ui1       | Logon         | LoginComma...     | OK     | USERSECURI...  |
| 4 | Sep 21, 2007 2... | SysAdmin     | oma2ui1       | View          | ISOMsgPrflListRq  |        |                |
| 5 | Sep 21, 2007 2... | SecAdmin     | oma2ui1       | View          | InterfaceListR... |        |                |
| 6 | Sep 21, 2007 2... | systemuser07 | oma2ui1       | View          | InstConfigGetI... |        |                |

Detail More

Audit Detail

Find:

AuditReport :

- AuditDetails :
  - row : 3
    - Audit\_JoggingRq :
      - Timestamp : 2007-09-21T07:30:11.734Z
      - ContextDescr : LoginCommand
        - Ticket :
          - UserID : systemuser03
          - SessionNumber : 48
          - TerminalID : oma2ui1/172.17.1.177
        - ErrorData : OK
        - ActivityGroup :
          - ActivityType : Logon

## Automated User Auditing

User audit extracts to file can be performed automatically by specifying the `com.aciworldwide.common.timertask.UserAuditReport` classname for the configuration properties file `timertask.function.n.classname` configuration parameter. The Java Server Framework application specified as the `timertask.manager.processid` invokes the classname at application initialization.

The following properties are used to configure automated user audit reporting:

| Property                                          | Description                                                                                    |
|---------------------------------------------------|------------------------------------------------------------------------------------------------|
| <code>report.userauditlog.loc</code>              | The file path for the user audit report.                                                       |
| <code>report.userauditlog.name</code>             | The name of the user audit report.                                                             |
| <code>report.userauditlog.offset.days</code>      | The number of days prior to the current day to use for obtaining user activity for the report. |
| <code>report.userauditlog.report.starttime</code> | The time at which the report is generated.                                                     |

For example, if today is Wednesday and the time is 9:00 AM, the offset is one day, and the report start time is 2:00 AM, then the most recent audit information available is that for 2:00 AM Tuesday to 2:00 AM Wednesday.

Refer to the *ACI Java Server Framework Reference Guide* for more information about the above properties.

*ACI Worldwide Inc.*



## 6: Version Checker


---

The desktop provides a way for clients to keep the desktop configuration current. This configuration support is provided by the Version Checker, which is a utility that manages the versions of Java<sup>TM</sup> Archive (JAR) files of desktop components that are distributed to ACI desktop clients. The Version Checker automatically runs during startup of the desktop at which time it compares the current version of the client files to new versions, which reside in a predetermined location (i.e., repository). The location of the Version Checker repository is defined during installation. New files that are to be distributed to clients are placed in this location.

The Version Checker automatically runs when a desktop is started per commands located in the **RunDesktop.bat** file. Desktop shortcuts specified during installation point to this batch file. Whether a user is prompted to accept any new files or the files are automatically downloaded is dependent upon configuration settings as discussed in this section.

The files on the repository for which the version differs from that of the client are displayed in the Version Checker Client window. This window provides a list of the files along with the version number of each file on the repository and the version number of the file on the client. If automatic file updating is enabled (discussed later in this section), then this window is not displayed.

To download new files from the repository, select the applicable files and click Update. This update process can be skipped or canceled.



The **Select All** option can be used to select all listed files on the Version Checker Client window. Individual files can be selected by deselecting the Select All option and then clicking in the row for each desired file to download. Only selected files are downloaded.

If the **Close When Done** option is selected, the Version Checker Client window will automatically close after completion of the download of all selected files.

By selecting **Mirror Repository** on the Version Checker Client window, verification is initiated to ensure that no jars reside on the client that are not also on the server repository. That is, any files that exist on the client that do not exist on the current version of the server repository are deleted from the client.

The Version Checker can be configured to download updated and new files automatically. This automatic file updating (called VC quiet mode) is an option presented during installation of the ACI desktop.

Including the parameter “-Q” in the Version Checker command line located in the **RunDesktop.bat** file enables automatic file updating. Note that the “-Q” is added during installation when the VC quiet mode option is selected.

For example:

```
call "C:\ACI\VersionChecker\verChk" -Q
```

## 7: Online Help

---

The ACI desktop provides online help for windows (screens) and window components (e.g., fields). This help is displayed in a Java-based HTML browser, called the **Helpset Viewer**:



The components of the Helpset Viewer are:

- 1** — The **Title Bar** in which the name of the helpset is displayed.
- 2** — The **Toolbar** that contains various menu and button functions.
- 3** — The **Navigation Pane** in which are located Contents and Index tabs useful for navigating to desired help content, and a Search tab for searching content.
- 4** — The **Content Pane** in which help content is displayed.
- 5** — The **Contents** tab that provides structured access to window-level help files.
- 6** — The **Index** tab that provides alphabetical access to all help topics.
- 7** — The **Search** tab for searching help content.

## Access to JavaHelp from the ACI Desktop

JavaHelp content can be accessed with or without context. These two methods are explained below.

### With Context

Accessing online help with context displays the Helpset Viewer with content displayed in the Content Pane that is specific to a window or window component. To display help with context from the ACI desktop, select **Help > Context Help** or click  on the toolbar. Either of these actions display the Help Pointer  to use for clicking in a general area of a window for window-level help or on a window field for field-level help.

If a window is not open, help with context is not available because an active window in the Application Area of the ACI desktop is necessary to provide context. When context help is not available, the Context Help function and the button are inactive.

Note that the traditional way to access field-level help by placing the cursor in the field and pressing the **F1** key can also be used.

### Without Context

To display online help without context from the ACI desktop, select **Help > Help Topics** from the Menu Bar or click  on the Toolbar. A window does not need to be open to access online help without context. When online help is accessed using this method, the Helpset Viewer is displayed with the default home page provided in the content pane and the default TOC view in the navigation pane.

If the Help Topics function and the button are not enabled, then the ACI desktop does not have access to online help. Check with a System Administrator to obtain ACI online help.

# JavaHelp Files

The following files together are referred to as a **JavaHelp helpset**:

- The **helpset file** (ACI\_Help.hs), which is identified by the .hs file extension, defines the name of the helpset displayed in the Title Bar, the JavaHelp components used, the name of the map file, the names of the table of contents and index files, and the ID of the default content file to display in the Content Pane when help is accessed without context. The helpset file is the top-level file in the JavaHelp helpset.

Be careful not to confuse the term “JavaHelp helpset” with the helpset (.hs) file. *JavaHelp helpset* refers to a collection of JavaHelp files as discussed on this page. Whereas the helpset (.hs) file is a single file (see following page).

- The **map file** is an XML file identified by the .jhm file extension that corresponds identifiers to HTML content files. This file is necessary to provide context-sensitive help for windows and window components as discussed later in this section.
- The **table of contents file** that defines the structure and links of the text entries of the Contents tab.
- The **index file** that defines the structure and links of the text entries of the Index tab located in the Navigation Pane of the Helpset Viewer.
- **HTML files** in which help content resides.
- **Cascading Style Sheets (CSS)** define the style rules applied to content.
- The **images** displayed within HTML content files. Images used in content are in Graphical Interchange Format (GIF) and Joint Photographic Experts Group (JPEG or JPG) formats.

## JavaHelp Packages

ACI online help is packaged and distributed in the following Java™ Archive (JARs) files:

- **ACI\_Help\_apf.jar** — For APF-Admin ACI desktop windows
- **ACI\_Help\_es.jar** — For BASE24-eps
- **ACI\_Help\_tss.jar** — For Transaction Security Services (TSS)
- **ACI\_Help\_pm.jar** — For ACI Payments Manager (PM)

## Helpset File

The helpset file defines the Java components used, home page, map file, TOC, index, and views. Below is an example helpset file. Comments between “<!--” and “-->” have been added to provide additional information.

```
<?xml version='1.0' encoding='ISO-8859-1' ?>
<!DOCTYPE helpset
  PUBLIC "-//Sun Microsystems Inc.//DTD JavaHelp HelpSet Version 2.0//EN"
  "http://java.sun.com/products/javahelp/helpset_2_0.dtd">
<helpset version="2.0">

  <!-- The title displayed in the Title Bar -->
  <title>ACI Online Help</title>

  <!-- Map information -->
  <maps>
    <homeID>splash</homeID> <!-- The map ID of the splash page -->
    <mapref location="map.jhm" /> <!-- The map file -->
  </maps>

  <!-- Each view represents a tab on the Helpset viewer -->
  <!-- This helpset has 3 views. -->
  <!-- Immediately below is the TOC view -->
  <view>
    <name>TOC</name>
    <label>Contents</label> <!-- The popup (flyover) text of the tab -->
    <type>javax.help.TOCView</type> <!-- The JavaHelp TOC component -->
    <data>toc.xml</data> <!-- The name of the table of contents file -->
  </view>

  <!-- This is the index view -->
  <view>
    <name>Index</name>
    <label>Index</label>
    <type>javax.help.IndexView</type> <!--
    <data>ix.xml</data> <!-- The name of the index file -->
  </view>

  <!-- This is the search view -->
  <view>
    <name>Search</name>
    <label>Search</label>
    <type>javax.help.SearchView</type>
    <data engine="com.sun.java.help.search.DefaultSearchEngine">
      JavaHelpSearch
    </data> <!-- The search engine defined by the engine attribute -->
    <!-- And, the search database. In this case, the search -->
    <!-- database is located in a folder named JavaHelpSearch -->
  </view>


</helpset>
```

# How Context is Implemented in JavaHelp

Help context is implemented in JavaHelp by the use of unique identifiers. Each identifier (referred to as a map ID or help ID) appears as necessary in the following files:

- The property (.properties) file for a window (desktop application)  
**Note:** Most application windows have their own properties file. Also, some properties common among all windows are located in common property files that are shared among the window properties files.
- The JavaHelp map file, map.jhm (pmdesktop.jhm for ACI Payments Manager)
- The table of contents file, toc.xml (ACI\_Help\_pmtoc.xml for ACI Payments Manager)
- The index file, ix.xml (all applications)

The use and relationship of the identifiers in the above files is shown in the following illustration.




## Search the Helpset for a Text String

The Search tab provides a text entry field (Find) to locate up to 100 occurrences of a text string within a helpset.

**Note:** Search is not case sensitive.

Enter the text string in the Find text entry field and press the **Enter** key. JavaHelp searches through the helpset and displays a list of topics in which the text string is found. This list is displayed in the Navigation Area by topic title and in descending order of number of matches. Select the desired topic to display the topic's content in the Content area.





# Custom Help Content

Online help can be modified in a number of different ways depending on the level of modification desired.

- Content files can be modified.
- Cascading style sheets can be modified to change display formats.
- Images referenced in content files can be edited.

**Note:** Modifying the JavaHelp configuration files can adversely affect the performance of JavaHelp and is not discussed in this manual.

If an installed version of JavaHelp is customized, care must be taken to avoid overwriting the customized JavaHelp files when accepting an updated help JAR file for placement on the Version Checker repository. Therefore, the following guidelines can be used to establish procedures for maintaining and protecting customized JavaHelp:

- Always keep a backup of both original and customized files.
- Consider appending an identifier (e.g., “custom”) to the name of customized files. If a help file name is changed, the change must also be made to the map.jhm file. For example, a file named f\_connection.htm file is customized and renamed to f\_connection\_custom.htm. The url attribute in the map.jhm file must be changed as follows:

From:

```
<mapID target="f_connection"
      url="f_connection.htm"/>
```

To:

```
<mapID target="f_connection"
      url="f_connection_custom.htm"/>
```

- Another option is to keep the same name of the file but place the customized file into a separate directory as follows:

```
<mapID target="f_connection"
      url="custom/f_connection.htm"/>
```

## Customization of HTML Content Files

All content files within the JavaHelp JAR files are in compliance with the W3C HTML revision 3.2 format. This format is required for content files to display properly within the Helpset Viewer. Certain parts of the HTML revision 4.0 format can be used since it shares most markup tag elements with 3.2; however, care should be taken when implementing revision 4.0 features into content files destined for JavaHelp because certain revision 4.0 features might not be supported. To ensure proper behavior of content files in JavaHelp, always test the display characteristics of HTML files in JavaHelp before releasing the help files.

One advantage of the content files being in HTML format is that common editors can be used to modify help content. The specifics of editing HTML files are not discussed here since these depend on the editor; however, the following general always apply:

1. Before an HTML content file within a JAR file can be edited, the file must be extracted to a working location using a tool, such as WinZip. The extracted HTML file is a copy of the original file. Make a backup of the original file and place it in a specified archive directory for later retrieval. All editing should be done on the extracted copy.
2. Select an appropriate HTML editor. Note that some HTML editors automatically add embedded XML, HTML and other types of objects to HTML code. Such objects can adversely affect the display of the content within JavaHelp. As a result, editing tools that do not automatically add objects are recommended. Such tools include Macromedia's Dreamweaver and ASCII editors, such as Notepad.
3. Save the modified HTML file to the working location.
4. Add the modified file to the applicable JAR file replacing the original file in the JAR (the original being maintained in the archive directory location). Do not change the file extension.
5. If the name of the HTML file is changed to reflect customization, such as from `f_connection.htm` to `f_connection_custom.htm`, the URL attribute of the `map.jhm` file needs to be updated to reflect the name change. The `.jhm` file can be updated using an ASCII editor.

# Change the Display of Content

The format and style of the content displayed in the Helpset Viewer can be modified by altering the values of the style properties in the applicable cascading style sheet (CSS) file. CSS files are defined in the <head>...</head> section of each HTML file used in the ACI online help using <link> tags as follows:

```
<link rel="StyleSheet" href="Templates/forScreen.css" type="text/css"
media="screen">
```

```
<link rel="StyleSheet" href="Templates/forPrint.css" type="text/css"
media="print">
```

CSS files are located in the Templates folder within the applicable helpset JAR (ACI\_Help\_es.jar, ACI\_Help\_tss.jar, and ACI\_Help\_pm.jar).

**Note:** For ACI Payments Manager, the name of the CSS is document.css for both screen and print media.

To ensure that content displays properly in the Helpset Viewer, always test before releasing the modified CSS files.

## Install JavaHelp for Stand-alone Use


JavaHelp can be installed for direct access to helpset (.hs) files without the need to have the ACI desktop open. Note that Java must be already installed. The remainder of this topic discusses installing JavaHelp on a Java enabled Windows-based PC.

1. Download the latest version of JavaHelp from:


<http://java.sun.com/products/javahelp>

**Note:** JavaHelp is distributed as a zip file such as **Javahelp 2.0\_02.zip** (a more current version might be available).

2. Open the zip file and extract all files to an easily accessible location, such as (e.g., C:\jh2.0). Among the files extracted is the **hsvviewer.jar** file that is needed later in this procedure.
3. Find java.exe and create a shortcut to the file. Java.exe must be already installed. Cut and paste the shortcut to an easily accessible location.
4. Right click on the shortcut and select Properties on the drop-down menu:



The properties for the shortcut are available in the Properties window:




5. In the Target field located on the Shortcut tab, enter the path to java.exe, followed by a space, -jar, another space, and then the path to the installed location of hviewer.jar. In the illustration above, the full text of the Target field is partially obscured, but contains:

"C:\Program Files\jdk1.5.0\_05\bin\java.exe" -jar "C:\jh2.0\demos\bin\hviewer.jar"

**Note:** If a blank space is located in a file path (e.g., C:\Program Files\...), enclose the path in quotes, as shown above.

6. Click OK.

7. Test the install by clicking on the shortcut, after which the following Set HelpSet window should display that can be used to browse to a helpset file (.hs extension) that you want to open.



If the above window does not display, a number of problems could exist. For example, either Java, JavaHelp, or both are not installed properly. Also, the target path in the shortcut could be incorrect. Verify that the paths in the shortcut reflect the actual paths for both java.exe and hsvviewer.jar.

# A: BASE24-eps Window (UI) Information

---

The term *window* is used in documentation and online help. This term relates to a collection of graphical user interface (GUI) components (i.e., buttons, fields, field names, tabs, buttons, tables, trees, and messages) that provide access to a particular application, function and data source(s).

Each window, which can also be called a UI, is managed by a particular application server on the host. The applications available (therefore, the windows available) depend on the ACI desktop configuration and user security access permissions.

An application (and the corresponding window) is identified by a task ID. Tasks available on a desktop can be viewed in the Task ID selectable field located on the Permissions tab of the User Security Role Configuration window (**Configure > User Security > Role**).

Window information is presented alphabetically by window name. Information is structured as follows:

|                 |                                                                                                                                                                                                                                       |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | The unique task ID for the window.                                                                                                                                                                                                    |
| Permissions:    | Full access and view access permissions, as applicable.                                                                                                                                                                               |
| Help ID:        | The unique ID for context sensitive help between the desktop and the online help system.                                                                                                                                              |
| Data Sources:   | A list of data sources possibly updated by the window. The actual data source(s) impacted by a change made at a window can vary by application configuration. Verify impacted data sources using the OLTP Warmboot Management window. |
| Desktop Access: | How the window is accessed on the ACI desktop.                                                                                                                                                                                        |
| Messages:       | Messages exchanged with the server.                                                                                                                                                                                                   |

## Interface Profile Permissions

FullAcqProfileConfigPermission  
ViewAcquirerProfileConfig

FullAcqTransAllowedPermission  
ViewAcqTransAllowedPermission

FullIssTransAllowedPermission  
ViewIssTransAllowedPermission

FullContextConfigPermission  
ViewContextConfigPermission

FullISOFrameworkCfgPermission  
ViewISOFrameworkCfgPermission

FullActionCodePermission  
ViewActionCodePermission

FullATMSurchPrflPermission  
ViewATMSurchPrflPermission

FullISOTranMapPermission  
ViewISOTranMapPermission



**ABI (Italian Banking Association) ISO Interface Configuration Window**

|                 |                                                                                   |
|-----------------|-----------------------------------------------------------------------------------|
| Task ID:        | AbiIsoInterface                                                                   |
| Permissions:    | FullAbiIsoInterfacePermission<br>ViewAbiIsoInterfacePermission                    |
| Help ID:        | n/a                                                                               |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station                                   |
| Desktop Access: | Configure > Interface > Network > ABI (Italian Banking Association) ISO Interface |
| Messages:       | n/a                                                                               |

**ACCEL/Exchange Interface Configuration Window**

|                 |                                                                    |
|-----------------|--------------------------------------------------------------------|
| Task ID:        | AccelInterface                                                     |
| Permissions:    | FullAccelInterfacePermission<br>ViewAccelInterfacePermission       |
| Help ID:        | n/a                                                                |
| Data Sources:   | ACCEL_Interface<br>Interface<br>Interface_SAF<br>Interface_Station |
| Desktop Access: | Configure > Interface > Network > Accel/Exchange                   |
| Messages:       | n/a                                                                |

## ACCEL-Exchange Network ID/Instrument Type Relationship Configuration Window

|                      |                                                                                             |
|----------------------|---------------------------------------------------------------------------------------------|
| Task ID:             | AccelBrandInstrmRelation                                                                    |
| Permissions:         | FullAccelBrandInstrmRelnPerm<br>ViewAccelBrandInstrmRelnPerm                                |
| Related Permissions: | FullAccelInterfacePermission<br>ViewAccelInterfacePermission                                |
| Help ID:             | n/a                                                                                         |
| Data Sources:        | n/a                                                                                         |
| Desktop Access:      | Configure > Interface > Network > ACCEL-Exchange<br>Network ID/Instrument Type Relationship |
| Messages:            | n/a                                                                                         |

## Acquirer Transactions Allowed Profile Configuration Window

|                 |                                                                                                                   |
|-----------------|-------------------------------------------------------------------------------------------------------------------|
| Task ID:        | AcquirerTransactionsAllowed                                                                                       |
| Permissions:    | FullAcqTransAllowedPermission<br>ViewAcqTransAllowedPermission                                                    |
| Help ID:        | w_acquirer_transactions_allowed_profile_configuration                                                             |
| Data Sources:   | Acquirer_Txn_Allowed                                                                                              |
| Desktop Access: | Configure > Transactions Allowed > Acquirer Transactions<br>Profile                                               |
| Messages:       | ATAPrflListRq<br>ATAPrflInsertRq<br>ATAPrflViewRq<br>ATAPrflUpdateRq<br>ATAPrflDeleteRq<br>ATAPrflGenericDeleteRq |

## Action Code Profile Configuration Window

|                 |                                                                                                                                                                                                                                                   |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ActionCode                                                                                                                                                                                                                                        |
| Permissions:    | FullActionCodePermission<br>FullIFXHostActCdPermission<br>ViewActionCodePermission<br>ViewIFXHostActCdPermission                                                                                                                                  |
| Help ID:        | w_action_code                                                                                                                                                                                                                                     |
| Data Sources:   | Action_Code_Extrn_to_Intrn<br>Action_Code_Intrn_to_Extrn                                                                                                                                                                                          |
| Desktop Access: | Configure > Action Code Profile                                                                                                                                                                                                                   |
| Messages:       | ActionCodeIntInsertRq<br>ActionCodeExtInsertRq<br>ActionCodeListRq<br>ActionCodeIntViewRq<br>ActionCodeIntUpdateRq<br>ActionCodeExtViewRq<br>ActionCodeExtUpdateRq<br>ActionCodeIntDeleteRq<br>ActionCodeExtDeleteRq<br>ActionCodeGenericDeleteRq |

## Active Scripts Statistics and Management Window

|                 |                                                                                                                      |
|-----------------|----------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ActiveScript                                                                                                         |
| Permissions:    | FullActiveScriptPermission<br>ViewActiveScriptPermission                                                             |
| Help ID:        | w_active_script_statistics_and_management                                                                            |
| Data Sources:   | Active_Script_Statistics                                                                                             |
| Desktop Access: | System Operations > Active Script Statistics                                                                         |
| Messages:       | ActiveScriptListRq<br>ActiveScriptMsgTypeListRq<br>AuthScriptDataRq<br>ActiveScriptViewRq<br>ActiveScriptResetDataRq |

## Administrative Card Configuration Window

|                 |                                                                                |
|-----------------|--------------------------------------------------------------------------------|
| Task ID:        | AdministrativeCardManagement                                                   |
| Permissions:    | FullAdminCardMgmtPermission<br>ViewAdminCardMgmtPermission                     |
| Help ID:        | w_administrative_card_configuration                                            |
| Data Sources:   | Admin_Card                                                                     |
| Desktop Access: | Configure > Administrative Card                                                |
| Messages:       | AdminCardInsertRq<br>AdminCardViewRq<br>AdminCardUpdateRq<br>AdminCardDeleteRq |

## American Express Global Network Services Configuration Window

|                 |                                                                                                            |
|-----------------|------------------------------------------------------------------------------------------------------------|
| Task ID:        | AmexGNSInterface                                                                                           |
| Permissions:    | FullAmexGNSInterfacePermission                                                                             |
| Help ID:        | w_aegn_interface_configuration                                                                             |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>AEGN_Interface                                          |
| Desktop Access: | Configure > Interface > Network > American Express Global Network                                          |
| Messages:       | InterfaceStationListRq<br>InterfaceStationInsertRq<br>InterfaceStationUpdateRq<br>InterfaceStationDeleteRq |

## Application Configuration Window

|                 |                                                                                                               |
|-----------------|---------------------------------------------------------------------------------------------------------------|
| Task ID:        | IWTApplicationConfig                                                                                          |
| Permissions:    | FullIWTAppIcfigPermission<br>ViewIWTAppIcfigPermission                                                        |
| Help ID:        | w_application_configuration                                                                                   |
| Data Sources:   | APPLCNFG                                                                                                      |
| Desktop Access: | System Operations > Server Management > Application                                                           |
| Messages:       | IWTfAppCfgInsertRq<br>IWTfAppCfgGetPropertyRq<br>IWTfAppCfgListRq<br>IWTfAppCfgUpdateRq<br>IWTfAppCfgDeleteRq |

## Application Management Comms Handler Window

|                 |                                                                             |
|-----------------|-----------------------------------------------------------------------------|
| Task ID:        | ApplctnManagementSummary                                                    |
| Permissions:    | FullApplctnManagementSummary<br>ViewApplctnManagementSummary                |
| Data Sources:   | Not specified.                                                              |
| Help ID:        | w_appmanage_comms_handler_summary                                           |
| Desktop Access: | System Operations > Application Management > Comms<br>Handler Summary       |
| Messages:       | ApMgButtonRq<br>ApMgMbListRq<br>ApMgSummaryRq<br>ApMgUpdateRq<br>ApMgViewRq |

## Application Management Message Router Summary Window

|                 |                                                                             |
|-----------------|-----------------------------------------------------------------------------|
| Task ID:        | ApplctnManagementSummary                                                    |
| Permissions:    | FullApplctnManagementSummary<br>ViewApplctnManagementSummary                |
| Data Sources:   | Not specified.                                                              |
| Help ID:        | w_appmanage_message_router_summary                                          |
| Desktop Access: | System Operations > Application Management > Message Router Summary         |
| Messages:       | ApMgButtonRq<br>ApMgMbListRq<br>ApMgSummaryRq<br>ApMgUpdateRq<br>ApMgViewRq |

## Application Management Process Summary Window

|                 |                                                                             |
|-----------------|-----------------------------------------------------------------------------|
| Task ID:        | ApplctnManagementSummary                                                    |
| Permissions:    | FullApplctnManagementSummary<br>ViewApplctnManagementSummary                |
| Data Sources:   | Not specified.                                                              |
| Help ID:        | w_appmanage_process_summary                                                 |
| Desktop Access: | System Operations > Application Management > Process Summary                |
| Messages:       | ApMgButtonRq<br>ApMgMbListRq<br>ApMgSummaryRq<br>ApMgUpdateRq<br>ApMgViewRq |

## Application Management Queue Manager Summary Window

|                 |                                                                             |
|-----------------|-----------------------------------------------------------------------------|
| Task ID:        | ApplctnManagementSummary                                                    |
| Permissions:    | FullApplctnManagementSummary<br>ViewApplctnManagementSummary                |
| Data Sources:   | Not specified.                                                              |
| Help ID:        | w_appmanage_queue_manager_summary                                           |
| Desktop Access: | System Operations > Application Manager > Queue Manager Summary             |
| Messages:       | ApMgButtonRq<br>ApMgMbListRq<br>ApMgSummaryRq<br>ApMgUpdateRq<br>ApMgViewRq |

## Application Management Queue Summary Window

|                 |                                                                             |
|-----------------|-----------------------------------------------------------------------------|
| Task ID:        | ApplctnManagementSummary                                                    |
| Permissions:    | FullApplctnManagementSummary<br>ViewApplctnManagementSummary                |
| Data Sources:   | Not specified.                                                              |
| Help ID:        | w_appmanage_queue_summary                                                   |
| Desktop Access: | System Operations > Application Management > Queue Summary                  |
| Messages:       | ApMgButtonRq<br>ApMgMbListRq<br>ApMgSummaryRq<br>ApMgUpdateRq<br>ApMgViewRq |

## Application Management Station Summary Window

|                 |                                                                             |
|-----------------|-----------------------------------------------------------------------------|
| Task ID:        | ApplctnManagementSummary                                                    |
| Permissions:    | FullApplctnManagementSummary<br>ViewApplctnManagementSummary                |
| Data Sources:   | Not specified.                                                              |
| Help ID:        | w_appmanage_station_summary                                                 |
| Desktop Access: | System Operations > Application Management > Station Summary                |
| Messages:       | ApMgButtonRq<br>ApMgMbListRq<br>ApMgSummaryRq<br>ApMgUpdateRq<br>ApMgViewRq |

## Application Management Window

|                 |                                                                             |
|-----------------|-----------------------------------------------------------------------------|
| Task ID:        | ApplctnManagement                                                           |
| Permissions:    | FullApplctnManagement<br>ViewApplctnManagement                              |
| Data Sources:   | Not specified.                                                              |
| Help ID:        | t_appmanage_detail                                                          |
| Desktop Access: | System Operations > Application Management > Application Management         |
| Messages:       | ApMgButtonRq<br>ApMgMbListRq<br>ApMgSummaryRq<br>ApMgUpdateRq<br>ApMgViewRq |



## Application Parameter Management System Interface Configuration Window

|                 |                                                                 |
|-----------------|-----------------------------------------------------------------|
| Task ID:        | APMSInterfaceConfiguration                                      |
| Permissions:    | FullAPMSIFCfgPermission                                         |
| Help ID:        | w_apms_interface_configuration                                  |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station                 |
| Desktop Access: | Configure > Interface > Host > Application Parameter Management |
| Messages:       | n/a                                                             |

## Armed Forces Financial Network (AFFN) Institution Configuration Window

|                 |                                                                                                                             |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | AffnInstitution                                                                                                             |
| Permissions:    | FullAffnInstitutionPermission                                                                                               |
| Help ID:        | n/a                                                                                                                         |
| Data Sources:   | n/a                                                                                                                         |
| Desktop Access: | Configure > Interface > Network > Armed Forces Financial Network (AFFN) > Armed Forces Financial Network (AFFN) Institution |
| Messages:       | n/a                                                                                                                         |

## Armed Forces Financial Network (AFFN) Interface Configuration Window

|                 |                                                                                                                           |
|-----------------|---------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | AffnInterface                                                                                                             |
| Permissions:    | FullAffnInterfacePermission                                                                                               |
| Help ID:        | n/a                                                                                                                       |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station                                                                           |
| Desktop Access: | Configure > Interface > Network > Armed Forces Financial Network (AFFN) > Armed Forces Financial Network (AFFN) Interface |
| Messages:       | n/a                                                                                                                       |

## ATM BASE24 Compatibility Profile Configuration Window

|                 |                                                                                                                                                                                                                      |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMB24CompatProfile                                                                                                                                                                                                  |
| Permissions:    | FullATMB24CompatPrflPermission<br>ViewATMB24CompatPrflPermission                                                                                                                                                     |
| Help ID:        | w_atm_base24_compatibility_profile_configuration                                                                                                                                                                     |
| Data Sources:   | CMPTPRFL                                                                                                                                                                                                             |
| Desktop Access: | Configure > ATM (Java) > ATM BASE24 Compatibility Profile                                                                                                                                                            |
| Messages:       | ATM BASE24 Compatibility Profile<br>ATMB24CompatProfileInsertRq<br>ATMB24CompatProfileListRq<br>ATMB24CompatProfileViewRq<br>ATMB24CompatProfileUpdateRq<br>ATMB24CompatProfileViewRq<br>ATMB24CompatProfileDeleteRq |

## ATM Channel Administration Window

|                 |                                                                                                                                    |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMChannelAdministration                                                                                                           |
| Permissions:    | FullATMChannelAdminPermission<br>ViewATMChannelAdminPermission                                                                     |
| Help ID:        | w_atm_channel_administration_java                                                                                                  |
| Data Sources:   | ATDCNFG<br>ESATDD1<br>ESATDS1<br>HPRPRFL                                                                                           |
| Desktop Access: | System Operations > ATM (Java) > ATM Channel Administration                                                                        |
| Messages:       | ATM Channel Administration<br>ATMChannelAdminListRq<br>ATMChannelAdminViewRq<br>ATMChannelAdminUpdateRq<br>ATMChannelAdminSubmitRq |

## ATM Channel Administration Window

|                 |                                                                                                      |
|-----------------|------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHChannelAdministration                                                                           |
| Permissions:    | FullATMDHChannelAdminPerm<br>ViewATMDHChannelAdminPerm                                               |
| Help ID:        | w_atm_channel_administration_cplus                                                                   |
| Data Sources:   | ATDCNFG<br>ESATDD1<br>ESATDS1                                                                        |
| Data Sources:   | HPRPRFL                                                                                              |
| Desktop Access: | System Operations > ATM > ATM Channel Administration                                                 |
| Messages:       | ATMChannelAdminListRq<br>ATMChannelAdminViewRq<br>ATMChannelAdminUpdateRq<br>ATMChannelAdminSubmitRq |

## ATM Channel Configuration Window

|                 |                                                                                                                                                                                                                                                        |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMChannel                                                                                                                                                                                                                                             |
| Permissions:    | FullATMChannelPermission<br>FullATMChannelAdminPermission<br>FullATMChannelMgmtPermission<br>FullATMChannelPrflPermission<br>ViewATMChannelPermission<br>ViewATMChannelAdminPermission<br>ViewATMChannelMgmtPermission<br>ViewATMChannelPrflPermission |
| Help ID:        | w_atm_channel_configuration_java                                                                                                                                                                                                                       |
| Data Sources:   | Not specified.                                                                                                                                                                                                                                         |
| Desktop Access: | Configure > ATM (Java) > ATM Channel                                                                                                                                                                                                                   |
| Messages:       | Not specified.                                                                                                                                                                                                                                         |

## ATM Channel Configuration Window

|                 |                                                                                                                                                                                                                                                            |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHChannel                                                                                                                                                                                                                                               |
| Permissions:    | FullATMDHChannelPermission<br>FullATMDHChannelAdminPerm<br>FullATMDHChannelMgmtPermission<br>FullATMDHChannelPrflPermission<br>ViewATMDHChannelPermission<br>ViewATMDHChannelAdminPerm<br>ViewATMDHChannelMgmtPermission<br>ViewATMDHChannelPrflPermission |
| Help ID:        | w_atm_channel_configuration_cplus                                                                                                                                                                                                                          |
| Data Sources:   | ATM_DS1                                                                                                                                                                                                                                                    |
| Desktop Access: | Configure > ATM > ATM Channel                                                                                                                                                                                                                              |
| Messages:       | Not specified.                                                                                                                                                                                                                                             |

**ATM Channel Management - All Channels Window**

|                 |                                                                        |
|-----------------|------------------------------------------------------------------------|
| Task ID:        | ATMChannelManagement                                                   |
| Permissions:    | FullATMChannelMgmtPermission<br>ViewATMChannelMgmtPermission           |
| Help ID:        | w_atm_channel_management_all_java                                      |
| Data Sources:   | ESATDD1<br>ESATDS1                                                     |
| Desktop Access: | System Operations > ATM (Java) > ATM Channel Management > All Channels |
| Messages:       | ATMChannelMgmtAllSubmitRq                                              |

**ATM Channel Management - All Channels Window**

|                 |                                                                  |
|-----------------|------------------------------------------------------------------|
| Task ID:        | ATMDHChannelManagement                                           |
| Permissions:    | FullATMDHChannelMgmtPermission<br>ViewATMDHChannelMgmtPermission |
| Help ID:        | w_atm_channel_management_all_cplus                               |
| Data Sources:   | ESATDD1<br>ESATDS1                                               |
| Desktop Access: | System Operations > ATM > ATM Channel Management > All Channels  |
| Messages:       | ATMChannelMgmtAllSubmitRq                                        |

**ATM Channel Management - Selected Channels Window**

|                 |                                                                         |
|-----------------|-------------------------------------------------------------------------|
| Task ID:        | ATMDHChanMgmtSelectedChannels                                           |
| Permissions:    | FullATMDHChanMgmtSCPermission<br>ViewATMDHChanMgmtSCPermission          |
| Help ID:        | w_atm_channel_management_selected_cplus                                 |
| Data Sources:   | ESATDD1<br>ESATDS1                                                      |
| Desktop Access: | System Operations > ATM > ATM Channel Management ><br>Selected Channels |
| Messages:       | ATMChannelMgmtViewRq<br>ATMChannelMgmtSubmitRq                          |

**ATM Channel Management - Selected Channels Window**

|                 |                                                                                |
|-----------------|--------------------------------------------------------------------------------|
| Task ID:        | ATMChanMgmtSelectedChannels                                                    |
| Permissions:    | FullATMChanMgmtSCPermission<br>ViewATMChanMgmtSCPermission                     |
| Help ID:        | w_atm_channel_management_selected_java                                         |
| Data Sources:   | ESATDD1<br>ESATDS1                                                             |
| Desktop Access: | System Operations > ATM (Java) > ATM Channel<br>Management > Selected Channels |
| Messages:       | ATMChannelMgmtViewRq<br>ATMChannelMgmtSubmitRq                                 |

## ATM Channel Profile Configuration Window

|                 |                                                                                                                                      |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMChannelProfile                                                                                                                    |
| Permissions:    | FullATMChannelPrflPermission<br>ViewATMChannelPrflPermission                                                                         |
| Help ID:        | w_atm_channel_profile_configuration                                                                                                  |
| Data Sources:   | ATM_PRFL                                                                                                                             |
| Desktop Access: | Configure > ATM (Java) > ATM Channel Profile                                                                                         |
| Messages:       | ATMConfigProfileInsertRq<br>ATMConfigProfileListRq<br>ATMConfigProfileViewRq<br>ATMConfigProfileUpdateRq<br>ATMConfigProfileDeleteRq |

## ATM Channel Profile Configuration Window

|                 |                                                                                                                                      |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHChannelProfile                                                                                                                  |
| Permissions:    | FullATMDHChannelPrflPermission<br>ViewATMDHChannelPrflPermission                                                                     |
| Help ID:        | w_atm_channel_profile_cplus                                                                                                          |
| Data Sources:   | ATM_PRFL                                                                                                                             |
| Desktop Access: | Configure > ATM > ATM Channel Profile                                                                                                |
| Messages:       | ATMConfigProfileInsertRq<br>ATMConfigProfileListRq<br>ATMConfigProfileViewRq<br>ATMConfigProfileUpdateRq<br>ATMConfigProfileDeleteRq |

## ATM Consumer Media Configuration Window

|                 |                                                                                                                                                                                     |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHConsumerMedia                                                                                                                                                                  |
| Permissions:    | FullATMDHConsumerMediaPerm<br>ViewATMDHConsumerMediaPerm                                                                                                                            |
| Help ID:        | w_consumer_media_configuration                                                                                                                                                      |
| Data Sources:   | ATM_CONSUMER_MEDIA                                                                                                                                                                  |
| Desktop Access: | Configure > ATM > ATM Consumer Media                                                                                                                                                |
| Messages:       | ATMDHConsumerMediaInsertRq<br>ATMDHConsumerMediaListRq<br>ATMDHConsumerMediaViewRq<br>ATMDHConsumerMediaUpdateRq<br>ATMDHConsumerMediaDeleteRq<br>ATMDHConsumerMediaGenericDeleteRq |

## ATM Depository Bin Profile Configuration Window

|                 |                                                                                                                                                                                     |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHDepositoryBinProfile                                                                                                                                                           |
| Permissions:    | FullATMDHDepBinPrflPermission<br>ViewATMDHDepBinPrflPermission                                                                                                                      |
| Help ID:        | n/a                                                                                                                                                                                 |
| Data Sources:   | ATM_SSB_BIN                                                                                                                                                                         |
| Desktop Access: | Configure > ATM > ATM Depository Bin Profile                                                                                                                                        |
| Messages:       | ATMDHDepBinProfileInsertRq<br>ATMDHDepBinProfileListRq<br>ATMDHDepBinProfileViewRq<br>ATMDHDepBinProfileUpdateRq<br>ATMDHDepBinProfileDeleteRq<br>ATMDHDepBinProfileGenericDeleteRq |



## ATM Device Handler Interface Configuration Window

|                 |                                                      |
|-----------------|------------------------------------------------------|
| Task ID:        | ATMDHInterfaceConfiguration                          |
| Permissions:    | FullATMDHIFCfgPermission<br>ViewATMDHIFCfgPermission |
| Help ID:        | w_atm_device_handler_interface_configuration         |
| Data Sources:   | Not specified.                                       |
| Desktop Access: | Configure > Interface > Host > ATM Device Handler    |
| Messages:       | Not specified.                                       |

## ATM Diebold Channel Operator Configuration Window

|                 |                                                                                                                                           |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHDieboldChannelOperatorID                                                                                                             |
| Permissions:    | FullATMDHDbldChanOpIDPerm<br>ViewATMDHDbldChanOpIDPerm                                                                                    |
| Help ID:        | w_atm_diebold_channel_operator_configuration                                                                                              |
| Data Sources:   | ATM_OPER                                                                                                                                  |
| Desktop Access: | Configure > ATM > ATM Diebold Channel Operator                                                                                            |
| Messages:       | ATMDHOperIdInsertRq<br>ATMDHOperIdListRq<br>ATMDHOperIdViewRq<br>ATMDHOperIdUpdateRq<br>ATMDHOperIdDeleteRq<br>ATMDHOperIdGenericDeleteRq |

## ATM Diebold Channel Operator ID Configuration Window

|                 |                                                                                                                                           |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDieboldChannelOperatorID                                                                                                               |
| Permissions:    | FullATMDbldChanOprIDPermission<br>ViewATMDbldChanOprIDPermission                                                                          |
| Help ID:        | w_atm_diebold_channel_id_configuration                                                                                                    |
| Data Sources:   | ATM_OPER                                                                                                                                  |
| Desktop Access: | Configure > ATM (Java) > ATM Diebold Channel Operator                                                                                     |
| Messages:       | ATMDHOperIdInsertRq<br>ATMDHOperIdListRq<br>ATMDHOperIdViewRq<br>ATMDHOperIdUpdateRq<br>ATMDHOperIdDeleteRq<br>ATMDHOperIdGenericDeleteRq |

## ATM EMV Profile Configuration Window

|                 |                                                                                                                       |
|-----------------|-----------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMEmvProfile                                                                                                         |
| Permissions:    | FullATMEMVProfilePermission<br>ViewATMEMVProfilePermission                                                            |
| Help ID:        | w_atm_emv_profile_configuration                                                                                       |
| Data Sources:   | ATM_EMV                                                                                                               |
| Desktop Access: | Configure > ATM (Java) > ATM EMV Profile                                                                              |
| Messages:       | ATMEmvProfileInsertRq<br>ATMEmvProfileListRq<br>ATMEmvProfileViewRq<br>ATMEmvProfileUpdateRq<br>ATMEmvProfileDeleteRq |

## ATM Fast Cash Profile Configuration Window

|                 |                                                                                                                                                |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHFastCashProfile                                                                                                                           |
| Permissions:    | FullATMDHFastCashPrflPerm<br>ViewATMDHFastCashPrflPerm                                                                                         |
| Help ID:        | w_atm_fast_cash_profile_configuration                                                                                                          |
| Data Sources:   | ATM_FAST_CASH                                                                                                                                  |
| Desktop Access: | Configure > ATM > ATM Fast Cash Profile                                                                                                        |
| Messages:       | ATMFastCashProfileInsertRq<br>ATMFastCashProfileListRq<br>ATMFastCashProfileViewRq<br>ATMFastCashProfileUpdateRq<br>ATMFastCashProfileDeleteRq |

## ATM Fast Cash Profile Configuration Window

|                 |                                                                                                                                                |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMFastCashProfile                                                                                                                             |
| Permissions:    | FullATMFastCashPrflPermission<br>ViewATMFastCashPrflPermission                                                                                 |
| Help ID:        | w_atm_fast_cash_profile_configuration                                                                                                          |
| Data Sources:   | ATM_FAST_CASH                                                                                                                                  |
| Desktop Access: | Configure > ATM (Java) > ATM Fast Cash Profile                                                                                                 |
| Messages:       | ATMFastCashProfileInsertRq<br>ATMFastCashProfileListRq<br>ATMFastCashProfileViewRq<br>ATMFastCashProfileUpdateRq<br>ATMFastCashProfileDeleteRq |

## ATM Flow Configuration

|                 |                                                                                                                                                                                                                                                                                                          |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHFlowconfig                                                                                                                                                                                                                                                                                          |
| Permissions:    | FullATMDHFlowConfigPermission<br>ViewATMDHFlowConfigPermission                                                                                                                                                                                                                                           |
| Help ID:        | w_atm_flow_configuration                                                                                                                                                                                                                                                                                 |
| Data Sources:   | ATM_FLOW_CNTL                                                                                                                                                                                                                                                                                            |
| Desktop Access: | Configure > ATM > ATM Flow > ATM Flow Configuration                                                                                                                                                                                                                                                      |
| Messages:       | ATMDHFlowInsertRq<br>ATMDHFlowListRq<br>ATMDHFlowGetControlInfoRq<br>ATMDHFlowViewRq<br>ATMDHFlowUpdateRq<br>ATMDHFlowDeleteRq<br>ATMDHFlowCreateWorkingRq<br>ATMDHFlowCheckInWorkingRq<br>ATMDHFlowSequenceControlListRq<br>ATMDHFlowGenericDeleteRq<br>ATMDHFlowWorkingListRq<br>ATMDHFlowActiveListRq |

## ATM Flow Management

|                 |                                                                                                                                                                                                                                                                                                          |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHFlowManagement                                                                                                                                                                                                                                                                                      |
| Permissions:    | FullATMDHFlowMgmtPermission<br>ViewATMDHFlowMgmtPermission                                                                                                                                                                                                                                               |
| Help ID:        | w_atm_flow_management                                                                                                                                                                                                                                                                                    |
| Data Sources:   | ATM_FLOW_CNTL                                                                                                                                                                                                                                                                                            |
| Desktop Access: | Configure > ATM > ATM Flow > ATM Flow Management                                                                                                                                                                                                                                                         |
| Messages:       | ATMDHFlowInsertRq<br>ATMDHFlowListRq<br>ATMDHFlowGetControlInfoRq<br>ATMDHFlowViewRq<br>ATMDHFlowUpdateRq<br>ATMDHFlowDeleteRq<br>ATMDHFlowCreateWorkingRq<br>ATMDHFlowCheckInWorkingRq<br>ATMDHFlowSequenceControlListRq<br>ATMDHFlowGenericDeleteRq<br>ATMDHFlowWorkingListRq<br>ATMDHFlowActiveListRq |

## ATM Flow Perusal

|                 |                                                                                                                                                                                                                                                                                                          |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHFlowPerusal                                                                                                                                                                                                                                                                                         |
| Permissions:    | FullATMDHFlowPerusalPermission<br>ViewATMDHFlowPerusalPermission                                                                                                                                                                                                                                         |
| Help ID:        | w_atm_flow_perusal                                                                                                                                                                                                                                                                                       |
| Data Sources:   | ATM_FLOW_CNTL                                                                                                                                                                                                                                                                                            |
| Desktop Access: | Configure > ATM > ATM Flow > ATM Flow Perusal                                                                                                                                                                                                                                                            |
| Messages:       | ATMDHFlowInsertRq<br>ATMDHFlowListRq<br>ATMDHFlowGetControlInfoRq<br>ATMDHFlowViewRq<br>ATMDHFlowUpdateRq<br>ATMDHFlowDeleteRq<br>ATMDHFlowCreateWorkingRq<br>ATMDHFlowCheckInWorkingRq<br>ATMDHFlowSequenceControlListRq<br>ATMDHFlowGenericDeleteRq<br>ATMDHFlowWorkingListRq<br>ATMDHFlowActiveListRq |

## ATM Hardware Status Window

|                 |                                                                |
|-----------------|----------------------------------------------------------------|
| Task ID:        | ATMHardwareStatus                                              |
| Permissions:    | FullATMHardwareStatPermission<br>ViewATMHardwareStatPermission |
| Help ID:        | w_atm_hardware_status                                          |
| Data Sources:   | ESATDD1                                                        |
| Desktop Access: | System Operations > ATM (Java) > ATM Hardware Status           |
| Messages:       | ATMHardwareStatusListRq<br>ATMHardwareStatusViewRq             |

## ATM Hopper Profile Configuration Window

|                 |                                                                                                                                      |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHHopperProfile                                                                                                                   |
| Permissions:    | FullATMDHHopperPrflPermission<br>ViewATMDHHopperPrflPermission                                                                       |
| Help ID:        | w_atm_hopper_profile_configuration_cplus                                                                                             |
| Data Sources:   | ATM_HOPR                                                                                                                             |
| Desktop Access: | Configure > ATM > ATM Hopper Profile                                                                                                 |
| Messages:       | ATMHopperProfileInsertRq<br>ATMHopperProfileListRq<br>ATMHopperProfileViewRq<br>ATMHopperProfileUpdateRq<br>ATMHopperProfileDeleteRq |

## ATM Hopper Profile Configuration Window

|                 |                                                                                                                                      |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMHopperProfile                                                                                                                     |
| Permissions:    | FullATMHopperPrflPermission<br>ViewATMHopperPrflPermission                                                                           |
| Help ID:        | w_atm_hopper_profile_configuration_java                                                                                              |
| Data Sources:   | ATM_HOPR                                                                                                                             |
| Desktop Access: | Configure > ATM (Java) > ATM Hopper Profile                                                                                          |
| Messages:       | ATMHopperProfileInsertRq<br>ATMHopperProfileListRq<br>ATMHopperProfileViewRq<br>ATMHopperProfileUpdateRq<br>ATMHopperProfileDeleteRq |

## ATM Inactivity Alert Profile Configuration Window

|                 |                                                                                                                                 |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHInactivityProfile                                                                                                          |
| Permissions:    | FullATMDHInactiveAlertPrflPerm<br>ViewATMDHInactiveAlertPrflPerm                                                                |
| Help ID:        | w_atm_inactivity_alert_profile_configuration                                                                                    |
| Data Sources:   | ATM_INACT                                                                                                                       |
| Desktop Access: | Configure > ATM > ATM Inactivity Alert Profile                                                                                  |
| Messages:       | ATMInactProfileInsertRq<br>ATMInactProfileListRq<br>ATMInactProfileViewRq<br>ATMInactProfileUpdateRq<br>ATMInactProfileDeleteRq |

## ATM Inactivity Alert Profile Configuration Window

|                 |                                                                                                                                 |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMInactivityProfile                                                                                                            |
| Permissions:    | FullATMInactivePrflPermission<br>ViewATMInactivePrflPermission                                                                  |
| Help ID:        | w_atm_inactivity_alert_profile_configuration                                                                                    |
| Data Sources:   | ATM_INACT                                                                                                                       |
| Desktop Access: | Configure > ATM (Java) > ATM Inactivity Alert Profile                                                                           |
| Messages:       | ATMInactProfileInsertRq<br>ATMInactProfileListRq<br>ATMInactProfileViewRq<br>ATMInactProfileUpdateRq<br>ATMInactProfileDeleteRq |



## ATM Load Configuration Administration Window

|                 |                                                                 |
|-----------------|-----------------------------------------------------------------|
| Task ID:        | ATMDHLoadConfigAdmin                                            |
| Permissions:    | FullATMDHLoadCnfgAdminPerm<br>ViewATMDHLoadCnfgAdminPerm        |
| Help ID:        | w_atm_load_configuration_administration                         |
| Data Sources:   | ATM_CONF                                                        |
| Desktop Access: | System Operations > ATM > ATM Load Configuration Administration |
| Messages:       | ATMDHConfUtilSubmitRq                                           |

## ATM Load Profile Window

|                 |                                                                        |
|-----------------|------------------------------------------------------------------------|
| Task ID:        | ATMDHLoadProfile                                                       |
| Permissions:    | FullATMDHLoadPrflPermission<br>ViewATMDHLoadPrflPermission             |
| Help ID:        | w_atm_load_profile                                                     |
| Data Sources:   | ATMCNFG                                                                |
| Desktop Access: | Configure > ATM > ATM Load Profile                                     |
| Messages:       | ATMLoadProfileDeleteRq<br>ATMLoadProfileListRq<br>ATMLoadProfileViewRq |

## ATM Load Profile Window

|                 |                                                                        |
|-----------------|------------------------------------------------------------------------|
| Task ID:        | ATMLoadProfile                                                         |
| Permissions:    | FullATMLoadProfilePermission<br>ViewATMLoadProfilePermission           |
| Help ID:        | w_atm_load_profile                                                     |
| Data Sources:   | ATMCNFG                                                                |
| Desktop Access: | Configure > ATM (Java) > ATM Load Profile                              |
| Messages:       | ATMLoadProfileDeleteRq<br>ATMLoadProfileListRq<br>ATMLoadProfileViewRq |

## ATM Load Timeout Profile Configuration Window

|                 |                                                                                                                                 |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMLdTmtProfile                                                                                                                 |
| Permissions:    | FullATMLoadTimerPrflPermission<br>ViewATMLoadTimerPrflPermission                                                                |
| Help ID:        | w_atm_load_timeout_profile_configuration                                                                                        |
| Data Sources:   | LTMRPRFL                                                                                                                        |
| Desktop Access: | Configure > ATM (Java) > ATM Load Timeout Profile                                                                               |
| Messages:       | ATMLdTmtProfileInsertRq<br>ATMLdTmtProfileListRq<br>ATMLdTmtProfileViewRq<br>ATMLdTmtProfileUpdateRq<br>ATMLdTmtProfileDeleteRq |

## ATM MAC Profile Configuration Window

|                 |                                                                                                                       |
|-----------------|-----------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHMacProfile                                                                                                       |
| Permissions:    | FullATMDHMacProfilePermission<br>ViewATMDHMacProfilePermission                                                        |
| Help ID:        | w_atm_mac_profile_configuration_cplus                                                                                 |
| Data Sources:   | ATM_MAC                                                                                                               |
| Desktop Access: | Configure > ATM > ATM MAC Profile                                                                                     |
| Messages:       | ATMMacProfileInsertRq<br>ATMMacProfileListRq<br>ATMMacProfileViewRq<br>ATMMacProfileUpdateRq<br>ATMMacProfileDeleteRq |

## ATM MAC Profile Configuration Window

|                 |                                                                                                                       |
|-----------------|-----------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMMacProfile                                                                                                         |
| Permissions:    | FullATMMACProfilePermission<br>ViewATMMACProfilePermission                                                            |
| Help ID:        | w_atm_mac_profile_configuration_java                                                                                  |
| Data Sources:   | ATM_MAC                                                                                                               |
| Desktop Access: | Configure > ATM (Java) > ATM MAC Profile                                                                              |
| Messages:       | ATMMacProfileInsertRq<br>ATMMacProfileListRq<br>ATMMacProfileViewRq<br>ATMMacProfileUpdateRq<br>ATMMacProfileDeleteRq |

## ATM Operation Code Configuration Window

|                 |                                                                                                             |
|-----------------|-------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHOpCodeMapping                                                                                          |
| Permissions:    | FullATMDHOpCodeMapPermission<br>ViewATMDHOpCodeMapPermission                                                |
| Help ID:        | w_atm_operation_code_configuration                                                                          |
| Data Sources:   | ATM_OP_CDE                                                                                                  |
| Desktop Access: | Configure > ATM > ATM Operation Code                                                                        |
| Messages:       | ATMDHOpCodeInsertRq<br>ATMDHOpCodeListRq<br>ATMDHOpCodeViewRq<br>ATMDHOpCodeUpdateRq<br>ATMDHOpCodeDeleteRq |

## ATM Optional Receipt Profile Window

|                 |                                                                                                                                 |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMOptionalReceiptProfile                                                                                                       |
| Permissions:    | FullATMOptnRcptPrflPermission<br>ViewATMOptnRcptPrflPermission                                                                  |
| Help ID:        | w_atm_optional_receipt_profile                                                                                                  |
| Data Sources:   | ATM_OP_CDE                                                                                                                      |
| Desktop Access: | Configure > ATM (Java) > ATM Optional Receipt Profile                                                                           |
| Messages:       | ATMOptnRcptPrflInsertRq<br>ATMOptnRcptPrflListRq<br>ATMOptnRcptPrflViewRq<br>ATMOptnRcptPrflUpdateRq<br>ATMOptnRcptPrflDeleteRq |

## ATM Peak Load Profile Window

|                 |                                                            |
|-----------------|------------------------------------------------------------|
| Task ID:        | ATMDHPeakLoadProfile                                       |
| Permissions:    | n/a                                                        |
| Help ID:        | w_atm_peak_load_profile_configuration                      |
| Data Sources:   | ATM_PEAK_LOAD                                              |
| Desktop Access: | Configure > ATM > ATM Peak Load Profile                    |
| Messages:       | ATMDHPeakLoadProfileViewRq<br>ATMDHPeakLoadProfileUpdateRq |

## ATM Receipt Format Profile Configuration Window

|                 |                                                                                                                                                                                     |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHReceiptFormat                                                                                                                                                                  |
| Permissions:    | FullATMDHRCptFrmtPrflPerm<br>ViewATMDHRCptFrmtPrflPerm                                                                                                                              |
| Help ID:        | w_atm_receipt_format_profile_configuration_cplus                                                                                                                                    |
| Data Sources:   | ATM_RECEIPT                                                                                                                                                                         |
| Desktop Access: | Configure > ATM > ATM Receipt Format Profile                                                                                                                                        |
| Messages:       | ATMDHReceiptFormatInsertRq<br>ATMDHReceiptFormatListRq<br>ATMDHReceiptFormatViewRq<br>ATMDHReceiptFormatUpdateRq<br>ATMDHReceiptFormatDeleteRq<br>ATMDHReceiptFormatGenericDeleteRq |

## ATM Receipt Format Profile Configuration Window

|                 |                                                                                                                                                                                     |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMReceiptFormat                                                                                                                                                                    |
| Permissions:    | FullATMReceiptFormatPermission<br>ViewATMReceiptFormatPermission                                                                                                                    |
| Help ID:        | w_atm_receipt_format_profile_configuration_java                                                                                                                                     |
| Data Sources:   | ATM_RECEIPT                                                                                                                                                                         |
| Desktop Access: | Configure > ATM (Java) > ATM Receipt Format                                                                                                                                         |
| Messages:       | ATMDHReceiptFormatInsertRq<br>ATMDHReceiptFormatListRq<br>ATMDHReceiptFormatViewRq<br>ATMDHReceiptFormatUpdateRq<br>ATMDHReceiptFormatDeleteRq<br>ATMDHReceiptFormatGenericDeleteRq |

## ATM Receipt Required Profile Configuration Window

|                 |                                                                                                                                                                             |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHReceiptRequiredType                                                                                                                                                    |
| Permissions:    | FullATMDHRCptRqdTypPrflPerm<br>ViewATMDHRCptRqdTypPrflPerm                                                                                                                  |
| Help ID:        | w_atm_receipt_required_profile_configuration                                                                                                                                |
| Data Sources:   | ATM_REQ_RCPT                                                                                                                                                                |
| Desktop Access: | Configure > ATM > ATM Receipt Required Profile                                                                                                                              |
| Messages:       | ATMReceiptReqTypeInsertRq<br>ATMReceiptReqTypeListRq<br>ATMReceiptReqTypeViewRq<br>ATMReceiptReqTypeUpdateRq<br>ATMReceiptReqTypeTableDeleteRq<br>ATMReceiptReqTypeDeleteRq |

## ATM Receipt Required Profile Configuration Window

|                 |                                                                                                                                                                             |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMReceiptRequiredType                                                                                                                                                      |
| Permissions:    | FullATMRcptReqTypePermission<br>ViewATMRcptReqTypePermission                                                                                                                |
| Help ID:        | w_atm_receipt_required_profile_configuration                                                                                                                                |
| Data Sources:   | ATM_REQ_RCPT                                                                                                                                                                |
| Desktop Access: | Configure > ATM (Java) > ATM Receipt Required Profile                                                                                                                       |
| Messages:       | ATMReceiptReqTypeInsertRq<br>ATMReceiptReqTypeListRq<br>ATMReceiptReqTypeViewRq<br>ATMReceiptReqTypeUpdateRq<br>ATMReceiptReqTypeTableDeleteRq<br>ATMReceiptReqTypeDeleteRq |

## ATM Reload Map Request Window

|                 |                                                 |
|-----------------|-------------------------------------------------|
| Task ID:        | ATMReloadMaps                                   |
| Permissions:    | FullATMReloadMapsPermission                     |
| Help ID:        | w_atm_reload_map_request                        |
| Data Sources:   | Not specified.                                  |
| Desktop Access: | System Operations > ATM (Java) > ATM Reload Map |
| Messages:       | ATMReloadMapSubmitRq                            |

## ATM State and Screen Configuration Window

|                 |                                                                                                                                             |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | CurrencyConvRateConfiguration                                                                                                               |
| Permissions:    | FullCrncyConvRateCfgPermission<br>ViewCrncyConvRateCfgPermission                                                                            |
| Help ID:        | w_atm_state_and_screen_configuration                                                                                                        |
| Data Sources:   | ATM_STATE_SCRN                                                                                                                              |
| Desktop Access: | Configure > ATM > ATM State and Screen                                                                                                      |
| Messages:       | ATMDHStateScreenInsertRq<br>ATMDHStateScreenListRq<br>ATMDHStateScreenViewRq<br>ATMDHStateScreenUpdateRq<br>ATMDHStateScreenGenericDeleteRq |

## ATM Statement Print Profile Configuration Window

|                 |                                                                                                                                                     |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHStatementPrintProfile                                                                                                                          |
| Permissions:    | FullATMDHStmntPrntPrflPerm<br>ViewATMDHStmntPrntPrflPerm                                                                                            |
| Help ID:        | w_atm_statement_print_profile_configuration                                                                                                         |
| Data Sources:   | ATM_STMNT_PRNT                                                                                                                                      |
| Desktop Access: | Configure > ATM > ATM Statement Print Profile                                                                                                       |
| Messages:       | ATMStmntPrntProfileInsertRq<br>ATMStmntPrntProfileListRq<br>ATMStmntPrntProfileViewRq<br>ATMStmntPrntProfileUpdateRq<br>ATMStmntPrntProfileDeleteRq |

## ATM Statement Print Profile Configuration Window

|                 |                                                                                                                                                     |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMStatementPrintProfile                                                                                                                            |
| Permissions:    | FullATMStmntPrntPrflPermission<br>ViewATMStmntPrntPrflPermission                                                                                    |
| Help ID:        | w_atm_statement_print_profile_configuration                                                                                                         |
| Data Sources:   | ATM_STMNT_PRNT                                                                                                                                      |
| Desktop Access: | Configure > ATM (Java) > ATM Statement Print Profile                                                                                                |
| Messages:       | ATMStmntPrntProfileInsertRq<br>ATMStmntPrntProfileListRq<br>ATMStmntPrntProfileViewRq<br>ATMStmntPrntProfileUpdateRq<br>ATMStmntPrntProfileDeleteRq |



## ATM Status Window

|                 |                                                                |
|-----------------|----------------------------------------------------------------|
| Task ID:        | ATMHardwareStatus                                              |
| Permissions:    | FullATMHardwareStatPermission<br>ViewATMHardwareStatPermission |
| Help ID:        | w_atm_status                                                   |
| Data Sources:   | ATM_DD1                                                        |
| Desktop Access: | System Operations > ATM > ATM Status                           |
| Messages:       | ATMDHStatusListRq<br>ATMDHStatusViewRq                         |

## ATM Status Query Window

|                 |                                                                  |
|-----------------|------------------------------------------------------------------|
| Task ID:        | ATMDHStatusQuery                                                 |
| Permissions:    | FullATMDHStatusQueryPermission<br>ViewATMDHStatusQueryPermission |
| Help ID:        | w_atm_status_query_cplus                                         |
| Data Sources:   | n/a                                                              |
| Desktop Access: | System Operations > ATM > ATM Status Query                       |
| Messages:       | ATMStatusViewRq                                                  |

## ATM Status Query Window

|                 |                                                   |
|-----------------|---------------------------------------------------|
| Task ID:        | ATMStatusQuery                                    |
| Permissions:    | FullATMStatusQueryPermission                      |
| Help ID:        | w_atm_status_query_java                           |
| Data Sources:   | ESATDD1<br>ESATDS1                                |
| Desktop Access: | System Operations > ATM (Java) > ATM Status Query |
| Messages:       | ATMStatusViewRq                                   |

## ATM Surcharge Profile Configuration Window

|                 |                                                                                                                                                     |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMDHSurchargeProfile                                                                                                                               |
| Permissions:    | FullATMDHSurchargePrflPerm<br>ViewATMDHSurchargePrflPerm                                                                                            |
| Help ID:        | w_atm_surcharge_profile_configuration_cplus                                                                                                         |
| Data Sources:   | ATM_SUR                                                                                                                                             |
| Desktop Access: | Configure > ATM > ATM Surcharge Profile                                                                                                             |
| Messages:       | ATMSurchargeProfileInsertRq<br>ATMSurchargeProfileListRq<br>ATMSurchargeProfileViewRq<br>ATMSurchargeProfileUpdateRq<br>ATMSurchargeProfileDeleteRq |

## ATM Surcharge Profile Configuration Window

|                 |                                                                                                                                                     |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMSurchargeProfile                                                                                                                                 |
| Permissions:    | FullATMSurchPrflPermission<br>ViewATMSurchPrflPermission                                                                                            |
| Help ID:        | w_atm_surcharge_profile_configuration_java                                                                                                          |
| Data Sources:   | ATM_SUR                                                                                                                                             |
| Desktop Access: | Configure > ATM (Java) > ATM Surcharge Profile                                                                                                      |
| Messages:       | ATMSurchargeProfileInsertRq<br>ATMSurchargeProfileListRq<br>ATMSurchargeProfileViewRq<br>ATMSurchargeProfileUpdateRq<br>ATMSurchargeProfileDeleteRq |

## ATM Totals Window

|                 |                                                            |
|-----------------|------------------------------------------------------------|
| Task ID:        | ATMDHTotals                                                |
| Permissions:    | FullATMDHTotalsPermission<br>ViewATMDHTotalsPermission     |
| Help ID:        | w_atm_totals                                               |
| Data Sources:   | ATM_DD1<br>ATM_DS1<br>ATM_HOPR<br>ATM_PREV_TTL<br>ATM_PRFL |
| Desktop Access: | System Operations > ATM > ATM Totals                       |
| Messages:       | ATMDHTotalsCurViewRq<br>ATMDHTotalsPrvViewRq               |

## Audit Store and Forward (SAF) Configuration Window

|                 |                                                              |
|-----------------|--------------------------------------------------------------|
| Task ID:        | AuditSAFConfig                                               |
| Permissions:    | FullAuditSAFConfigPermission<br>ViewAuditSAFConfigPermission |
| Help ID:        | w_audit_store_and_forward_configuration                      |
| Data Sources:   | Audit_Store_and_Forward                                      |
| Desktop Access: | System Operations > Audit SAF                                |
| Messages:       | AuditSAFViewRq<br>AuditSAFUpdateRq                           |

## Authentication Profile Configuration Window

|                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | AuthenticationConfiguration                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| Permissions:    | FullAuthentConfigPermission<br>ViewAuthentConfigPermission                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| Help ID:        | UnknownHelpID                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Data Sources:   | Card_Verification<br>Diebold_Number_Table<br>Dynamic_Card_Verification<br>EMV_Security<br>IBM_DES<br>Identikey<br>NCR_PIN_Verification<br>Visa_PVV                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Desktop Access: | Configure > Transaction Security > Authentication Profile                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Messages:       | AuthentCnfgCardProfilesRq<br>AuthentCnfgIdentikeyProfilesRq<br>AuthentCnfgPinProfilesRq<br>AuthentCnfgInsertDNTRq<br>AuthentCnfgSummaryViewRq<br>AuthentCnfgViewDNTRq<br>AuthentCnfgUpdateDNTRq<br>AuthentCnfgViewDNTRq<br>AuthentCnfgDeleteRq<br>AuthentCnfgProfileDeleteRq<br>AuthentCnfgInsertNCRRq<br>AuthentCnfgNCRProfilesRq<br>AuthentCnfgViewNCRRq<br>AuthentCnfgUpdateNCRRq<br>AuthentCnfgInsertEMVRq<br>AuthentCnfgEMVProfilesRq<br>AuthentCnfgViewEMVRq<br>AuthentCnfgUpdateEMVRq<br>AuthentCnfgInsertIdentikeyRq<br>AuthentCnfgViewIdentikeyRq<br>AuthentCnfgUpdateIdentikeyRq<br>AuthentCnfgInsertRq<br>AuthentCnfgViewRq<br>AuthentCnfgUpdateRq |

## Authorization Script Configuration Window

|                      |                                                                                                                                     |
|----------------------|-------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:             | AuthScript                                                                                                                          |
| Permissions:         | FullAuthScriptPermission<br>ViewAuthScriptPermission                                                                                |
| Related Permissions: | FullScriptRepository<br>ViewScriptRepository                                                                                        |
| Help ID:             | w_authorization_script_configuration                                                                                                |
| Data Sources:        | Authorization_Script                                                                                                                |
| Desktop Access:      | Configure > Script > Authorization Script                                                                                           |
| Messages:            | AuthScriptListRq<br>AuthScriptInsertRq<br>AuthScriptViewRq<br>AuthScriptUpdateRq<br>AuthScriptDeleteRq<br>AuthScriptGenericDeleteRq |

## Banknet Acquirers Configuration Window

|                 |                                                                                                                    |
|-----------------|--------------------------------------------------------------------------------------------------------------------|
| Task ID:        | BanknetAcquirers                                                                                                   |
| Permissions:    | FullBanknetAcquirersPermission<br>ViewBanknetAcquirersPermission                                                   |
| Help ID:        | w_banknet_acquirers_configuration                                                                                  |
| Data Sources:   | Banknet_Institution_Id                                                                                             |
| Desktop Access: | Configure > Interface > Network > BankNet > Banknet Acquirers                                                      |
| Messages:       | BanknetInstitutionInsertRq<br>BanknetInstitutionDeleteRq<br>BanknetInstitutionUpdateRq<br>BanknetInstitutionViewRq |

## BankNet ISO Interface Configuration Window

|                 |                                                                                                                                    |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | BanknetInterface                                                                                                                   |
| Permissions:    | FullBanknetInterfacePermission<br>ViewBanknetInterfacePermission                                                                   |
| Help ID:        | w_banknet_iso_interface_configuration                                                                                              |
| Data Sources:   | Banknet_Configuration<br>Interface<br>Interface_SAF<br>Interface_Station                                                           |
| Desktop Access: | Configure > Interface > Network > BankNet ISO                                                                                      |
| Messages:       | BanknetMerchantProgramInsertRq<br>BanknetMerchantProgramViewRq<br>BanknetMerchantProgramUpdateRq<br>BanknetMerchantProgramDeleteRq |

## (Banknet) Merchant Programs Window

|                 |                                                                                                                                    |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | BanknetMerchantProgram                                                                                                             |
| Permissions:    | FullBanknetMerchProgPermission                                                                                                     |
| Help ID:        | w_merchant_programs_configuration                                                                                                  |
| Data Sources:   | Banknet_Merchant_Program                                                                                                           |
| Desktop Access: | Configure > Interface > Network > Banknet > Merchant Programs                                                                      |
| Messages:       | BanknetMerchantProgramInsertRq<br>BanknetMerchantProgramDeleteRq<br>BanknetMerchantProgramUpdateRq<br>BanknetMerchantProgramViewRq |

## BASE24 ISO8583 Host Interface Configuration Window

|                 |                                                                             |
|-----------------|-----------------------------------------------------------------------------|
| Task ID:        | B24HISOInterfaceConfig                                                      |
| Permissions:    | FullB24HISOIFConfigPermission<br>ViewB24HISOIFConfigPermission              |
| Help ID:        | w_base24_iso8583_host_interface_configuration                               |
| Data Sources:   | HISO87_Interface<br>Interface<br>Interface_SAF<br>Interface_Station         |
| Desktop Access: | Configure > Interface > Host > BASE24 ISO8583 Host ><br>BASE24 ISO8583 Host |
| Messages:       | HISO87InsertRq<br>HISO87ViewRq<br>HISO87UpdateRq<br>HISO87DeleteRq          |

## BASE24 KEYF Configuration Window

|                 |                                                                         |
|-----------------|-------------------------------------------------------------------------|
| Task ID:        | B24KEYFSecurity                                                         |
| Permissions:    | FullB24KEYFSecuritPermission<br>ViewB24KEYFSecuritPermission            |
| Help ID:        | w_base24_keyf_configuration                                             |
| Data Sources:   | BASE24_KEYF                                                             |
| Desktop Access: | Configure > BASE24 > KEYF                                               |
| Messages:       | B24KEYFGetFIIDListRq<br>B24KEYFInsertRq<br>B24KEYFGetSymbolicNameListRq |

## BASE24-atm Transaction Mapping Profile Configuration Window

|                 |                                                                                                                                                                                                                                                                                                                         |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | B24AtmTranMapping                                                                                                                                                                                                                                                                                                       |
| Permissions:    | FullB24ATMTranMapPermission<br>ViewB24ATMTranMapPermission                                                                                                                                                                                                                                                              |
| Help ID:        | w_base24atm_transaction_mapping_profile                                                                                                                                                                                                                                                                                 |
| Data Sources:   | ATM_TC_Proc_Code<br>Proc_Code_ATM_TC                                                                                                                                                                                                                                                                                    |
| Desktop Access: | Configure > BASE24 > Transaction Mapping > ATM                                                                                                                                                                                                                                                                          |
| Messages:       | B24AtmTranMappingListRq<br>B24AtmTranMappingInbInsertRq<br>B24AtmTranMappingOutInsertRq<br>B24AtmTranMappingInbViewRq<br>B24AtmTranMappingInbUpdateRq<br>B24AtmTranMappingOutViewRq<br>B24AtmTranMappingOutUpdateRq<br>B24AtmTranMappingInbDeleteRq<br>B24AtmTranMappingOutDeleteRq<br>B24AtmTranMappingGenericDeleteRq |



## BASE24-pos Transaction Mapping Profile Configuration Window

|                 |                                                                                                                                                                                                                                                                                                                         |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | B24PosTranMapping                                                                                                                                                                                                                                                                                                       |
| Permissions:    | FullB24POSTranMapPermission<br>ViewB24POSTranMapPermission                                                                                                                                                                                                                                                              |
| Help ID:        | w_base24pos_transaction_mapping_profile                                                                                                                                                                                                                                                                                 |
| Data Sources:   | POS_TC_Proc_Code<br>Proc_Code_POS_TC                                                                                                                                                                                                                                                                                    |
| Desktop Access: | Configure > BASE24 > Transaction Mapping > POS                                                                                                                                                                                                                                                                          |
| Messages:       | B24PosTranMappingListRq<br>B24PosTranMappingInbInsertRq<br>B24PosTranMappingOutInsertRq<br>B24PosTranMappingInbViewRq<br>B24PosTranMappingInbUpdateRq<br>B24PosTranMappingOutViewRq<br>B24PosTranMappingOutUpdateRq<br>B24PosTranMappingInbDeleteRq<br>B24PosTranMappingOutDeleteRq<br>B24PosTranMappingGenericDeleteRq |

## BIC ISO (87) Interface Configuration Window

|                 |                                                                  |
|-----------------|------------------------------------------------------------------|
| Task ID:        | BicIsoInterface                                                  |
| Permissions:    | FullBicIsoInterfacePermission                                    |
| Help ID:        | w_bic_iso_87_interface_configuration                             |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>BIC_Interface |
| Desktop Access: | Configure > Interface > Network > BIC ISO (87)                   |
| Messages:       | n/a                                                              |

## BNTng Key Header Configuration Window

|                 |                                                                                                             |
|-----------------|-------------------------------------------------------------------------------------------------------------|
| Task ID:        | BNTngHeaderConfig                                                                                           |
| Permissions:    | FullBNTngHdrCnfgPermission<br>ViewBNTngHdrCnfgPermission                                                    |
| Help ID:        | w_bntng_key_header_configuration                                                                            |
| Data Sources:   | BNTng_Header                                                                                                |
| Desktop Access: | Configure > Transaction Security > BNTng Header                                                             |
| Messages:       | BNTngHeaderInsertRq<br>BNTngHeaderListRq<br>BNTngHeaderViewRq<br>BNTngHeaderUpdateRq<br>BNTngHeaderDeleteRq |

## COOP Interface Configuration Window

|                 |                                                                     |
|-----------------|---------------------------------------------------------------------|
| Task ID:        | CoopInterface                                                       |
| Permissions:    | FullCoopInterfacePermission                                         |
| Help ID:        | n/a                                                                 |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>EFunds_Interface |
| Desktop Access: | Configure > Interface > Network > COOP                              |
| Messages:       | n/a                                                                 |

## Cache Administration Window

|                 |                                                                                         |
|-----------------|-----------------------------------------------------------------------------------------|
| Task ID:        | IWTCacheAdministration                                                                  |
| Permissions:    | FullIWTCacheAdminPermission<br>ViewIWTCacheAdminstratioin                               |
| Help ID:        | w_cache_administration                                                                  |
| Data Sources:   | Not specified.                                                                          |
| Desktop Access: | System Operations > Server Management > Server<br>Administration > Cache Administration |
| Messages:       | IWTFCacheAdminListRq<br>IWTFCacheAdminResetRq                                           |

## Card Management Window

|                 |                                                                                                                                                                                                                                                                                                                                                                                                    |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | CardConfiguration<br>CardAccount<br>CardLimit<br>CardLimits<br>CardStatus<br>FindCard                                                                                                                                                                                                                                                                                                              |
| Permissions:    | FullCardConfigPermission<br>ViewCardConfigPermission<br>FullCardAccountPermission<br>ViewCardAccountPermission<br>FullCardAddressPermission<br>ViewCardAddressPermission<br>FullCardLimitPermission<br>ViewCardLimitPermission<br>FullCardLimitsPermission<br>ViewCardLimitsPermission<br>FullCardStatusPermission<br>ViewCardStatusPermission<br>FullFindCardPermission<br>ViewFindCardPermission |
| Help ID:        | w_card_management                                                                                                                                                                                                                                                                                                                                                                                  |
| Data Sources:   | Card<br>Card_Account<br>Environment                                                                                                                                                                                                                                                                                                                                                                |
| Desktop Access: | Customer Management > Card                                                                                                                                                                                                                                                                                                                                                                         |
| Messages:       | CardEnvParamRq<br>CardInsertRq<br>CardPANListRq<br>CardAcctInsertRq<br>CardViewRq<br>CardUpdateRq<br>CardAcctViewRq<br>CardAcctUpdateRq<br>CardAcctDeleteRq<br>CardDeleteRq                                                                                                                                                                                                                        |

## Certificate Management Window

|                 |                                                                                           |
|-----------------|-------------------------------------------------------------------------------------------|
| Task ID:        | Certificate                                                                               |
| Permissions:    | FullCertificatePermission<br>ViewCertificatePermission                                    |
| Help ID:        | w_certificate_management                                                                  |
| Data Sources:   | Not specified.                                                                            |
| Desktop Access: | Configure > Transaction Security > Automated Key<br>Distribution > Certificate Management |
| Messages:       | CertGenMesgDigestRq<br>CertGetPublicKeyDataRq<br>CertValidateRq                           |

## Channel Public Key Perusal Window

|                 |                                                                   |
|-----------------|-------------------------------------------------------------------|
| Task ID:        | ChannelPKPerusal                                                  |
| Permissions:    | FullChannelPKPerusalPermission<br>ViewChannelPKPerusalPermission  |
| Help ID:        | w_channel_public_key_perusal                                      |
| Data Sources:   | Channel_Public_Key_Security                                       |
| Desktop Access: | View > Automated Key Distribution > Channel Public Key<br>Perusal |
| Messages:       | ChannelPubKeyListRq                                               |

## Channel Security Configuration Window

|                 |                                                                |
|-----------------|----------------------------------------------------------------|
| Task ID:        | ChannelSecurity                                                |
| Permissions:    | FullChannelSecurityPermission<br>ViewChannelSecurityPermission |
| Help ID:        | w_channel_security_configuration                               |
| Data Sources:   | Channel_Security                                               |
| Desktop Access: | Configure > Transaction Security > Channel                     |
| Messages:       | ChannelIDSecurListGetRq<br>ChannelListGetRq                    |

## Configuration Properties Window

|                 |                                                                                          |
|-----------------|------------------------------------------------------------------------------------------|
| Task ID:        | IWTConfigurationAdministration                                                           |
| Permissions:    | FullIWTConfigAdminPermission<br>ViewIWTConfigurationAdmin                                |
| Help ID:        | w_configuration_properties                                                               |
| Data Sources:   | Not specified.                                                                           |
| Desktop Access: | System Operations > Server Management > Server Administration > Configuration Properties |
| Messages:       | IWTFCfgPropertiesListRq<br>IWTFCfgPropertiesReloadRq                                     |

## Context Profile Configuration Window

|                 |                                                                                                                       |
|-----------------|-----------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ContextConfiguration                                                                                                  |
| Permissions:    | FullContextConfigPermission<br>ViewContextConfigPermission                                                            |
| Help ID:        | w_context_profile_configuration                                                                                       |
| Data Sources:   | Context_Configuration                                                                                                 |
| Desktop Access: | Configure > Interface > Context Profile                                                                               |
| Messages:       | ContextConfigInsertRq<br>ContextConfigListRq<br>ContextConfigViewRq<br>ContextConfigUpdateRq<br>ContextConfigDeleteRq |

## Contingency Interface Configuration Window

|                 |                                            |
|-----------------|--------------------------------------------|
| Task ID:        | ContingencyInterface                       |
| Permissions:    | FullContingencyInterface                   |
| Help ID:        | w_contingency_interface_configuration      |
| Data Sources:   | Contingency_Interface                      |
| Desktop Access: | Configure > Interface > Host > Contingency |
| Messages:       | Not specified.                             |

## Contingency Store and Forward (SAF) Configuration Window

|                 |                                                              |
|-----------------|--------------------------------------------------------------|
| Task ID:        | ContingencySAF                                               |
| Permissions:    | FullContingencySAFPermission<br>ViewContingencySAFPermission |
| Help ID:        | w_contingency_store_and_forward                              |
| Data Sources:   | Store_and_Forward                                            |
| Desktop Access: | System Operations > Contingency SAF                          |
| Messages:       | ContingencySAFCnfgViewRq<br>ContingencySAFCnfgUpdateRq       |

## Credit Union 24 (CU24) Institution Configuraiton Window

|                 |                                                                                                  |
|-----------------|--------------------------------------------------------------------------------------------------|
| Task ID:        | Cu24Institution                                                                                  |
| Permissions:    | FullCu24InstitutionPermission                                                                    |
| Help ID:        | n/a                                                                                              |
| Data Sources:   | n/a                                                                                              |
| Desktop Access: | Configure > Interface > Network > Credit Union 24 (CU24) ><br>Credit Union 24 (CU24) Institution |
| Messages:       | n/a                                                                                              |

## Credit Union 24 (CU24) Interface Configuration Window

|                 |                                                                                                |
|-----------------|------------------------------------------------------------------------------------------------|
| Task ID:        | Cu24Interface                                                                                  |
| Permissions:    | FullCu24InterfacePermission                                                                    |
| Help ID:        | n/a                                                                                            |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station                                                |
| Desktop Access: | Configure > Interface > Network > Credit Union 24 (CU24) ><br>Credit Union 24 (CU24) Interface |
| Messages:       | n/a                                                                                            |

## CSC Interface Configuration Window

|                 |                                                                     |
|-----------------|---------------------------------------------------------------------|
| Task ID:        | CSC                                                                 |
| Permissions:    | FullCSCPermission<br>ViewCSCPermission                              |
| Help ID:        | w_iso_93_host_interface_configuration                               |
| Data Sources:   | HISO93_Interface<br>Interface<br>Interface_SAF<br>Interface_Station |
| Desktop Access: | Configure > Interface > Host > CSC Interface                        |
| Messages:       | Not specified.                                                      |

## Currency Conversion Rate Configuration Window

|                 |                                                                                                                           |
|-----------------|---------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | CurrencyConvRateConfiguration                                                                                             |
| Permissions:    | FullCrncyConvRateCfgPermission<br>ViewCurrencyConvRateConfig                                                              |
| Help ID:        | w_currency_conversion_rate_configuration                                                                                  |
| Data Sources:   | Currency_Conversion_Rate                                                                                                  |
| Desktop Access: | Configure > Currency Conversion > Currency Conversion<br>Rate                                                             |
| Messages:       | CurrConvRateInsertRq<br>CurrConvRateListRq<br>CurrConvRateUpdateRq<br>CurrConvRateDeleteRq<br>CurrConvRateGenericDeleteRq |



## Database Administration Window

|                 |                                                                                         |
|-----------------|-----------------------------------------------------------------------------------------|
| Task ID:        | IWTDatabaseAdministration                                                               |
| Permissions:    | FullIWTDatabaseAdminPermission<br>ViewIWTDatabaseAdministration                         |
| Help ID:        | w_database_administration                                                               |
| Data Sources:   | Not specified.                                                                          |
| Desktop Access: | System Operations > Server Management > Server Administration > Database Administration |
| Messages:       | IWTFDBConnectionAdminViewRq                                                             |

## Destination Routing Profile Configuration Window

|                 |                                                                         |
|-----------------|-------------------------------------------------------------------------|
| Task ID:        | IssuerProfileConfig                                                     |
| Permissions:    | FullIssProfConfigPermission<br>ViewIssuerProfileConfig                  |
| Help ID:        | w_destination_routing_profile_configuration                             |
| Data Sources:   | Issuer_Route_Profile                                                    |
| Desktop Access: | Configure > Routing > Profile Description > Destination Routing Profile |
| Messages:       | Not specified.                                                          |

## Disable KEYGEN Window

|                 |                                                                                |
|-----------------|--------------------------------------------------------------------------------|
| Task ID:        | KEYGENLockdown                                                                 |
| Permissions:    | FullKEYGENLockdownPermission<br>ViewKEYGENLockdownPermission                   |
| Help ID:        | w_disable_keygen                                                               |
| Data Sources:   | not specified.                                                                 |
| Desktop Access: | Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN |
| Messages:       | DisableKeyGenViewRq<br>DisableKeyGenUpdateRq                                   |

## DUKPT Derivation Key Profile Configuration Window

|                 |                                                                                           |
|-----------------|-------------------------------------------------------------------------------------------|
| Task ID:        | B24SPDHDKPTDerivationKey                                                                  |
| Permissions:    | FullB24SPDHDKPTDKeyPermission<br>ViewB24SPDHDKPTDKeyPermission                            |
| Help ID:        | w_dukpt_derivation_key_profile_configuration                                              |
| Data Sources:   | Derivation_Key                                                                            |
| Desktop Access: | Configure > Transaction Security > DUKPT Derivation Key Profile                           |
| Messages:       | DrvKeyInsertRq<br>DrvKeyProfileListRq<br>DrvKeyViewRq<br>DrvKeyUpdateRq<br>DrvKeyDeleteRq |

## EMV Card Verification Results (CVR) Results Status Window

|                 |                                                                                                                                                |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | EMVCardVerifResultsStatusUI                                                                                                                    |
| Permissions:    | FullEMVCrdVrfRsItsStatUIPerm                                                                                                                   |
| Help ID:        | w_emv_card_verification_results_status_configuration                                                                                           |
| Data Sources:   | EMV_Card_Vrfn_Results_Status                                                                                                                   |
| Desktop Access: | Configure > EMV > Card Verification Results Status                                                                                             |
| Messages:       | EMVCardVerifResultsDetailListRq<br>EMVCardVerifResultsDetailInsertRq<br>EMVCardVerifResultsDetailUpdateRq<br>EMVCardVerifResultsDetailDeleteRq |

## EMV Reason Online Code (ROC) Description Configuration

|                 |                                                                                                                                                                                                                                                                       |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | EMVReasonOnlineCodeDescrUI                                                                                                                                                                                                                                            |
| Permissions:    | FullEMVReasonOnlCdeDscrUIPerm                                                                                                                                                                                                                                         |
| Help ID:        | w_emv_reason_online_code_description_configuration                                                                                                                                                                                                                    |
| Data Sources:   | Reason_Online_Code_Description                                                                                                                                                                                                                                        |
| Desktop Access: | Configure > EMV > Reason Online Code Description                                                                                                                                                                                                                      |
| Messages:       | EMVReasonOnlineCodeDescrViewRq<br>EMVReasonOnlineCodeDescrInsertRq<br>EMVReasonOnlineCodeDescrInsertRqEntry<br>EMVReasonOnlineCodeDescrUpdateRq<br>EMVReasonOnlineCodeDescrUpdateRqEntry<br>EMVReasonOnlineCodeDescrDeleteRq<br>EMVReasonOnlineCodeDescrDeleteRqEntry |

## EMV Reason Online Code Status Window

|                 |                                                                                                                                                                                                                                         |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | EMVReasonOnlineCodeStatusUI                                                                                                                                                                                                             |
| Permissions:    | FullEMVReasonOnlCdeStatUIPerm                                                                                                                                                                                                           |
| Help ID:        | w_emv_reason_online_code_status_configuration                                                                                                                                                                                           |
| Data Sources:   | EMV_Reason_Online_Code_Status                                                                                                                                                                                                           |
| Desktop Access: | Configure > EMV > Reason Online Code Status                                                                                                                                                                                             |
| Messages:       | EMVReasonOnlineCodeViewRq<br>EMVReasonOnlineCodeInsertRq<br>EMVReasonOnlineCodeInsertRqEntry<br>EMVReasonOnlineCodeUpdateRq<br>EMVReasonOnlineCodeUpdateRqEntry<br>EMVReasonOnlineCodeDeleteRqEntry<br>EMVReasonOnlineCodeDeleteRqEntry |

## EMV Terminal Verification Results Status Window

|                 |                                                                                                                                                                                                                              |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | EMVTermVerifResultsStatusUI                                                                                                                                                                                                  |
| Permissions:    | FullEMVTrmVrfRsItsStatUIPerm                                                                                                                                                                                                 |
| Help ID:        | w_emv_terminal_verification_results_status_configuration                                                                                                                                                                     |
| Data Sources:   | EMV_Terminal_Vrfn_Results_Status                                                                                                                                                                                             |
| Desktop Access: | Configure > EMV > EMV Terminal Verification Results Status                                                                                                                                                                   |
| Messages:       | EMVTerminalVerifResultsDetailListRq<br>EMVTerminalVerifResultsInsertRq<br>EMVTerminalVerifResultsInsertRqEntry<br>EMVTerminalVerifResultsInsertRsEntry<br>EMVTerminalVerifResultsUpdateRq<br>EMVTerminalVerifResultsDeleteRq |

## Environment Configuration Window

|                 |                                                                                        |
|-----------------|----------------------------------------------------------------------------------------|
| Task ID:        | EnvironmentManagement                                                                  |
| Permissions:    | FullEnvironmentMgmtPermission<br>ViewEnvironmentMgmtPermission                         |
| Help ID:        | w_environment_configuration                                                            |
| Data Sources:   | Environment                                                                            |
| Desktop Access: | System Operations > Environment                                                        |
| Messages:       | EnvironmentInsertRq<br>EnvironmentViewRq<br>EnvironmentUpdateRq<br>EnvironmentDeleteRq |

## EPP Serial Number Configuration Window

|                 |                                                                                      |
|-----------------|--------------------------------------------------------------------------------------|
| Task ID:        | EPPSerialNumberConfig                                                                |
| Permissions:    | FullEPPSerialNumCfgPermission<br>ViewEPPSerialNumCfgPermission                       |
| Help ID:        | w_epp_serial_number_configuration                                                    |
| Data Sources:   | EPP_Serial_Number                                                                    |
| Desktop Access: | Configure > Transaction Security > Automated Key<br>Distribution > EPP Serial Number |
| Messages:       | EPPSerNumInsertRq<br>EPPSerNumViewRq<br>EPPSerNumUpdateRq<br>EPPSerNumDeleteRq       |

## EPS-Net Institution Configuration Window

|                 |                                                                                                                                           |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | EPSNetInstitution                                                                                                                         |
| Permissions:    | FullEPSNetInstPermission<br>ViewEPSNetInstPermission                                                                                      |
| Help ID:        | w_epsnet_institution_configuration                                                                                                        |
| Data Sources:   | EPSNET_Inst                                                                                                                               |
| Desktop Access: | Configure > Interface > Network > EPS-Net > EPS-Net<br>Institution                                                                        |
| Messages:       | EPSNetInstitutionInsertRq<br>EPSNetInstitutionListRq<br>EPSNetInstitutionViewRq<br>EPSNetInstitutionUpdateRq<br>EPSNetInstitutionDeleteRq |

## EPS-Net ISO Interface Configuration Window

|                 |                                                                     |
|-----------------|---------------------------------------------------------------------|
| Task ID:        | EPSNetInterfaceConfiguration                                        |
| Permissions:    | FullEPSNetInterfacePermission<br>ViewEPSNetInterfacePermission      |
| Help ID:        | w_epsnet_iso_interface_configuration                                |
| Data Sources:   | EPSNET_Interface<br>Interface<br>Interface_SAF<br>Interface_Station |
| Desktop Access: | Configure > Interface > Network > EPS-Net > EPS-Net ISO             |
| Messages:       | EPSNetInsertRq<br>EPSNetViewRq<br>EPSNetUpdateRq<br>EPSNetDeleteRq  |

## Euro Opted Currency Configuration Window

|                 |                                                                                        |
|-----------------|----------------------------------------------------------------------------------------|
| Task ID:        | EuroOptedCurrencyConfiguration                                                         |
| Permissions:    | FullEuroOptedCurrCfgPermission<br>ViewEuroOptedCurrencyConfig                          |
| Help ID:        | w_euro_opted_currency_configuration                                                    |
| Data Sources:   | Euro_Opted_Currency                                                                    |
| Desktop Access: | Configure > Currency Conversion > Euro Opted Currency                                  |
| Messages:       | EuroOptCurrInsertRq<br>EuroOptCurrListRq<br>EuroOptCurrUpdateRq<br>EuroOptCurrDeleteRq |

## Event Configuration and Management Window

|                 |                                                     |
|-----------------|-----------------------------------------------------|
| Task ID:        | EventConfiguration                                  |
| Permissions:    | FullEventConfigPermission<br>ViewEventConfiguration |
| Help ID:        | w_integrated_server_event_configuration             |
| Data Sources:   | Event                                               |
| Desktop Access: | System Operations > Event > Event Management        |
| Messages:       | Not specified.                                      |

## Event Perusal Window

|                 |                                                          |
|-----------------|----------------------------------------------------------|
| Task ID:        | EventPerusal                                             |
| Permissions:    | FullEventPerusalPermission<br>ViewEventPerusalPermission |
| Help ID:        | w_event_perusal                                          |
| Data Sources:   | EVNTLOG                                                  |
| Desktop Access: | System Operations > Event > Event Perusal                |
| Messages:       | EventPerusalViewRq                                       |

## Event Subsystem ID Configuration Window

|                 |                                                          |
|-----------------|----------------------------------------------------------|
| Task ID:        | EventSubsystemConfiguration                              |
| Permissions:    | FullEventSubConfigPermission<br>ViewEventSubsystemConfig |
| Help ID:        | w_event_subsystem_id_configuration                       |
| Data Sources:   | Event_Document                                           |
| Desktop Access: | System Operations > Event > Subsystem ID                 |
| Messages:       | Not specified.                                           |

## Exported Operators Configuration Window

|                 |                                                                                         |
|-----------------|-----------------------------------------------------------------------------------------|
| Task ID:        | ExportedOperator                                                                        |
| Permissions:    | FullExportedOperatorPermission<br>ViewExportedOperatorPermission                        |
| Help ID:        | w_exported_operators_configuration                                                      |
| Data Sources:   | Exported_Operator_Documentation                                                         |
| Desktop Access: | Configure > Script > Exported Operators                                                 |
| Messages:       | ExpOperListRq<br>ExpOperInsertRq<br>ExpOperViewRq<br>ExpOperUpdateRq<br>ExpOperDeleteRq |

## External Connection Configuration Window

|                 |                                                                                                                                 |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | IWTConnectionConfig                                                                                                             |
| Permissions:    | FullIWTConnectionCfgPermission<br>ViewIWTConnectionCfgPermission                                                                |
| Help ID:        | w_external_connection_configuration                                                                                             |
| Data Sources:   | EXTRCNCT                                                                                                                        |
| Desktop Access: | System Operations > Server Management > External Connection                                                                     |
| Messages:       | IWTFCConnectionListRq<br>IWTFCConnectionInsertRq<br>IWTFCConnectionViewRq<br>IWTFCConnectionUpdateRq<br>IWTFCConnectionDeleteRq |



## File Partition Configuration Window

|                 |                                                                                                                                                            |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | FilePartition                                                                                                                                              |
| Permissions:    | FullFilePartitionPermission<br>ViewFilePartitionPermission                                                                                                 |
| Help ID:        | w_file_partition_configuration                                                                                                                             |
| Data Sources:   | file_part_fields<br>file_part_list                                                                                                                         |
| Desktop Access: | System Operations > Database Management > File Partition                                                                                                   |
| Messages:       | FilePartAssgnFieldsListRq<br>FilePartAssgnListRq<br>FilePartCatalogInsertRq<br>FilePartCatalogUpdateRq<br>FilePartCatalogViewRq<br>FilePartGenericDeleteRq |

## File Update Router Configuration Window

|                 |                                                                                                          |
|-----------------|----------------------------------------------------------------------------------------------------------|
| Task ID:        | FileUpdateRouterConfig                                                                                   |
| Permissions:    | FullFileUpdateRouterConfigPerm<br>ViewFileUpdateRouterConfigPerm                                         |
| Help ID:        | w_file_update_router_configuration                                                                       |
| Data Sources:   | File_Update_Route                                                                                        |
| Desktop Access: | Configure > Routing > File Update Router                                                                 |
| Messages:       | FilUpdRtrInsertRq<br>FilUpdRtrListRq<br>FilUpdRtrViewRq<br>FilUpdRtrDeleteRq<br>FilUpdRtrGenericDeleteRq |

## Host Public Key Perusal Window

|                 |                                                                        |
|-----------------|------------------------------------------------------------------------|
| Task ID:        | HostPKPerusal                                                          |
| Permissions:    | FullHostPKPerusalPermission<br>ViewHostPKPerusalPermission             |
| Help ID:        | w_host_public_key_perusal                                              |
| Data Sources:   | HOST_Public_Key_Security_Primary<br>HOST_Public_Key_Security_Secondary |
| Desktop Access: | View > Automated Key Distribution > Host Public Key<br>Perusal         |
| Messages:       | HostPubKeyListRq                                                       |

## Hypercom NAC Profile Window

|               |                                                                                        |
|---------------|----------------------------------------------------------------------------------------|
| Task ID:      | HypercomNac                                                                            |
| Permissions:  | FullHypercomNacPermission                                                              |
| Help ID:      | w_hypercom_nac_profile_configuration                                                   |
| Data Sources: | HPDH_NAC_Term                                                                          |
| Data Sources: | Configure > Merchant Processing > Hypercom NAC Profile                                 |
| Messages:     | HypercomNacViewRq<br>HypercomNacInsertRq<br>HypercomNacUpdateRq<br>HypercomNacDeleteRq |

## Hypercom NMS Profile Window

|                 |                                                                                        |
|-----------------|----------------------------------------------------------------------------------------|
| Task ID:        | HypercomNms                                                                            |
| Permissions:    | FullHypercomNmsPermission                                                              |
| Help ID:        | w_hypercom_nms_profile_configuration                                                   |
| Data Sources:   | HPDH_NMS_Term                                                                          |
| Desktop Access: | Configure > Merchant Processing > Hypercom NMS Profile                                 |
| Messages:       | HypercomNmsViewRq<br>HypercomNmsInsertRq<br>HypercomNmsUpdateRq<br>HypercomNmsDeleteRq |

## IFX Host Action Code Profile Configuration Window

|                 |                                                                                                                                                                                                               |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | IFXHostActionCode                                                                                                                                                                                             |
| Permissions:    | FullIFXHostActCdPermission<br>ViewIFXHostActCdPermission                                                                                                                                                      |
| Help ID:        | w_ifx_host_action_code_profile_configuration                                                                                                                                                                  |
| Data Sources:   | IFX_Host_Action_Cod_Int_Ext                                                                                                                                                                                   |
| Desktop Access: | Configure > Interface > Host > IFX Host > IFX Host Action Code Profile                                                                                                                                        |
| Messages:       | IFX Host Action Code Profile<br>IFXHostActionCodeListRq<br>IFXHostActionCodeInsertRq<br>IFXHostActionCodeViewRq<br>IFXHostActionCodeUpdateRq<br>IFXHostActionCodeDeleteRq<br>IFXHostActionCodeGenericDeleteRq |

## IFX Host Interface Configuration Window

|                 |                                                                                                            |
|-----------------|------------------------------------------------------------------------------------------------------------|
| Task ID:        | IFXHostInterface                                                                                           |
| Permissions:    | FullIFXHostIntfPermission<br>ViewIFXHostIntfPermission                                                     |
| Help ID:        | w_ifx_host_interface_configuration                                                                         |
| Data Sources:   | IFX_Host_Interface<br>Interface<br>Interface_SAF<br>Interface_Station                                      |
| Desktop Access: | Configure > Interface > Host > IFX Host > IFX Host Interface                                               |
| Messages:       | IFXHostInterfaceInsertRq<br>IFXHostInterfaceViewRq<br>IFXHostInterfaceUpdateRq<br>IFXHostInterfaceDeleteRq |

## Internal Message Translator (IMT) Interface Configuration Window

|                 |                                                                            |
|-----------------|----------------------------------------------------------------------------|
| Task ID:        | IMTInterface                                                               |
| Permissions:    | FullIMTInterfacePermission<br>ViewIMTInterfacePermission                   |
| Help ID:        | w_imt_interface_configuration                                              |
| Data Sources:   | IMT_Interface<br>Interface<br>Interface_SAF<br>Interface_Station           |
| Desktop Access: | Configure > BASE24 > Internal Message Translator (IMT)                     |
| Messages:       | IMTInsertRequest<br>IMTViewRequest<br>IMTUpdateRequest<br>IMTDeleteRequest |

## Institution Configuration Window

|                 |                                                                                                                                              |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | InstitutionConfiguration                                                                                                                     |
| Permissions:    | FullInstConfigPermission<br>ViewInstConfigPermission                                                                                         |
| Help ID:        | w_institution_configuration                                                                                                                  |
| Data Sources:   | Institution                                                                                                                                  |
| Desktop Access: | Configure > Institution                                                                                                                      |
| Messages:       | InstConfigGetIDListRq<br>InstConfigGetIDListFilteredRq<br>InstConfigInsertRq<br>InstConfigViewRq<br>InstConfigUpdateRq<br>InstConfigDeleteRq |

## Instrument Status Mapping Profile Configuration Window

|                 |                                                                                                                                                                                                                   |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | InstrStatusMappingProfile                                                                                                                                                                                         |
| Permissions:    | FullInstStatMapPrflPermission<br>ViewInstStatMapPrflPermission                                                                                                                                                    |
| Help ID:        | w_instrument_status_mapping_profile_configuration                                                                                                                                                                 |
| Data Sources:   | Instrm_Status_Extrn_to_Intrn                                                                                                                                                                                      |
| Desktop Access: | Configure > Interface > Instrument Status Mapping Profile                                                                                                                                                         |
| Messages:       | InstrumentStatusMappingInsertRq<br>InstrumentStatusMappingListRq<br>InstrumentStatusMappingViewRq<br>InstrumentStatusMappingUpdateRq<br>InstrumentStatusMappingDeleteRq<br>InstrumentStatusMappingGenericDeleteRq |

## Instrument Type Window

|                 |                                                                                                    |
|-----------------|----------------------------------------------------------------------------------------------------|
| Task ID:        | InstrumentTypeCnfg                                                                                 |
| Permissions:    | FullInstrumentTypePermission                                                                       |
| Help ID:        | w_instrument_type_configuration                                                                    |
| Data Sources:   | Instrument_Type                                                                                    |
| Desktop Access: | Configure > Instrument Type                                                                        |
| Messages:       | InstrumentTypeViewRq<br>InstrumentTypeInsertRq<br>InstrumentTypeUpdateRq<br>InstrumentTypeDeleteRq |

## Instrument Type/Interchange Relationship Configuration Window

|                 |                                                                  |
|-----------------|------------------------------------------------------------------|
| Task ID:        | InstrumentTypeIchgRelation                                       |
| Permissions:    | FullInstTypIchgRelPermission<br>ViewInstTypIchgRelPermission     |
| Help ID:        | w_instrument_type_interchange_relationship_configuration         |
| Data Sources:   | Instrum_Typ_Interchange_Rel                                      |
| Desktop Access: | Configure > Interface > Instrument Type/Interchange Relationship |
| Messages:       | Not specified.                                                   |

## Interchange Prefix Configuration Window

|                 |                                                                                                                                              |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | InterchangePrefixConfiguration                                                                                                               |
| Permissions:    | FullIchgPrefixConfigPermission<br>ViewIchgPrefixConfigPermission                                                                             |
| Help ID:        | w_interchange_prefix_configuration                                                                                                           |
| Data Sources:   | System_Prefix                                                                                                                                |
| Desktop Access: | Configure > Prefix > Not-On-Us > Interchange Prefix                                                                                          |
| Messages:       | InterchangePrefixInsertRq<br>InterchangePrefixGetFileRq<br>InterchangePrefixViewRq<br>InterchangePrefixUpdateRq<br>InterchangePrefixDeleteRq |

## Interface Security Configuration Window

|                 |                                                                                                                                                                                                                                                                                                                                                                                      |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | InterfaceSecurityConfiguration                                                                                                                                                                                                                                                                                                                                                       |
| Permissions:    | FullIFSecurityConfigPermission<br>ViewIFSecurityConfigPermission                                                                                                                                                                                                                                                                                                                     |
| Help ID:        | Not specified.                                                                                                                                                                                                                                                                                                                                                                       |
| Data Sources:   | Interchange_Security                                                                                                                                                                                                                                                                                                                                                                 |
| Desktop Access: | Configure > Transaction Security > Interface                                                                                                                                                                                                                                                                                                                                         |
| Messages:       | InterfaceSafInsertRq<br>InterfaceSafViewRq<br>InterfaceListRequest<br>InterfaceInsertRequest<br>InterfaceStationInsertRq<br>InterfaceSecInsertRq<br>InterfaceViewRequest<br>InterfaceUpdateRequest<br>InterfaceStationListRq<br>InterfaceStationUpdateRq<br>InterfaceSecViewRq<br>InterfaceSecUpdateRq<br>InterfaceSecDeleteRq<br>InterfaceStationDeleteRq<br>InterfaceDeleteRequest |

## Interface Status Window

|                 |                                                                                                  |
|-----------------|--------------------------------------------------------------------------------------------------|
| Task ID:        | InterfaceStatus                                                                                  |
| Permissions:    | FullInterfaceStatusPermission<br>ViewInterfaceStatusPermission                                   |
| Help ID:        | w_interface_status                                                                               |
| Data Sources:   | n/a                                                                                              |
| Desktop Access: | System Operations > Interface > Interface Status                                                 |
| Messages:       | InterfaceStatusAllInterfacesViewRq<br>InterfaceStatusAllStationsViewRq<br>InterfaceStationListRq |

## Interface Terminal Configuration Window

|                 |                                                                                                                                                                          |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | InterfaceTerm                                                                                                                                                            |
| Permissions:    | FullInterfaceTermPermission<br>ViewInterfaceTermPermission                                                                                                               |
| Help ID:        | w_interface_terminal_configuration                                                                                                                                       |
| Data Sources:   | Interface_Terminal                                                                                                                                                       |
| Desktop Access: | Configure > Interface > Network > STAR > Interface Terminal                                                                                                              |
| Messages:       | InterfaceTerminalInsertRq<br>InterfaceTerminalListRq<br>InterfaceTerminalFindListRq<br>InterfaceTerminalViewRq<br>InterfaceTerminalUpdateRq<br>InterfaceTerminalDeleteRq |

## Interface Totals Window

|                 |                                                  |
|-----------------|--------------------------------------------------|
| Task ID:        | InterfaceTotals                                  |
| Permissions:    | FullInterfaceTotalsPermission                    |
| Help ID:        | w_interface_totals                               |
| Data Sources:   | n/a                                              |
| Desktop Access: | System Operations > Interface > Interface Totals |
| Messages:       | InterfaceTotalsViewRq                            |



## Interpay BIM Interface Configuration Window

|                 |                                                                            |
|-----------------|----------------------------------------------------------------------------|
| Task ID:        | InterpayInterface                                                          |
| Permissions:    | FullInterpayIntfPermission<br>ViewInterpayIntfPermission                   |
| Help ID:        | w_interpay_bim_interface_configuration                                     |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>Ipay_Interface          |
| Desktop Access: | Configure > Interface > Network > Interpay BIM                             |
| Messages:       | InterPayInsertRq<br>InterPayViewRq<br>InterPayUpdateRq<br>InterPayDeleteRq |

## ISO8583 (93) Host Interface Configuration Window

|                 |                                                                     |
|-----------------|---------------------------------------------------------------------|
| Task ID:        | B24HISO93InterfaceConfig                                            |
| Permissions:    | FullB24HISO93IFCnfgPermission<br>ViewB24HISO93IFCnfgPermission      |
| Help ID:        | w_iso_93_host_interface_configuration                               |
| Data Sources:   | HISO93_Interface<br>Interface<br>Interface_SAF<br>Interface_Station |
| Desktop Access: | Configure > Interface > Host > ISO8583 (93) Host                    |
| Messages:       | HISO93InsertRq<br>HISO93ViewRq<br>HISO93UpdateRq<br>HISO93DeleteRq  |

## ISO Message Profile Configuration Window

|                 |                                                                                                                                                                  |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ISOFrameworkConfiguration                                                                                                                                        |
| Permissions:    | FullISOFrameworkCfgPermission<br>ViewISOFrameworkCfgPermission                                                                                                   |
| Help ID:        | w_iso_message_profile_configuration                                                                                                                              |
| Data Sources:   | ISO_Field<br>ISO_Message                                                                                                                                         |
| Desktop Access: | Configure > ISO > Message Profile                                                                                                                                |
| Messages:       | ISOMsgPrflListRq<br>ISOFldInsertRq<br>ISOMsgInsertRq<br>ISOFldViewRq<br>ISOFldUpdateRq<br>ISOMsgDataListRq<br>ISOMsgUpdateRq<br>ISOMsgDeleteRq<br>ISOFldDeleteRq |

## ISO Transaction Mapping Profile Configuration Window

|                 |                                                                                                                                                                                                                                                                                           |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ISOTranMapping                                                                                                                                                                                                                                                                            |
| Permissions:    | FullISOTranMapPermission<br>ViewISOTranMapPermission                                                                                                                                                                                                                                      |
| Help ID:        | w_iso_transaction_mapping_profile_configuration                                                                                                                                                                                                                                           |
| Data Sources:   | ISO_PROC_CODE<br>PROC_CODE_ISO                                                                                                                                                                                                                                                            |
| Desktop Access: | Configure > ISO > Transaction Mapping                                                                                                                                                                                                                                                     |
| Messages:       | IsoTranMappingListRq<br>IsoTranMappingInbInsertRq<br>IsoTranMappingOutInsertRq<br>IsoTranMappingInbViewRq<br>IsoTranMappingInbUpdateRq<br>IsoTranMappingOutViewRq<br>IsoTranMappingOutUpdateRq<br>IsoTranMappingInbDeleteRq<br>IsoTranMappingOutDeleteRq<br>IsoTranMappingGenericDeleteRq |

## Issuer Transactions Allowed Profile Configuration Window

|                 |                                                                                                                                                                                     |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | IssuerTransactionsAllowed                                                                                                                                                           |
| Permissions:    | FullIssTransAllowedPermission<br>ViewIssTransAllowedPermission                                                                                                                      |
| Help ID:        | w_issuer_transactions_allowed_profile_configuration                                                                                                                                 |
| Data Sources:   | Issue_Txn_Allowed                                                                                                                                                                   |
| Desktop Access: | Configure > Transactions Allowed > Issuer Transaction Profile                                                                                                                       |
| Messages:       | IssuerTransAllowedInsertRq<br>IssuerTransAllowedListRq<br>IssuerTransAllowedViewRq<br>IssuerTransAllowedUpdateRq<br>IssuerTransAllowedDeleteRq<br>IssuerTransAllowedGenericDeleteRq |

## JCB Interface Configuration Window

|                 |                                                                  |
|-----------------|------------------------------------------------------------------|
| Task ID:        | JcbInterface                                                     |
| Permissions:    | FullJcbInterfacePermission                                       |
| Help ID:        | n/a                                                              |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>JCB_Interface |
| Desktop Access: | Configure > Interface > Network > JCB                            |
| Messages:       | n/a                                                              |

## JEANIE Institution Configuration Window

|                 |                                                               |
|-----------------|---------------------------------------------------------------|
| Task ID:        | JeanieInstitution                                             |
| Permissions:    | FullJeanieInstPermission                                      |
| Help ID:        | n/a                                                           |
| Data Sources:   | n/a                                                           |
| Desktop Access: | Configure > Interface > Network > JEANIE > JEANIE Institution |
| Messages:       | n/a                                                           |

## JEANIE Interface Configuration Window

|                 |                                                             |
|-----------------|-------------------------------------------------------------|
| Task ID:        | JeanieInterface                                             |
| Permissions:    | FullJeanieInterfacePermission                               |
| Help ID:        | n/a                                                         |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station             |
| Desktop Access: | Configure > Interface > Network > JEANIE > JEANIE Interface |
| Messages:       | n/a                                                         |

## Journal Issuer Profile Relationship Configuration Window

|                 |                                                              |
|-----------------|--------------------------------------------------------------|
| Task ID:        | JournalConfigurationMapping                                  |
| Permissions:    | FullJrnlCfgMappingPermission<br>ViewJrnlCfgMappingPermission |
| Help ID:        | w_journal_issuer_profile_relationship_configuration          |
| Data Sources:   | Not specified.                                               |
| Desktop Access: | Configure > Journal > Issuer Profile Relationship            |
| Messages:       | Not specified.                                               |

## Journal Profile Configuration Window

|                 |                                                              |
|-----------------|--------------------------------------------------------------|
| Task ID:        | JournalProfileConfiguration                                  |
| Permissions:    | FullJrnlProfileCfgPermission<br>ViewJrnlProfileCfgPermission |
| Help ID:        | w_journal_profile_configuration                              |
| Data Sources:   | Journal_Profile_Group<br>Journal_Profile_Group_Assign        |
| Desktop Access: | Configure > Journal > Journal Profile                        |
| Messages:       | Not specified.                                               |

## Journal Perusal Window

|                 |                                                              |
|-----------------|--------------------------------------------------------------|
| Task ID:        | LogFilePerusal                                               |
| Permissions:    | FullLogFilePerusalPermission<br>ViewLogFilePerusalPermission |
| Help ID:        | w_journal_perusal                                            |
| Data Sources:   | n/a                                                          |
| Desktop Access: | View > Journal Perusal                                       |
| Messages:       | Not specified.                                               |

## Journal Query Configuration Window

|                 |                                                                                                                                                |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | JournalQueryConfiguration                                                                                                                      |
| Permissions:    | FullJrnlQueryConfigPermission<br>ViewJournalQueryConfiguration                                                                                 |
| Help ID:        | w_journal_query_configuration                                                                                                                  |
| Data Sources:   | n/a                                                                                                                                            |
| Desktop Access: | Configure > Journal > Journal Query                                                                                                            |
| Messages:       | JournalQueryListRq<br>JournalQueryInsertRq<br>JournalQueryPositionViewRq<br>JournalQueryViewRq<br>JournalQueryUpdateRq<br>JournalQueryDeleteRq |

## Journal TDE Suppression Configuration Window

|                 |                                                                                                                               |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | JournalTDESuppression                                                                                                         |
| Permissions:    | FullJrnlTDESuppressPermission<br>ViewJrnlTDESuppressPermission                                                                |
| Help ID:        | w_journal_tde_suppression                                                                                                     |
| Data Sources:   | Journal_Data_Suppression                                                                                                      |
| Desktop Access: | Configure > Journal > Journal TDE Suppression                                                                                 |
| Messages:       | JrnlTdeSpInsertRq<br>JrnlTdeSpListRq<br>JrnlTdeSpViewRq<br>JrnlTdeSpUpdateRq<br>JrnlTdeSpDeleteRq<br>JrnlTdeSpGenericDeleteRq |

## KEYGEN Command Configuration and Submission Window

|                 |                                                                                                                   |
|-----------------|-------------------------------------------------------------------------------------------------------------------|
| Task ID:        | KEYGENLockdown                                                                                                    |
| Permissions:    | FullKEYGENLockdownPermission                                                                                      |
| Help ID:        | w_keygen_command_configuration_and_submission                                                                     |
| Data Sources:   | n/a                                                                                                               |
| Desktop Access: | Configure > Transaction Security > Automated Key<br>Distribution > KEYGEN Command Configuration and<br>Submission |
| Messages:       | n/a                                                                                                               |

## Limit Profile Management Window

|                 |                                                                                                      |
|-----------------|------------------------------------------------------------------------------------------------------|
| Task ID:        | PaymentLimitConfig                                                                                   |
| Permissions:    | FullPmtLimitConfigPermission<br>ViewPmtLimitConfigPermission                                         |
| Help ID:        | w_limit_profile_configuration                                                                        |
| Data Sources:   | Limits                                                                                               |
| Desktop Access: | Customer Management > Limit Profile                                                                  |
| Messages:       | LimitListRq<br>LimitInsertRq<br>LimitDetailRq<br>LimitUpdateRq<br>LimitDeleteRq<br>LimitDeletePrflRq |

## LINK ISO Interface (LIS5) Configuration Window

|                 |                                                                   |
|-----------------|-------------------------------------------------------------------|
| Task ID:        | LIS5Interface                                                     |
| Permissions:    | FullLIS5InterfacePermission<br>ViewLIS5InterfacePermission        |
| Help ID:        | w_link_lis5_interface_configuration                               |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>LIS5_Interface |
| Desktop Access: | Configure > Interface > Network > LINK ISO                        |
| Messages:       | Lis5InsertRq<br>Lis5ViewRq<br>Lis5UpdateRq<br>Lis5DeleteRq        |

## Linked Currency Configuration

|                 |                                                                          |
|-----------------|--------------------------------------------------------------------------|
| Task ID:        | LinkedCurrencyConfiguration                                              |
| Permissions:    | FullLinkedCurrCfgPermission<br>ViewLinkedCurrencyConfig                  |
| Help ID:        | w_linked_currency_configuration                                          |
| Data Sources:   | Linked_Currency                                                          |
| Desktop Access: | Configure > Currency Conversion > Linked Currency                        |
| Messages:       | LinkedCurrencyInsertRq<br>LinkedCurrencyListRq<br>LinkedCurrencyDeleteRq |

## Listener Configuration Window

|                 |                                                                                                                       |
|-----------------|-----------------------------------------------------------------------------------------------------------------------|
| Task ID:        | IWTListenerConfig                                                                                                     |
| Permissions:    | FullIWTListenerCfgPermission<br>ViewIWTListenerCfgPermission                                                          |
| Help ID:        | w_listener_configuration                                                                                              |
| Data Sources:   | LISTENER                                                                                                              |
| Desktop Access: | System Operations > Server Management > Listener                                                                      |
| Messages:       | IWTFLListenerInsertRq<br>IWTFLListenerListRq<br>IWTFLListenerViewRq<br>IWTFLListenerUpdateRq<br>IWTFLListenerDeleteRq |



## Master File Key Conversion Window

|                 |                                                               |
|-----------------|---------------------------------------------------------------|
| Task ID:        | MFKConverter                                                  |
| Permissions:    | FullMFKConverterPermission<br>ViewMFKConverterPermission      |
| Help ID:        | w_master_file_key_conversion                                  |
| Data Sources:   | Not specified.                                                |
| Desktop Access: | Configure > Transaction Security > Master File Key Conversion |
| Messages:       | MFKConv_ConvertKeysRq                                         |

## MasterCard Brand/Instrument Type Relationship Window

|                 |                                                                                              |
|-----------------|----------------------------------------------------------------------------------------------|
| Task ID:        | MasterCardIpF                                                                                |
| Permissions:    | FullMasterCardIpFPermission                                                                  |
| Help ID:        | w_mastercard_brand_instrument_type_relationship_configuration                                |
| Data Sources:   | MDS_Brand_Rel                                                                                |
| Desktop Access: | Configure > Interface > Network > Banknet > MasterCard Brand/Instrument Type Relationship    |
| Desktop Access: | Configure > Interface > Network > MasterCard > MasterCard Brand/Instrument Type Relationship |
| Messages:       | MdsBrandRelViewRq<br>MdsBrandRelInsertRq<br>MdsBrandRelUpdateRq<br>MdsBrandRelDeleteRq       |

## MasterCard Debit Switch (MDS) Interface Configuration Window

|                 |                                                                            |
|-----------------|----------------------------------------------------------------------------|
| Task ID:        | MaestroDebitSwitch                                                         |
| Permissions:    | FullMaestroPermission<br>ViewMaestroPermission                             |
| Help ID:        | w_mastercard_debit_switch_configuration                                    |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>MDS_Interface           |
| Desktop Access: | Configure > Interface > Network > MasterCard Debit Switch (MDS)            |
| Messages:       | MdsInsertRequest<br>MdsViewRequest<br>MdsUpdateRequest<br>MdsDeleteRequest |

## (MasterCard) Merchant Programs Window

|                 |                                                                                                                                    |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | BanknetMerchantProgram                                                                                                             |
| Permissions:    | FullBanknetMerchProgPermission                                                                                                     |
| Help ID:        | w_merchant_programs_configuration                                                                                                  |
| Data Sources:   | Banknet_Merchant_Program                                                                                                           |
| Desktop Access: | Configure > Interface > Network > MasterCard > Merchant Programs                                                                   |
| Messages:       | BanknetMerchantProgramInsertRq<br>BanknetMerchantProgramDeleteRq<br>BanknetMerchantProgramUpdateRq<br>BanknetMerchantProgramViewRq |

## Merchant Channel Configuration Window

|                 |                                                                                                                                    |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | MerchantChannel                                                                                                                    |
| Permissions:    | FullMerchantChannelPermission<br>FullMerchantChnlPrflPermission<br>ViewMerchantChannelPermission<br>ViewMerchantChnlPrflPermission |
| Help ID:        | w_merchant_channel_configuration_and_statistics                                                                                    |
| Data Sources:   | Merchant_Channel_Profile                                                                                                           |
| Desktop Access: | Configure > Merchant Processing > Merchant Channel                                                                                 |
| Messages:       | Not specified.                                                                                                                     |

## Merchant Channel Profile Window

|                 |                                                                                      |
|-----------------|--------------------------------------------------------------------------------------|
| Task ID:        | MerchantChannelProfile                                                               |
| Permissions:    | FullMerchantChnlPrflPermission<br>ViewMerchantChnlPrflPermission                     |
| Help ID:        | w_merchant_channel_profile_configuration                                             |
| Data Sources:   | APACS_Configuration<br>Chan_Profile_Instrm_Typ_Relation<br>Merchant_Delivery_Channel |
| Desktop Access: | Configure > Merchant Processing > Merchant Channel Profile                           |
| Messages:       | Not specified.                                                                       |

## Merchant Configuration Window

|                 |                                                                                                                    |
|-----------------|--------------------------------------------------------------------------------------------------------------------|
| Task ID:        | MerchantConfiguration                                                                                              |
| Permissions:    | FullMerchantConfigPermission<br>ViewMerchantConfigPermission                                                       |
| Help ID:        | w_merchant_configuration_and_statistics                                                                            |
| Data Sources:   | Merchant<br>Merch_Instr_Typ_Relation                                                                               |
| Desktop Access: | Configure > Merchant Processing > Merchant                                                                         |
| Messages:       | MerchantInstrmTypeInsertRq<br>MerchantInstrmTypeViewRq<br>MerchantInstrmTypeUpdateRq<br>MerchantInstrmTypeDeleteRq |

## (Networks (NETS)) Interface Terminal Configuration Window

|                 |                                                                                                                                                                          |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | NetsInterfaceTerminal                                                                                                                                                    |
| Permissions:    | FullNetsInterfaceTermPerm                                                                                                                                                |
| Help ID:        | w_interface_terminal_configuration                                                                                                                                       |
| Data Sources:   | Interface_Terminal                                                                                                                                                       |
| Desktop Access: | Configure > Interface > Network > Networks (NETS) ><br>Networks (NETS) Interface Terminal                                                                                |
| Messages:       | InterfaceTerminalInsertRq<br>InterfaceTerminalListRq<br>InterfaceTerminalFindListRq<br>InterfaceTerminalViewRq<br>InterfaceTerminalUpdateRq<br>InterfaceTerminalDeleteRq |

## Networks (NETS) Interface Configuration

|                 |                                                                        |
|-----------------|------------------------------------------------------------------------|
| Task ID:        | NetsInterface                                                          |
| Permissions:    | FullNetsInterfacePermission                                            |
| Help ID:        | n/a                                                                    |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station                        |
| Desktop Access: | Configure > Interface > Network > Network (NETS) > Networks (NETS) ISO |
| Messages:       | n/a                                                                    |

## NYCE Acquirers Configuration Window

|                 |                                                         |
|-----------------|---------------------------------------------------------|
| Task ID:        | NyceAcquirers                                           |
| Permissions:    | FullNyceAcquirersPermission                             |
| Help ID:        | n/a                                                     |
| Data Sources:   | NYCE_Institution                                        |
| Desktop Access: | Configure > Interface > Network > NYCE > NYCE Acquirers |
| Messages:       | NyceAcquirersListRq                                     |

## NYCE ISO Interface Configuration

|                 |                                                                   |
|-----------------|-------------------------------------------------------------------|
| Task ID:        | NyceInterface                                                     |
| Permissions:    | FullNyceInterfacePermission                                       |
| Help ID:        | n/a                                                               |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>NYCE_Interface |
| Desktop Access: | Configure > Interface > Network > NYCE > NYCE ISO                 |
| Messages:       | n/a                                                               |

## (NYCE) Interface Terminal Configuration Window

|                 |                                                                                                                                                                          |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | NyceInterfaceTerminal                                                                                                                                                    |
| Permissions:    | FullNyceInterfaceTermPerm                                                                                                                                                |
| Help ID:        | w_interface_terminal_configuration                                                                                                                                       |
| Data Sources:   | Interface_Terminal                                                                                                                                                       |
| Desktop Access: | Configure > Interface > Network > NYCE > NYCE Interface Terminal                                                                                                         |
| Messages:       | InterfaceTerminalInsertRq<br>InterfaceTerminalListRq<br>InterfaceTerminalFindListRq<br>InterfaceTerminalViewRq<br>InterfaceTerminalUpdateRq<br>InterfaceTerminalDeleteRq |

## OLTP Warmboot Management Window

|                 |                                                                                   |
|-----------------|-----------------------------------------------------------------------------------|
| Task ID:        | OltWarmbootManagement                                                             |
| Permissions:    | FullOLTPWarmbootMgmtPermission<br>ViewOLTPWarmbootMgmtPermission                  |
| Help ID:        | w_oltp_warmboot_management                                                        |
| Data Sources:   | OLTP_Warmboot                                                                     |
| Desktop Access: | System Operations > OLTP Warmboot Management                                      |
| Messages:       | OltWarmbootMngmntViewRq<br>OltWarmbootMngmntUpdateRq<br>OltWarmbootMngmntDeleteRq |

## On-Us Prefix Configuration Window

|                 |                                                                                                                              |
|-----------------|------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | PrefixConfiguration                                                                                                          |
| Permissions:    | FullIchgPrefixConfigPermission<br>FullPrefixConfigPermission<br>ViewIchgPrefixConfigPermission<br>ViewPrefixConfigPermission |
| Help ID:        | w_prefix_configuration                                                                                                       |
| Data Sources:   | Prefix                                                                                                                       |
| Desktop Access: | Configure > Prefix > On-Us                                                                                                   |
| Messages:       | PrefixListRq<br>PrefixConfigInsertRq<br>PrefixConfigViewRq<br>PrefixConfigUpdateRq<br>PrefixConfigDeleteRq                   |

## PIN Transport Key Profile Window

|                 |                                                              |
|-----------------|--------------------------------------------------------------|
| Task ID:        | PINTransportKeyUI                                            |
| Permissions:    | FullPINTransportKeyUIPerm                                    |
| Help ID:        | w_pin_transport_key_configuration                            |
| Data Sources:   | Transport_Key                                                |
| Desktop Access: | Configure > Transaction Security > PIN Transport Key Profile |
| Messages:       | TransportKeyInsertRq                                         |

## Perusal Profile Configuration Window

|                 |                                                                                                                                                                  |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | PerusalConfiguration                                                                                                                                             |
| Permissions:    | FullPerusalConfigPermission<br>ViewPerusalConfiguration                                                                                                          |
| Help ID:        | w_perusal_profile_configuration                                                                                                                                  |
| Data Sources:   | Perusal_Script                                                                                                                                                   |
| Desktop Access: | Configure > Journal > Perusal > Perusal Profile                                                                                                                  |
| Messages:       | PerusalPrflListRq<br>PerusalPrflInsertRq<br>PerusalPrflViewRq<br>PerusalPrflUpdateRq<br>PerusalPrflDeleteRq<br>PerusalPrflGenericDeleteRq<br>PerusalUserIDListRq |



## Positive Balance Management Window

|                 |                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | PositiveBalance<br>PositiveBalanceActivity<br>PositiveBalanceBalances<br>PositiveBalanceGeneral<br>PositiveBalanceLimits<br>PositiveBalanceStatus<br>FindAccount                                                                                                                                                                                                                                                                     |
| Permissions:    | FullPositiveBalancePermission<br>ViewPositiveBalancePermission<br>FullPositiveBalActivityPerm<br>ViewPositiveBalActivityPerm<br>FullPositiveBalBalancesPerm<br>ViewPositiveBalBalancesPerm<br>FullPositiveBalGeneralPerm<br>ViewPositiveBalGeneralPerm<br>FullPositiveBalLimitsPerm<br>ViewPositiveBalLimitsPerm<br>FullPositiveBalStatusPerm<br>ViewPositiveBalStatusPerm<br>FullFindAccountPermission<br>ViewFindAccountPermission |
| Help ID:        | w_positive_balance_management                                                                                                                                                                                                                                                                                                                                                                                                        |
| Data Sources:   | Institution<br>Positive_Balance                                                                                                                                                                                                                                                                                                                                                                                                      |
| Desktop Access: | Customer Management > Positive Balance                                                                                                                                                                                                                                                                                                                                                                                               |
| Messages:       | PositiveBalanceAcctListRq<br>PositiveBalanceInsertRq<br>PositiveBalanceViewRq<br>PositiveBalanceUpdateRq<br>PositiveBalanceDeleteRq                                                                                                                                                                                                                                                                                                  |

## Preauthorization Hold Management Window

|                 |                                                                                                                                                               |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | PreAuthHold                                                                                                                                                   |
| Permissions:    | FullPreAuthHoldPermission<br>ViewPreAuthHoldPermission                                                                                                        |
| Help ID:        | w_preauthorization_hold_management                                                                                                                            |
| Data Sources:   | Pre_Auth_Hold                                                                                                                                                 |
| Desktop Access: | Customer Management > Preauthorization Hold                                                                                                                   |
| Messages:       | PreAuthHoldUITblInsertRq<br>PreAuthHoldUITblListRq<br>PreAuthHoldUITblViewRq<br>PreAuthHoldUITblUpdateRq<br>PreAuthHoldUITblDeleteRq<br>PreAuthHoldUIDeleteRq |

## Presto Interface Configuration Window

|                 |                                                                     |
|-----------------|---------------------------------------------------------------------|
| Task ID:        | PrestoInterface                                                     |
| Permissions:    | FullPrestoInterfacePermission                                       |
| Help ID:        | n/a                                                                 |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>Presto_Interface |
| Desktop Access: | Configure > Interface > Network > Presto                            |
| Messages:       | n/a                                                                 |

## PRM Interface Configuration Window

|                 |                                                                  |
|-----------------|------------------------------------------------------------------|
| Task ID:        | PRMInterface                                                     |
| Permissions:    | FullPRMInterfacePermission<br>ViewPRMInterfacePermission         |
| Help ID:        | w_prm_interface_configuration                                    |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>PRM_Interface |
| Desktop Access: | Configure > Interface > Network > PRM                            |
| Messages:       | Not specified.                                                   |

## Process Configuration Window

|                 |                                                                                                             |
|-----------------|-------------------------------------------------------------------------------------------------------------|
| Task ID:        | IWTProcessConfig                                                                                            |
| Permissions:    | FullIWTProcessCfgPermission<br>ViewIWTProcessCfgPermission                                                  |
| Help ID:        | w_process_configuration                                                                                     |
| Data Sources:   | PROCESS                                                                                                     |
| Desktop Access: | System Operations > Server Management > Process                                                             |
| Messages:       | IWTFProcessListRq<br>IWTFProcessInsertRq<br>IWTFProcessViewRq<br>IWTFProcessUpdateRq<br>IWTFProcessDeleteRq |

## Process Control Window

|                 |                                          |
|-----------------|------------------------------------------|
| Task ID:        | ProcessControl                           |
| Permissions:    | FullProcessControl<br>ViewProcessControl |
| Help ID:        | w_process_control                        |
| Data Sources:   | n/a                                      |
| Desktop Access: | System Operations > Process Control      |
| Messages:       | ProcessControlRq                         |

## Pulse Interface Configuration Window

|                 |                                                                    |
|-----------------|--------------------------------------------------------------------|
| Task ID:        | PulseInterface                                                     |
| Permissions:    | FullPulseInterfacePermission                                       |
| Help ID:        | w_pulse_interface_configuration                                    |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>Pulse_Interface |
| Desktop Access: | Configure > Interface > Network > Pulse > Pulse Interface          |
| Messages:       | n/a                                                                |

## **(Pulse) Interface Terminal Configuration Window**

|                 |                                                                                                                                                                          |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | PulseInterfaceTerminal                                                                                                                                                   |
| Permissions:    | FullPulseInterfaceTermPerm                                                                                                                                               |
| Help ID:        | w_interface_terminal_configuration                                                                                                                                       |
| Data Sources:   | Interface_Terminal                                                                                                                                                       |
| Desktop Access: | Configure > Interface > Network > Pulse > Pulse Interface Terminal                                                                                                       |
| Messages:       | InterfaceTerminalInsertRq<br>InterfaceTerminalListRq<br>InterfaceTerminalFindListRq<br>InterfaceTerminalViewRq<br>InterfaceTerminalUpdateRq<br>InterfaceTerminalDeleteRq |

## **Pulse Institution Configuration Window**

|                 |                                                             |
|-----------------|-------------------------------------------------------------|
| Task ID:        | PulseInstitution                                            |
| Permissions:    | FullPulseInstitutionPermission                              |
| Help ID:        | n/a                                                         |
| Data Sources:   | Pulse_Institution                                           |
| Desktop Access: | Configure > Interface > Network > Pulse > Pulse Institution |
| Messages:       | n/a                                                         |

## **Pulse Network ID/Instrument Type Relationship Configuration Window**

|                 |                                                                                           |
|-----------------|-------------------------------------------------------------------------------------------|
| Task ID:        | PulseBrandInstrmRelation                                                                  |
| Permissions:    | FullPulseBrandInstrmRelnPerm                                                              |
| Help ID:        | n/a                                                                                       |
| Data Sources:   | n/a                                                                                       |
| Desktop Access: | Configure > Interface > Network > Pulse > Pulse > Network ID/Instrument Type Relationship |
| Messages:       | n/a                                                                                       |

## Query Execute Window

|                 |                                                                  |
|-----------------|------------------------------------------------------------------|
| Task ID:        | JournalQueryExecution                                            |
| Permissions:    | FullJrnlQueryExecutePermission<br>ViewJrnlQueryExecutePermission |
| Help ID:        | w_query_execute                                                  |
| Data Sources:   | n/a                                                              |
| Desktop Access: | System Operations > Query Execution                              |
| Messages:       | Not specified.                                                   |

## Real Time Feed Interface Configuration Window

|                 |                                                                                            |
|-----------------|--------------------------------------------------------------------------------------------|
| Task ID:        | RealTimeFeedInterface                                                                      |
| Permissions:    | FullRealTimeFeedIFPermission<br>ViewRealTimeFeedIFPermission                               |
| Help ID:        | w_realtimefeed_interface_configuration                                                     |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>Real_Time_Feed_Config                   |
| Desktop Access: | Configure > Interface > Host > Real Time Feed                                              |
| Messages:       | RealTimeFeedInsertRq<br>RealTimeFeedViewRq<br>RealTimeFeedUpdateRq<br>RealTimeFeedDeleteRq |

## Routing Configuration - Destination Window

|                 |                                                                                     |
|-----------------|-------------------------------------------------------------------------------------|
| Task ID:        | RoutingConfiguration                                                                |
| Permissions:    | FullRoutingConfigPermission<br>ViewRoutingConfiguration                             |
| Help ID:        | w_routing_configuration_destination                                                 |
| Data Sources:   | Acquirer_Route_Profile<br>Issuer_Route_Profile<br>Route<br>Acquirer_Issuer_Relation |
| Desktop Access: | Configure > Routing > Destinations                                                  |
| Messages:       | Not specified.                                                                      |

## Routing Configuration - Destination/Source Relationship Window

|                 |                                                                                     |
|-----------------|-------------------------------------------------------------------------------------|
| Task ID:        | AcquirerIssuerRelationConfig                                                        |
| Permissions:    | FullAcqIssRelatnCfgPermission<br>ViewRoutingConfiguration                           |
| Help ID:        | w_destination_source_relationship                                                   |
| Data Sources:   | Acquirer_Route_Profile<br>Issuer_Route_Profile<br>Route<br>Acquirer_Issuer_Relation |
| Desktop Access: | Configure > Routing > Destination/Source                                            |
| Messages:       | Not specified.                                                                      |

## Saudi Payments Network (SPAN2) ISO Interface Configuration Window

|                 |                                                                                                       |
|-----------------|-------------------------------------------------------------------------------------------------------|
| Task ID:        | Span2Interface                                                                                        |
| Permissions:    | FullSpan2InterfacePermission                                                                          |
| Help ID:        | n/a                                                                                                   |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>SPAN2_Interface                                    |
| Desktop Access: | Configure > Interface > Network > Saudi Payments Network (SPAN2) > Saudi Payments Network (SPAN2) ISO |
| Messages:       | n/a                                                                                                   |

## Saudi Payments Network (SPAN2) Interface Terminal Configuration Window

|                 |                                                                                                                      |
|-----------------|----------------------------------------------------------------------------------------------------------------------|
| Task ID:        | Span2InterfaceTerminal                                                                                               |
| Permissions:    | FullSpan2InterfaceTerminalPerm                                                                                       |
| Help ID:        | n/a                                                                                                                  |
| Data Sources:   | SPAN2_Interface_Terminal                                                                                             |
| Desktop Access: | Configure > Interface > Network > Saudi Payments Network (SPAN2) > Saudi Payments Network (SPAN2) Interface Terminal |
| Messages:       | n/a                                                                                                                  |



## Script Editor Window

|                 |                                                                                                                   |
|-----------------|-------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ScriptEditor                                                                                                      |
| Permissions:    | FullScriptEditorPermission                                                                                        |
| Help ID:        | w_script_editor                                                                                                   |
| Data Sources:   | Script<br>Script_Configuration<br>Script_Source                                                                   |
| Desktop Access: | Configure > Script > Editor                                                                                       |
| Messages:       | ScriptListRetrvRq<br>ScriptInsertRq<br>ScriptSourceRetrvRq<br>ScriptUpdateRq<br>ScriptCompileRq<br>ScriptDeleteRq |

## Script Repository Window

|                 |                                                                                                                   |
|-----------------|-------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ScriptRepository                                                                                                  |
| Permissions:    | FullScriptRepository<br>ViewScriptRepository                                                                      |
| Help ID:        | w_script_repository                                                                                               |
| Data Sources:   | Script<br>Script_Configuration<br>Script_Source                                                                   |
| Desktop Access: | Configure > Script > Repository                                                                                   |
| Messages:       | ScriptListRetrvRq<br>ScriptInsertRq<br>ScriptSourceRetrvRq<br>ScriptUpdateRq<br>ScriptCompileRq<br>ScriptDeleteRq |

## Security Device Configuration Window

|                 |                                                                               |
|-----------------|-------------------------------------------------------------------------------|
| Task ID:        | SecurityDeviceConfiguration                                                   |
| Permissions:    | FullSecurityDevCfgPermission<br>ViewSecurityDevCfgPermission                  |
| Help ID:        | w_security_device_configuration                                               |
| Data Sources:   | Security_Device_Config                                                        |
| Desktop Access: | Configure > Transaction Security > Security Device                            |
| Messages:       | SDC_DevListRq<br>SDC_InsertRq<br>SDC_DetailRq<br>SDC_UpdateRq<br>SDC_DeleteRq |

## Shazam Interface Configuration Window

|                 |                                                 |
|-----------------|-------------------------------------------------|
| Task ID:        | ShazamInterface                                 |
| Permissions:    | FullShazamInterfacePermission                   |
| Help ID:        | n/a                                             |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station |
| Desktop Access: | Configure > Interface > Network > Shazam        |
| Messages:       | n/a                                             |

## Socket Administration Window

|                 |                                                                                                                                                                                                                                                                   |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | IWTSocketAdministration                                                                                                                                                                                                                                           |
| Permissions:    | FullIWTSocketAdminPermission<br>ViewIWTSocketAdministration                                                                                                                                                                                                       |
| Help ID:        | w_socket_administration                                                                                                                                                                                                                                           |
| Data Sources:   | Not specified.                                                                                                                                                                                                                                                    |
| Desktop Access: | System Operations > Server Management > Server Administration > Socket Administration                                                                                                                                                                             |
| Messages:       | IWTFSocketAdminViewRq<br>IWTFSocketInClientListRq<br>IWTFSocketInClientUpdateRq<br>IWTFSocketInServerListRq<br>IWTFSocketInServerUpdateRq<br>IWTFSocketOutClientListRq<br>IWTFSocketOutClientUpdateRq<br>IWTFSocketOutServerListRq<br>IWTFSocketOutServerUpdateRq |

## Source Routing Profile Configuration Window

|                 |                                                                                                                                 |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | AcquirerProfileConfiguration                                                                                                    |
| Permissions:    | FullAcqProfileConfigPermission<br>ViewAcqProfileConfigPermission                                                                |
| Help ID:        | w_source_routing_profile_configuration                                                                                          |
| Data Sources:   | Acquirer_Route_Profile<br>Issuer_Route_Profile<br>Route<br>Acquirer_Issuer_Relation                                             |
| Desktop Access: | Configure > Routing > Profile Description > Source Routing Profile                                                              |
| Messages:       | AcquirerProfileListRq<br>AcquirerProfileInsertRq<br>AcquirerProfileViewRq<br>AcquirerProfileUpdateRq<br>AcquirerProfileDeleteRq |

## SPDH Device Profile Configuration Window

|                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | SPDHDeviceConfig                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Permissions:    | FullSPDHDeviceConfigPermission<br>ViewSPDHDeviceConfigPermission                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Help ID:        | w_spdh_device_profile_configuration                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Data Sources:   | SPDH_act_cde_descr<br>SPDH_Configuration<br>SPDH_Message<br>SPDH_opt_resp_data<br>SPDH_txn_cde_descr                                                                                                                                                                                                                                                                                                                                                                                             |
| Desktop Access: | Configure > Merchant Processing > SPDH Device Profile                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Messages:       | SPDHActCodesDescrsInsertAllRq<br>SPDHActCodesDescrsGetAllRq<br>SPDHActCodesDescrsUpdateAllRq<br>SPDHActCodesDescrsDeleteAllRq<br>SPDHActionCodesInsertAllRq<br>SPDHActionCodesGetAllRq<br>SPDHActionCodesUpdateAllRq<br>SPDHActionCodesDeleteAllRq<br>SPDHMessagesInsertAllRq<br>SPDHMessagesGetAllRq<br>SPDHMessagesUpdateAllRq<br>SPDHMessagesDeleteAllRq<br>SPDHTranCodesDescrsInsertAllRq<br>SPDHTranCodesDescrsGetAllRq<br>SPDHTranCodesDescrsUpdateAllRq<br>SPDHTranCodesDescrsDeleteAllRq |

## STAR Institution Configuration Window

|                 |                                                                                                                                 |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | StarInstitution                                                                                                                 |
| Permissions:    | FullStarInstitutionPermission<br>ViewStarInstitutionPermission                                                                  |
| Help ID:        | w_star_institution_configuration                                                                                                |
| Data Sources:   | Star_Institution                                                                                                                |
| Desktop Access: | Configure > Interface > Network > STAR > STAR Institution                                                                       |
| Messages:       | StarInstitutionInsertRq<br>StarInstitutionListRq<br>StarInstitutionViewRq<br>StarInstitutionUpdateRq<br>StarInstitutionDeleteRq |

## STAR ISO Interface Configuration Window

|                 |                                                                                |
|-----------------|--------------------------------------------------------------------------------|
| Task ID:        | StarInterface                                                                  |
| Permissions:    | FullStarInterfacePermission<br>ViewStarInterfacePermission                     |
| Help ID:        | w_star_iso_interface_configuration                                             |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>Star_Interface              |
| Desktop Access: | Configure > Interface > Network > STAR > STAR ISO                              |
| Messages:       | StarInsertRequest<br>StarViewRequest<br>StarUpdateRequest<br>StarDeleteRequest |

## STAR NE Network ID/Instrument Type Relationship Configuration Window

|                 |                                                                                                                                                              |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | StarNEIpF                                                                                                                                                    |
| Permissions:    | FullStarNEIpFPermission                                                                                                                                      |
| Help ID:        | n/a                                                                                                                                                          |
| Data Sources:   | Star_NE_Network_Rel                                                                                                                                          |
| Desktop Access: | Configure > Interface > Network > STAR > STAR NE<br>Network ID/Instrument Type Relationship                                                                  |
| Messages:       | StarNEIpFViewRq<br>StarNEIpFInsertRq<br>StarNEIpFInsertRqEntry<br>StarNEIpFUpdateRq<br>StarNEIpFUpdateRqEntry<br>StarNEIpFDeleteRq<br>StarNEIpFDeleteRqEntry |

## STAR Network ID/Instrument Type Relationship Configuration Window

|                 |                                                                                          |
|-----------------|------------------------------------------------------------------------------------------|
| Task ID:        | StarNetworkIdRelationship                                                                |
| Permissions:    | FullStarNtwkIdRelationPerm<br>ViewStarNtwkIdRelationPerm                                 |
| Help ID:        | w_star_network_identifier_instrument_type_relationship_<br>configuration                 |
| Data Sources:   | STAR_Network_Rel                                                                         |
| Desktop Access: | Configure > Interface > Network > STAR > STAR Network<br>ID/Instrument Type Relationship |
| Messages:       | Not specified.                                                                           |

## Surcharge Country Code Configuration Window

|                 |                                                                                                                                                                                                               |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | SurchargeCntryCdeCnfg                                                                                                                                                                                         |
| Permissions:    | FullSurchCntryCdePermission                                                                                                                                                                                   |
| Help ID:        | w_surcharge_country_code_configuration                                                                                                                                                                        |
| Data Sources:   | Surcharge_Country_Code                                                                                                                                                                                        |
| Desktop Access: | Configure > Surcharge Country Code                                                                                                                                                                            |
| Messages:       | SurchCountryCodeViewRq<br>SurchCountryCodeInsertRq<br>SurchCountryCodeInsertRqEntry<br>SurchCountryCodeUpdateRq<br>SurchCountryCodeUpdateRqEntry<br>SurchCountryCodeDeleteRq<br>SurchCountryCodeDeleteRqEntry |

## Surcharge Profile Configuration Window

|                 |                                                                                                                          |
|-----------------|--------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | ATMSurcharge                                                                                                             |
| Permissions:    | FullATMSurchargePermission<br>FullATMSurchPrflPermission<br>ViewATMSurchargePermission<br>ViewATMSurchPrflPermission     |
| Help ID:        | w_surcharge_profile_configuration                                                                                        |
| Data Sources:   | Surcharge                                                                                                                |
| Desktop Access: | Configure > Surcharge Profile                                                                                            |
| Messages:       | SrchgPrflInsRq<br>SrchgPrflListRq<br>SrchgPrflViewTypeRq<br>SrchgPrflUpdRq<br>SrchgPrflDelRq<br>SrchgPrflGenericDeleteRq |

## System Algorithm Configuration Window

|                 |                                                                                                                   |
|-----------------|-------------------------------------------------------------------------------------------------------------------|
| Task ID:        | SystemAlgorithm                                                                                                   |
| Permissions:    | FullSystemAlgorithmPermission<br>ViewSystemAlgorithm                                                              |
| Help ID:        | w_system_algorithm                                                                                                |
| Data Sources:   | System_Alogrithm_Config                                                                                           |
| Desktop Access: | Configure > Prefix > Not-On-Us > System Algorithm                                                                 |
| Messages:       | SysAlgoInsertRq<br>SysAlgoListRq<br>SysAlgoViewRq<br>SysAlgoUpdateRq<br>SysAlgoDeleteRq<br>SysAlgoGenericDeleteRq |

## System Monitor Window

|                 |                                                                                   |
|-----------------|-----------------------------------------------------------------------------------|
| Task ID:        | IWTSystemMonitor                                                                  |
| Permissions:    | FullIWTSystemMonitorPermission<br>ViewIWTSystemMonitor                            |
| Help ID:        | w_system_monitor                                                                  |
| Data Sources:   | Not specified.                                                                    |
| Desktop Access: | System Operations > Server Management > Server<br>Administration > System Monitor |
| Messages:       | Not specified.                                                                    |



## System Prefix Configuration Window

|                 |                                                                                                                          |
|-----------------|--------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | SystemPrefix                                                                                                             |
| Permissions:    | FullSystemPrefixPermission<br>ViewSystemPrefix                                                                           |
| Help ID:        | w_system_prefix_configuration                                                                                            |
| Data Sources:   | SYSTEM_PREFIX                                                                                                            |
| Desktop Access: | Configure > Prefix > Not-On-Us > System Prefix                                                                           |
| Messages:       | SysPrfxInsertRq<br>SysPrfxPrflListRq<br>SysPrfxDetailListRq<br>SysPrfxUpdateRq<br>SysPrfxDeleteRq<br>SysPrfxDeletePrflRq |

## System Properties Window

|                 |                                                                                      |
|-----------------|--------------------------------------------------------------------------------------|
| Task ID:        | IWTSystemProperties                                                                  |
| Permissions:    | FullIWTSysPropertiesPermission<br>ViewIWTSystemProperities                           |
| Help ID:        | w_system_properties                                                                  |
| Data Sources:   | Not specified.                                                                       |
| Desktop Access: | System Operations > Server Management > Server<br>Administration > System Properties |
| Messages:       | Not specified.                                                                       |

## Terminal Logical Network FIID Mapping Configuration Window

|                 |                                                                                               |
|-----------------|-----------------------------------------------------------------------------------------------|
| Task ID:        | TermLnFiidMap                                                                                 |
| Permissions:    | FulltermLnFiidMapPermission<br>ViewtermLnFiidMapPermission                                    |
| Help ID:        | w_terminal_logical_network_fiid_mapping                                                       |
| Data Sources:   | TERM_LN_FIID_MAP                                                                              |
| Desktop Access: | Configure > Interface > Host > BASE24 ISO8583 Host ><br>Terminal Logical Network/FIID Mapping |
| Messages:       | Not specified.                                                                                |

## Token Profile Configuration Window

|                 |                                                                                                                                     |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | TokenProfile                                                                                                                        |
| Permissions:    | FullTokenProfilePermission<br>ViewTokenProfilePermission                                                                            |
| Help ID:        | w_token_profile_configuration                                                                                                       |
| Data Sources:   | Token_Config<br>Token_Id_List                                                                                                       |
| Desktop Access: | Configure > BASE24 > Token Profile                                                                                                  |
| Messages:       | TokenDescListRq<br>TokenProfileInsertRq<br>TokenProfileListRq<br>TokenProfileViewRq<br>TokenProfileUpdateRq<br>TokenProfileDeleteRq |

## Totals Tag Documentation Configuration Window

|                 |                                                  |
|-----------------|--------------------------------------------------|
| Task ID:        | TotalsTagDocumentation                           |
| Permissions:    | FullTotalsTagDocPermission                       |
| Help ID:        | w_totals_tag_documentation_configuration         |
| Data Sources:   | Totals_Tag_Documentation                         |
| Desktop Access: | Configure > Interface > Totals Tag Documentation |
| Messages:       | Not specified.                                   |

## Trace Configuration Window

|                 |                                                                                                             |
|-----------------|-------------------------------------------------------------------------------------------------------------|
| Task ID:        | TraceConfiguration                                                                                          |
| Permissions:    | FullTraceConfigPermission<br>ViewTraceConfigPermission                                                      |
| Help ID:        | w_trace_configuration                                                                                       |
| Data Sources:   | Trace_Config                                                                                                |
| Desktop Access: | System Operations > Trace > Trace Configuration                                                             |
| Messages:       | TraceConfigInsertRq<br>TraceConfigListRq<br>TraceConfigViewRq<br>TraceConfigUpdateRq<br>TraceConfigDeleteRq |

## Trace Filter Profile Configuration Window

|                 |                                                                                                                                           |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | TraceFilterConfiguration                                                                                                                  |
| Permissions:    | FullTraceFilterCfgPermission<br>ViewTraceFilterCfgPermission                                                                              |
| Help ID:        | w_trace_filter_profile_configuration                                                                                                      |
| Data Sources:   | Trace_Filter                                                                                                                              |
| Desktop Access: | System Operations > Trace > Trace Filter Profile                                                                                          |
| Messages:       | TraceFilterInsertRq<br>TraceFilterListRq<br>TraceFilterViewRq<br>TraceFilterUpdateRq<br>TraceFilterDeleteRq<br>TraceFilterGenericDeleteRq |

## Usages Management Window

|                 |                                              |
|-----------------|----------------------------------------------|
| Task ID:        | Usages                                       |
| Permissions:    | FullUsagesPermission<br>ViewUsagesPermission |
| Help ID:        | w_usages_management                          |
| Data Sources:   | Usage                                        |
| Desktop Access: | Customer Management > Usages                 |
| Messages:       | UsagesUIListRq<br>UsagesUITblViewRq          |

## User Audit

|                 |                            |
|-----------------|----------------------------|
| Task ID:        | UserAuditReport            |
| Permissions:    | FullUserAuditRptPermission |
| Help ID:        | w_audit_report_wizard      |
| Data Sources:   | Not specified.             |
| Desktop Access: | View > User Audit          |
| Messages:       | Not specified.             |

## User Permissions

|                 |                         |
|-----------------|-------------------------|
| Task ID:        | UserSecurityProfile     |
| Permissions:    | ViewUSPPermission       |
| Help ID:        | w_user_permissions      |
| Data Sources:   | Not specified.          |
| Desktop Access: | View > User Permissions |
| Messages:       | Not specified.          |

## User Profile Relationship Window

|                 |                                                                                                            |
|-----------------|------------------------------------------------------------------------------------------------------------|
| Task ID:        | UserProfileRelation                                                                                        |
| Permissions:    | FullUserProfRelationPermission<br>ViewUserProfileRelation                                                  |
| Help ID:        | w_user_profile_relationship                                                                                |
| Data Sources:   | Not specified.                                                                                             |
| Desktop Access: | Configure > Journal > Perusal > User Profile Relationship                                                  |
| Messages:       | UserRelationshipInsertRq<br>UserRelationshipViewRq<br>UserRelationshipUpdateRq<br>UserRelationshipDeleteRq |

## User Security Control Management Window

|                 |                                     |
|-----------------|-------------------------------------|
| Task ID:        | UserSecurityControl                 |
| Permissions:    | FullUSCtlPermission                 |
| Help ID:        | w_user_security_control_management  |
| Data Sources:   | Users                               |
| Desktop Access: | Configure > User Security > Control |
| Messages:       | Not specified.                      |

## User Security Group Configuration Window

|                 |                                              |
|-----------------|----------------------------------------------|
| Task ID:        | UserSecurityGroupConfig                      |
| Permissions:    | FullUSGCfgPermission<br>ViewUSGCfgPermission |
| Help ID:        | w_user_security_group_configuration          |
| Data Sources:   | SecGrp                                       |
| Desktop Access: | Configure > User Security > Group            |
| Messages:       | Not specified.                               |

## User Security Profile Configuration Window

|                 |                                        |
|-----------------|----------------------------------------|
| Task ID:        | UserSecurityProfile                    |
| Permissions:    | FullUSPPermission<br>ViewUSPPermission |
| Help ID:        | w_user_security_profile_configuration  |
| Data Sources:   | Users                                  |
| Desktop Access: | Configure > User Security > Profile    |
| Messages:       | Not specified.                         |

## User Security Role Configuration Window

|                 |                                              |
|-----------------|----------------------------------------------|
| Task ID:        | UserSecurityRoleConfig                       |
| Permissions:    | FullUSRCfgPermission<br>ViewUSRCfgPermission |
| Help ID:        | w_user_security_role_configuration           |
| Data Sources:   | UsrXRole                                     |
| Desktop Access: | Configure > User Security > Role             |
| Messages:       | Not specified.                               |

## User Status

|                 |                            |
|-----------------|----------------------------|
| Task ID:        | UserAuditReport            |
| Permissions:    | FullUserAuditRptPermission |
| Help ID:        | w_user_status              |
| Data Sources:   | UsrStat                    |
| Desktop Access: | View > User Status         |
| Messages:       | Not specified.             |

## Visa Acquirers Configuration Window

|                 |                                                            |
|-----------------|------------------------------------------------------------|
| Task ID:        | VisaAcquirers                                              |
| Permissions:    | FullVisaAcquirersPermission<br>ViewVisaAcquirersPermission |
| Help ID:        | w_visa_acquirers_configuration                             |
| Data Sources:   | Visa_Institution                                           |
| Desktop Access: | Configure > Interface > Network > VisaNet > Visa Acquirers |
| Messages:       | Not specified.                                             |

## Visa Brand/Instrument Type Relationship Configuration Window

|                 |                                                                                         |
|-----------------|-----------------------------------------------------------------------------------------|
| Task ID:        | VisaIpf                                                                                 |
| Permissions:    | FullVisaIpfPermission<br>ViewVisaIpfPermission                                          |
| Help ID:        | w_visa_brand_instrument_type_relationship_configuration                                 |
| Data Sources:   | Visa_Brand_Rel                                                                          |
| Desktop Access: | Configure > Interface > Network > VisaNet > Visa Brand/<br>Instrument Type Relationship |
| Messages:       | Not specified.                                                                          |

## Visa DPS Acquirers Configuration Window

|                 |                                                                                                                                                |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| Task ID:        | VisaDPSAcquirers                                                                                                                               |
| Permissions:    | FullVisaDPSAcquirersPermission<br>ViewVisaDPSAcquirersPermission                                                                               |
| Help ID:        | w_visa_dps_acquirers_configuration                                                                                                             |
| Data Sources:   | Visa_DPS_Institution                                                                                                                           |
| Desktop Access: | Configure > Interface > Network > Visa DPS > Visa DPS<br>Acquirers                                                                             |
| Messages:       | VisaDPSInstitutionInsertRq<br>VisaDPSInstitutionListRq<br>VisaDPSInstitutionViewRq<br>VisaDPSInstitutionUpdateRq<br>VisaDPSInstitutionDeleteRq |

## Visa DPS Interface Configuration Window

|                 |                                                                        |
|-----------------|------------------------------------------------------------------------|
| Task ID:        | VisaDPSInterface                                                       |
| Permissions:    | FullVisaDPSInterfacePermission<br>ViewVisaDPSInterfacePermission       |
| Help ID:        | w_vis_a_dps_interface_configuration                                    |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>Visa_DPS_Interface  |
| Desktop Access: | Configure > Interface > Network > Visa DPS > Visa DPS Interface        |
| Messages:       | VisaDPSInsertRq<br>VisaDPSViewRq<br>VisaDPSUpdateRq<br>VisaDPSDeleteRq |

## Visa DPS Network ID/Instrument Type Relationship Window

|                 |                                                                                               |
|-----------------|-----------------------------------------------------------------------------------------------|
| Task ID:        | VdpsBrandInstrmRelatiion                                                                      |
| Permissions:    | FullVdpsBrandInstrmReInPerm                                                                   |
| Help ID:        | w_vis_a_brand_instrument_type_relationship_configuration                                      |
| Data Sources:   | Visa_Brand_Rel                                                                                |
| Desktop Access: | Configure > Interface > Network > Visa DPS > Visa DPS Network ID/Instrument Type Relationship |
| Messages:       | Not specified.                                                                                |



## VisaNet ISO Interface Configuration Window

|                 |                                                                                |
|-----------------|--------------------------------------------------------------------------------|
| Task ID:        | VisanetInterfaceConfig                                                         |
| Permissions:    | FullVisanetIFConfigPermission<br>ViewVisanetIFConfigPermission                 |
| Help ID:        | w_visanet_iso_interface_configuration                                          |
| Data Sources:   | Interface<br>Interface_SAF<br>Interface_Station<br>Visa_Interface              |
| Desktop Access: | Configure > Interface > Network > VisaNet > VisaNet ISO                        |
| Messages:       | VisaInsertRequest<br>VisaViewRequest<br>VisaUpdateRequest<br>VisaDeleteRequest |

*ACI Worldwide, Inc.*

## B: Desktop.cfg File

---

The **desktop.cfg** configuration property file defines parameters for ACI Desktop user interface and Web clients. This file should be configured once for all users associated with a version checker server. Configuration files are created for each user of the desktop (*username.cfg*) and contain user-specific definitions. The properties of desktop.cfg file are divided into logical sections and are discussed below.

### [Desktop] section

The **AppPath** property specifies the location of the UI application jars and must contain a valid directory location.

The **SSLEnabled** property is a boolean value indicating whether the desktop is to use an HTTPS connection for SSL support. This property only applies to those desktop connections to a webserver over HTTP.

The **CachePermissions** property is a boolean value indicating whether permissions are maintained in memory during user sessions.

The **EnableUSECReloadCacheCmd** property is a boolean value that if set to true enables those users who can access the User Security Role Configuration window to reload the user security authorization cache on demand by clicking the Reload Cache button. If this property is set to false, the Reload Cache button is not presented on the window.

The **Host** property specifies the name of the host group currently selected (last used) by the user. The host group specified by the value of the host property is used by the desktop to determine the connectivity parameters of the host server. The Host property is required.

The **HostTimeout** property specifies the amount of time, in seconds, that can elapse after a host request has been sent without a response being received. This property is optional and if specified must be a positive number. If the value is zero, or this property is missing, host requests waits 60 seconds for a response.

The **ShowLoggedOnUser** property is used to activate the user icon located at the lower right of the desktop. When this icon is moused over, the desktop displays the name of the user currently logged onto the desktop in a popup message. Set this property to true to activate this functionality.

### [Hosts] section

The [Hosts] section contains definitions for host groups used by the Host property above.

Each group (e.g., ProdServer) key entry within the [Hosts] section represents a logical host which consists of one or more physical hosts which are mirrors of each other and available for load balancing and fail over. The actual key name of each group entry is listed in the host selection list on the desktop. The value of a group entry consists of one or more URL entries in the form of 'host:port/path' separated by commas ','. The currently selected group name key entry is set in the Host property of the [Desktop] section.

Example:

```
ProdServer=prod1:9023,prod2:8079
TestServer=test1:7765
```

### [OnlineHelp] section

The **ACI Help** property identifies the default JavaHelp helpset (e.g., ACI\_Help.hs) for the desktop.

### [Common] section

The **Debug** property specifies whether or not debug messages are enabled for the desktop. Debug messages are sent to the debug log file identified by the **LogFileName** property located at the location specified by the **LogPath** property. Valid values are true or false (the default). This property can be specified at run time by setting the Debug system property on the command line. Setting the command line property overrides this property value.

The **TPA** property refers to Third Party Authentication. It specifies the type of third party authentication. If set to true then DEFAULT is implied. If set to false then NONE is implied.

The **ChangePasswordAllowed** property contains a boolean value that identifies whether the desktop allows password change capability. Typically used in conjunctions with the TPA property above. By default this property is true. It can be set to false to disable the change password dialog of the desktop.

**PasswordProperty** defines the name and location of the SSL keystore encrypted password binary file.

The **ChannelTrace** is a boolean value. If true then connectivity and messaging between the desktop and server will be traced and logged to the log entry file configured for the desktop. If false, then no tracing will be logged. The default value, if not present, is false. If the system property - DChannelTrace is present it will be overridden by the setting from this property.

The **ChannelTraceLevel** property is a numerical value indicating the level of tracing that is performed. This value is only effective if the ChannelTrace property is set to true. Valid values are:

- 0 = Trace connection and all messages
- 4 = Trace all messages (default)
- 5 = Trace channel message header content only
- 6 = Trace summary information (this setting is only used until the user is authenticated afterwhich the user's trace flag is used. See user preferences in section 2)

## [SSL] section

Refer to Appendix C for more information.

**Note:** The SSL properties only apply if SSL enabled (i.e., the SSLEnabled property in the [Desktop] section is set to true).

If the **KeyStoreAutoUpdate** property is a boolean value that if set to true, the desktop automatically extracts the specified KeyStore file by identifying its location in the classpath. The extracted file will replace the local KeyStore file at the time this component is started. If this property is not present, it defaults to false. The KeyStore file name is found in the **KeyStore** property below.

The **KeyStore** property contains the key store file name used for retrieving private key information and any trusted certificates and associated keys. It must be built correctly in order for the SSL implementation to properly function. The default if not present is defaultKS.sto. Any specified file that is

not present locally or if **KeyStoreAutoUpdate** is set to true, causes the component to search the classpath for the specified key store. If found, it is extracted and stored in the specified location (local).

The **KeyStorePassword** property specifies the password value that allows access to the KeyStore private and trusted certificate public keys. The default is "default".

The **KeyStoreType** property specifies the type of KeyStore file generated. The default, is JKS (Java Key Store). If a client implements a different type of keystore then it must be specified in this property.

The **TrustStore** property identifies the trust store where trusted certificates are accessed. By default, a separate trust store is not needed. This is an optional property and if not present, defaults to the value of the **KeyStore** property.

For the **TrustStoreType** property, refer to the **KeyStoreType** property above. If not present, it defaults to the **KeyStoreType** specified.

For the **TrustStorePassword** property, refer to the **KeyStorePassword** property above. If not present, it defaults to the **KeyStorePassword** specified.

The **Protocol** property defines the cryptographic protocol used, such as TLS (Transport Layer Protocol) or SSL (Secure Sockets Layer).

The **KeyMgmtAlgo** property specifies certificates standard and how keys are managed in regards to the trusted certificates. The default value, if not present, is "SunX509"

The **Provider** property specifies the Provider class that is used as the SSL implementation. The default value, if not present, is "com.sun.net.ssl.internal.ssl.Provider".

The **ProtocolHandlerPkgs** property specifies the protocol handler package that is required in conjunction with the provider implementation. The default value, if not present, is "com.sun.net.ssl.internal.www.protocol".

# C: SSL Keystore Password Manager

---

The ACI desktop accesses SSL keystore passwords during secure communication with servers. These passwords are referenced (not stored) for the ACI desktop in the desktop.cfg configuration file. The keystore passwords are not stored in the desktop.cfg because passwords cannot be encrypted within the desktop.cfg file (see the PCI note below). Therefore, the encrypted passwords are placed in a binary file (e.g., passwords.bin) that is referenced within the desktop.cfg file in the [COMMON] section of file using the PasswordProperty property.

The Password Manager is provided to assist users in managing and encrypting SSL keystore password binary files. There are two types of passwords used: system and user-defined. The Password Manager can be used to manage both types. Passwords are associated with token IDs and descriptions.

Password values are encrypted using a proprietary bit encryption algorithm that the code base can cipher and decipher. The password properties file is made up of *tokens* (i.e., properties) that contain a password value. Thus, each password token is associated with a password value. It is the token IDs that are acted upon when using the Password Manager.



**Payment Card Industry (PCI) Note:** For security, stored password values must be encrypted. Cross-industry best practices recommend that vendor-supplied default passwords not be used, that passwords contain both numeric and alphabetic characters with a minimum password length of at least seven characters, that passwords be changed at least every 90 days, and that a new password not be the same as any of the last four passwords used.

## Sample Passwords.bin File

The example below is an ASCII-format representation of a passwords.bin file. The actual information is stored on disk encrypted and in binary format.

```
[UserTokens]
# This section is for user specific tokens (if any)

[SystemTokens]

ESF.password=USEC Database password token
EAF.password=UAUD Database password token
KeyStorePassword=SSL Key store password token for USEC/UAUD
TrustStorePassword=SSL Trust store password token for USEC/
    UAUD

[Password]
ESF.password=657e1f6fecea9ea8
EAF.password=657e1f6fecea9ea8
KeyStorePassword=512bb47f6f7206e90d0d440da775982b
TrustStorePassword=512bb47f6f7206e90d0d440da775982b
```



# Run the Password Manager from the Command Prompt

When the Password Manager is initiated from a command prompt, both system and user-defined password tokens can be added and deleted.

To run the Password Manager from a command prompt, enter the following command syntax at the command prompt:

---

## **Syntax:**

```
java -classpath {uif-jar} [-DPasswordProperty=password-bin-filename]
    framework.cipher.PswdMgr -keyword argument
```

where:

*uif-jar* is any one of the following JARs:

- uif\_dt.jar
- uif\_sh.jar
- uif\_verchk.jar

*password-bin-filename* is the optional name of the password bin file entered as a system property. If it is not specified, it defaults to a value of “Password.bin”. If the password bin file is entered as a run argument, it overrides this value.

*keyword argument* is one of the following formats:

```
-SetPW token password password [password-bin-filename]
-VerifyPW token password [password-bin-filename]
-SetTKN token description [password-bin-filename]
-SetSYSTKN token description [password-bin-filename]
-RemoveTKN token password [password-bin-filename]
-RemoveSYSTKN token password [password-bin-filename]
-RemovePW token password [password-bin-filename]
```

where:

- SetPW — To set or change a password value and associate it to an existing token.

**Note:** A password cannot be changed unless the associated token for the password already exists. Therefore, use SetTKN first to add a user-defined or system password token.

- ❑ VerifyPW — To verify a password value.
- ❑ SetTKN — To add a user-defined password token.
- ❑ SetSYSTKN — To add a system password token.
- ❑ RemoveTKN — To remove a user-defined password token and the password associated with the token.
- ❑ RemoveSYSTKN — To remove a system password token and the password associated with the token.
- ❑ RemovePW — To remove a password value, but retains the token and description.

*token* is the name of a password property in the desktop.cfg (or local.cfg) file.

*password* is a clear password value. For the SetPW command function, you must enter the password twice to ensure it is entered correctly.

*password-bin-filename* is the optional name of the password bin file. If it is not specified, the value for the PasswordProperty system property is used.

*description* is a text description of a token. If the description contains spaces, it must be enclosed within quotes (“USEC database password key/token”).

## Run the Password Manager from the PswdMgrUI Window

When running the Password Manager from the PswdMgrUI window, user-defined password tokens can be added and deleted. However, system password tokens cannot be added or deleted from the window, these tokens can only be changed.

To run Password Manager from the PswdMgrUI window, enter the following command syntax at the Command prompt. Tokens, descriptions, and password values can be edited using this window.

---

**Syntax:**

---

```
Java -classpath {framework-jar} framework.cipher.PswdMgrUI  
      [password-bin-filename]
```

where:

*framework-jar* is any one of the following JARs:


- uif\_dt.jar
- uif\_sh.jar
- uif\_verchk.jar

*password-bin-filename* is the optional name of the password bin file. If it is not specified, it defaults to a value of “Password.bin”.

## PswdMgrUI Window

The following is an example of the PswdMgrUI window. If the specified password bin file already exists, the window reads the file and displays all of the token/password entries in the file. System passwords are displayed in black text while

user-defined passwords are displayed in blue text. In addition, all passwords values are masked with asterisk characters for security reasons. If the password bin file does not yet exist, no table rows are displayed.



## Add a New User-Defined Password Token

Use the following procedures to add a new user-defined password token.

1. Click the New button to insert a new empty row into the table.
2. In the empty row, enter a token ID, description, and password value.
3. Click the Store button to save the new information to the password binary file (e.g., password.bin).
4. Click the Exit button to stop the Password Manager.

## Delete a User-Defined Password Token

Use the following procedures to delete a password token.

1. Click on the row of the token that you want to delete. A selected row has a modified background color.
2. Click the Delete button to delete the token.
3. Click the Store button to save the change to the password binary file (e.g., password.bin).
4. Click the Exit button to stop the Password Manager.

# D: Open Source Software License Agreements

---

The following is a copy of the BASE24-eps 07.4 click-thru license agreement presented during product installation. Upon Installation, ACI will provide product support of Software Products in accordance with the ACI Customer Support Guide.

**Certain portions of this product contain software from the following companies. Additional terms noted in bold are applicable to that software. Items not in bold are required by the provider but do NOT supercede or limit the terms and conditions of your organization's license with ACI.**

USE OF THIS SOFTWARE INDICATES THAT YOU **AGREE** TO BE BOUND TO THE RESTRICTIONS AND CONDITIONS CONTAINED BELOW. IF YOU **DO NOT AGREE, DO NOT CLICK** "AGREE". INSTEAD, PROMPTLY CANCEL THE INSTALLATION AND RETURN THIS SOFTWARE AND ANY RELATED MATERIALS TO THE SENDER

## JDOM Java XML API

Copyright (C) 2001 Brett McLaughlin & Jason Hunter. All rights reserved.

*The name "JDOM" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [license@jdom.org](mailto:license@jdom.org).*

*Products derived from this software may not be called "JDOM", nor may "JDOM" appear in their name, without prior written permission from the JDOM Project Management ([pm@jdom.org](mailto:pm@jdom.org)).*

THIS SOFTWARE IS PROVIDED BY JDOM "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE JDOM AUTHORS OR THE PROJECT CONTRIBUTORS BE LIABLE FOR

ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

**Apache Jakarta Common Language Version 2.0**

**Apache Jakarta Project Java Regular Expression Parser Version 1.2**

**Apache JakartaProject Tomcat Version 3.2**

**Apache JakartaProject ORO 2.0**

**Apache log4j Version 1.2**

**Apache XML Project Xerces Java Parser Versions 1.0 and 2.4**

**Apache XML Project Xerces C++ Parser Version 3.3, formerly licensed as IBM XML4C**

**The Apache Software License, Version 1.1**

**Copyright (c) 1999 The Apache Software Foundation. All rights reserved.**

"This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)."

*The names "Xerces", "The Jakarta Project", "Commons", "log4j", "Tomcat", "Jakarta-Regexp", and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [apache@apache.org](mailto:apache@apache.org).*

*Products derived from this software may not be called "Apache" nor may "Apache" appear in their names without prior written permission of the Apache Group.*

THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,

PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## **Apache Jakarta Commons Net 1.3 Apache Xerces C++ 2.8.0 SourceForge Piccolo XML Parser for Java**

**(C) Copyright 2002-2004 by Yuval Oren. All rights reserved.**

**Licensed under the Apache License, Version 2.0.**

THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## **ICU License - ICU 1.8.1 and later**

### **COPYRIGHT AND PERMISSION NOTICE**

**Copyright (c) 1995-2005 International Business Machines Corporation and others All rights reserved.**

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the

rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## **JAVA™ 2 RUNTIME ENVIRONMENT (J2RE), VERSION 1.3**

## **JAVA™ AUTHENTICATION AND AUTHORIZATION SERVICE**

## **VERSION 1.0**

## **JAVAHELP™ VERSION 2.0**

Sun Microsystems, Inc. Binary Code License

**Copyright ©2000 by Sun Microsystems Inc. All Rights Reserved.**

*Java Technology Restrictions. You may not modify the Java Platform Interface ("JPI", identified as classes contained within the "java" package or any sub-packages of the "java" package), by creating additional classes within the JPI or otherwise causing the addition to or modification of the classes in the JPI. In the event that you create an additional class and associated API(s) which (i) extends the functionality of the Java platform, and (ii) is exposed to third party software developers for the purpose of developing additional software which invokes such additional API, you must promptly publish broadly an accurate specification for such API for free use by all developers. You may not create, or authorize your licensees to create, additional classes, interfaces, or sub-packages that are in any way identified as "java", "javax", "sun" or similar convention as specified by Sun in any naming convention designation.*



JAXB Component of Java™ Web Services Developer Pack  
Java™ Secure Socket Extension  
JavaBeans Activation Framework  
JavaMail API  
License  
Copyright 1994-2004 Sun Microsystems, Inc. All Rights Reserved.

*Neither the name of Sun Microsystems, Inc. or the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission.*

This software is provided "AS IS," without a warranty of any kind. ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE HEREBY EXCLUDED. SUN MICROSYSTEMS, INC. ("SUN") AND ITS LICENSORS SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THIS SOFTWARE OR ITS DERIVATIVES. IN NO EVENT WILL SUN OR ITS LICENSORS BE LIABLE FOR ANY LOST REVENUE, PROFIT OR DATA, OR FOR DIRECT, INDIRECT, SPECIAL, CONSEQUENTIAL, INCIDENTAL OR PUNITIVE DAMAGES, HOWEVER CAUSED AND REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF THE USE OF OR INABILITY TO USE THIS SOFTWARE, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

You acknowledge that this software is not designed, licensed or intended for use in the design, construction, operation or maintenance of any nuclear facility.

## **Sun Java Graphics Repository**

**Copyright 2000 by Sun Microsystems, Inc. All Rights Reserved**

## **EXOLAB Castor, Exolab Core, Open JMS**

**Copyright 2000-2002 © Intalio Inc. All Rights Reserved.**

The ExoLab Project: <http://www.exolab.org/>

*The name "ExoLab" must not be used to endorse or promote products derived from this Software without prior written permission of Intalio Inc. For written permission, please contact [info@exolab.org](mailto:info@exolab.org).*

*Products derived from this Software may not be called "Castor" nor may "Castor" appear in their names without prior written permission of Intalio Inc. Exolab, Castor and Intalio are trademarks of Intalio Inc..*

THIS SOFTWARE IS PROVIDED BY INTALIO AND CONTRIBUTORS "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL INTALIO OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## The Legion of the Bouncy Castle

**Copyright (c) 2000 The Legion Of The Bouncy Castle(<http://www.bouncycastle.org>)**

*Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:*

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

# STLport

## License Agreement

**Boris Fomitchev** grants **Licensee** a non-exclusive, non-transferable, royalty-free license to use **STLport** and its documentation without fee.

*By downloading, using, or copying STLport or any portion thereof, Licensee agrees to abide by the intellectual property laws and all other applicable laws of the United States of America, and to all of the terms and conditions of this Agreement.*

**Licensee** shall maintain the following copyright and permission notices on **STLport** sources and its documentation unchanged:

### **Copyright 1999,2000 Boris Fomitchev**

This material is provided "as is", with absolutely no warranty expressed or implied. Any use is at your own risk.

Permission to use or copy this software for any purpose is hereby granted without fee, provided the above notices are retained on all copies. Permission to modify the code and to distribute modified code is granted, provided the above notices are retained, and a notice that the code was modified is included with the above copyright notice.

The **Licensee** may distribute binaries compiled with **STLport** (whether original or modified) without any royalties or restrictions.

The Licensee may distribute original or modified STLport sources, provided that:

The conditions indicated in the above permission notice are met;

The following copyright notices are retained when present, and conditions provided in accompanying permission notices are met:

### **Copyright 1994 Hewlett-Packard Company**

### **Copyright 1996, 97 Silicon Graphics Computer Systems, Inc.**

### **Copyright 1997 Moscow Center for SPARC Technology.**

*Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. Hewlett-Packard Company makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.*

*Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. Silicon Graphics makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.*

*Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. Moscow Center for SPARC Technology makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.*

## **MX4J**

**License Version 1.0. Copyright © 2001 MX4J. All Rights Reserved.**

**This product includes software developed by the MX4J project (<http://mx4j.sourceforge.net>).**

THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL CARLOS QUIROZ OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Jython

**Copyright © 2000, Jython Developers. All Rights Reserved.**

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the Jython Developers nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## JPYthon

**Copyright © 1995-2001 Corporation for National Research Initiatives.**

JPYthon (Version 1.1.x) is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement may be located on the Internet using the following unique, persistent identifier (known as a handle): 1895.22/1006. The License may also be obtained from a proxy server on the Web using the following URL: <http://hdl.handle.net/1895.22/1006>.

CNRI is making the Software available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES

NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

CNRI SHALL NOT BE LIABLE TO LICENSEE OR OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF. SOME STATES DO NOT ALLOW THE LIMITATION OR EXCLUSION OF LIABILITY SO THE ABOVE DISCLAIMER MAY NOT APPLY TO LICENSEE.

## Jetty

### **Copyright Mort Bay Consulting Pty. Ltd. (Australia)**

\*\$Revision: 1.1 \$\*

\*Preamble:\*

The intent of this document is to state the conditions under which the Jetty Package may be copied, such that the Copyright Holder maintains some semblance of control over the development of the package, while giving the users of the package the right to use, distribute and make reasonable modifications to the Package in accordance with the goals and ideals of the Open Source concept as described at <http://www.opensource.org>.

It is the intent of this license to allow commercial usage of the Jetty package, so long as the source code is distributed or suitable visible credit given or other arrangements made with the copyright holders.

\*Definitions:\*

\* "Jetty" refers to the collection of Java classes that are distributed as a HTTP server with servlet capabilities and associated utilities.

\* "Package" refers to the collection of files distributed by the Copyright Holder, and derivatives of that collection of files created through textual modification.

\* "Standard Version" refers to such a Package if it has not been modified, or has been modified in accordance with the wishes of the Copyright Holder.

\* "Copyright Holder" is whoever is named in the copyright or copyrights for the package. Mort Bay Consulting Pty. Ltd. (Australia) is the "Copyright Holder" for the Jetty package.

\* "You" is you, if you're thinking about copying or distributing this Package.

\* "Reasonable copying fee" is whatever you can justify on the basis of media cost, duplication charges, time of people involved, and so on. (You will not be required to justify it to the Copyright Holder, but only to the computing community at large as a market that must bear the fee.)

\* "Freely Available" means that no fee is charged for the item itself, though there may be fees involved in handling the item. It also means that recipients of the item may redistribute it under the same conditions they received it.

0. The Jetty Package is Copyright (c) Mort Bay Consulting Pty. Ltd. (Australia) and others. Individual files in this package may contain additional copyright notices. The javax.servletpackages are copyright Sun Microsystems Inc.

1. The Standard Version of the Jetty package is available from <http://jetty.mortbay.org>.

2. You may make and distribute verbatim copies of the source form of the Standard Version of this Package without restriction, provided that you include this license and all of the original copyright notices and associated disclaimers.

3. You may make and distribute verbatim copies of the compiled form of the Standard Version of this Package without restriction, provided that you include this license.

4. You may apply bug fixes, portability fixes and other modifications derived from the Public Domain or from the Copyright Holder. A Package modified in such a way shall still be considered the Standard Version.

5. You may otherwise modify your copy of this Package in any way, provided that you insert a prominent notice in each changed file stating how and when you changed that file, and provided that you do at least ONE of the following:

- a) Place your modifications in the Public Domain or otherwise make them Freely Available, such as by posting said modifications to Usenet or an equivalent medium, or placing the modifications on a major archive site such as <ftp.uu.net>, or by allowing the Copyright Holder to include your modifications in the Standard Version of the Package.

- b) Use the modified Package only within your corporation or organization.
  - c) Rename any non-standard classes so the names do not conflict with standard classes, which must also be provided, and provide a separate manual page for each non-standard class that clearly documents how it differs from the Standard Version.
  - d) Make other arrangements with the Copyright Holder.
6. You may distribute modifications or subsets of this Package in source code or compiled form, provided that you do at least ONE of the following:
- a) Distribute this license and all original copyright messages, together with instructions (in the about dialog, manual page or equivalent) on where to get the complete Standard Version.
  - b) Accompany the distribution with the machine-readable source of the Package with your modifications. The modified package must include this license and all of the original copyright notices and associated disclaimers, together with instructions on where to get the complete Standard Version.
  - c) Make other arrangements with the Copyright Holder.
7. You may charge a reasonable copying fee for any distribution of this Package. You may charge any fee you choose for support of this Package. You may not charge a fee for this Package itself. However, you may distribute this Package in aggregate with other (possibly commercial) programs as part of a larger (possibly commercial) software distribution provided that you meet the other distribution requirements of this license.
8. Input to or the output produced from the programs of this Package do not automatically fall under the copyright of this Package, but belong to whomever generated them, and may be sold commercially, and may be aggregated with this Package.
9. Any program subroutines supplied by you and linked into this Package shall not be considered part of this Package.
10. The name of the Copyright Holder may not be used to endorse or promote products derived from this software without specific prior written permission.
11. This license may change with each release of a Standard Version of the Package. You may choose to use the license associated with version you are using or the license of the latest Standard Version.



12. THIS PACKAGE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

13. If any superior law implies a warranty, the sole remedy under such shall be ,at the Copyright Holders option either a) return of any price paid or b) use or reasonable endeavors to repair or replace the software.

14. This license shall be read under the laws of Australia.

## **JCheckTree**

Duguay, Claude, "Visual Components: Swinging on a JCheckTree, JAVAProMagazine, January 2001, Fawcette Technical Publications, Copyright 1999.

## **JSpinner**

Duguay, Claude, "Widget Factory: JSpinner," Java Developer's Journal, Volume 04, Issue 04, SYS-CON Media, Inc., Copyright 2001.

*ACI Worldwide, Inc.*

# Index

---

## A

Access user security windows, [3-2](#)  
Active sessions (maximum allowed), [3-6](#)  
Active user sessions, [4-3](#)  
allowPostLogonDebug task ID, [2-16](#)  
allowPostLogonTrace task ID, [2-16](#)  
Application Area, [1-1](#)  
Audit report XML format, [5-2](#)  
Audit\_Store\_and\_Forward data source, [5-1](#)  
Automatic file updating, [6-2](#)

## C

Cascading Style Sheets (CSS), JavaHelp, [7-3](#)  
Complex password requirements, [3-4](#)  
Concurrent active sessions, [2-6](#)  
Confirm deletes check box, [2-11](#)  
Confirm updates check box, [2-11](#)  
Content files, JavaHelp, [7-3](#)  
Context sensitive help, [7-5](#)  
Currency format locale, [2-11](#)  
Custom online help, [7-7](#)

## D

Desktop layout (areas), [1-1](#)  
desktop.cfg file, [B-1](#)  
DeskTop.log file, [2-17](#)  
Distributed Security Administration (DSA), [3-7](#)  
DSA (Distributed Security Administration), [3-7](#)

## F

Filter settings, [3-14](#)  
Frame open indicator, [2-11](#)

## G

Get Info function, [3-19](#)

## H

Help IDs, [7-5](#)

Helpset file, JavaHelp, [7-3](#)  
Helpset Viewer, [7-1](#)  
hsvviewer.jar, [7-10](#)

## I

Icon area, [1-2](#)  
Images, JavaHelp, [7-3](#)

## J

JAR files for JavaHelp, [7-3](#)  
JAR versions, [2-18](#)  
JavaHelp, [7-1](#)  
JavaHelp configuration files, [7-3](#)  
JavaHelp viewer, [7-1](#)

## L

local.cfg, [1-2](#)  
Logging sensitive data, [1-1](#)  
LogScrubber.cfg file, [2-16](#)

## M

Map file, JavaHelp, [7-3](#)  
Map IDs, [7-5](#)  
Maximum number of allowed active sessions, [3-6](#)  
Menu Bar, [1-1](#)  
Mirror the repository, [6-2](#)  
modules.lst file (Modules list), [1-4](#)

## N

Navigation tree, [1-1](#)  
Navigation tree check box, [2-11](#)

## O

Online help viewer (JavaHelp), [7-1](#)  
OwnerIDSupport property, [3-7](#), [3-12](#)

**P**

- Packaging of online help, [7-3](#)
- Password group, [3-4](#)
- Password manager (PswdMgr) utility
  - running directly from a Java prompt, [C-3](#)
  - running from a user interface window, [C-5](#)
- PasswordProperty, [C-1](#)
- Passwords, [3-4](#)
  - change by a user, [2-8](#)
  - change by an administrator, [4-5](#)
  - restrictions, [3-4](#)
- Permission groups, [3-3](#)
- Permissions, [3-4](#)
- Pre-show frame indicator, [2-12](#)
- Print Screen Orientation, [2-12](#)
- Procedures
  - Access online help from the desktop, [7-2](#)
  - Access user security windows, [3-2](#)
  - Assign a security group, [3-21](#)
  - Assign a system administration role filter, [3-12](#)
  - Assign filters to a user, [3-25](#)
  - Assign roles to a user, [3-23](#)
  - Change a password (by a user), [2-8](#)
  - Change a user password (by admin), [4-5](#)
  - Change the display of JavaHelp content, [7-9](#)
  - Configure a password group, [3-9](#)
  - Configure a security group, [3-10](#)
  - Configure a user role, [3-13](#)
  - Configure field filters, [3-14](#)
  - Configure permission groups, [3-19](#)
  - Configure permissions, [3-17](#)
  - Connect to a web server, [2-7](#)
  - Create custom JavaHelp content HTML files, [7-8](#)
  - Create custom online help, [7-7](#)
  - Display the name of the user logged on to the desktop, [2-8](#)
  - Display the user interface framework version, [2-18](#)
  - Display user password history, [4-5](#)
  - Enable SSL, [2-2](#)
  - Expire a user password, [4-5](#)
  - Hide or show the navigation tree, [2-11](#)
  - Install JavaHelp, [7-10](#)
  - Log off (out), [2-9](#)
  - Log off a user, [4-4](#)
  - Mirror the repository, [6-2](#)
  - Search the helpset, [7-6](#)
  - Send a snapshot, [2-17](#)
  - Set a user status, [4-2](#)
  - Set Error Notification settings, [2-13](#)
  - Set sound preferences, [2-14](#)
  - Set user preferences, [2-10](#)
  - Terminate an active user session, [4-4](#)
  - View active user sessions (refreshing, updating), [4-4](#)
  - View password change history, [4-5](#)

**R**

- report.userauditlog.loc environment attribute, [5-3](#)

- report.userdetail.xxx properties, [4-7](#)
- report.userpermissions.xxx properties, [4-10](#)
- Roles, [3-3](#)
- RunDesktop.bat, [2-1](#), [6-1](#)

**S**

- Search the helpset, [7-6](#)
- Secure Sockets Layer (SSL) protocol, [1-3](#)
  - enable, [2-2](#)
- Security domains, [3-7](#)
- Security error alert message, [2-5](#)
- Security groups (users), [3-5](#)
- Security warning alert message, [2-6](#)
- Session timeout, [3-6](#), [3-11](#)
- Sessions (active), [4-3](#)
- Snapshots, [2-17](#)
- sound.cfg, [2-14](#)
- Status Pane, [1-2](#)
- Status pane, [2-12](#)
- SysAdmin Profile, [3-12](#)
- System Administration Profile, [3-12](#)

**T**

- Table of contents, JavaHelp, [7-3](#)
- Timeouts
  - session, [3-11](#)
  - UI, [3-11](#)
- Title Bar, [1-1](#)
- Toolbar, [1-1](#), [2-12](#)
- Tooltip text (display errors in tooltip text), [2-13](#)

**U**

- UI timeout, [3-6](#), [3-11](#)
- User authentication, [1-4](#)
- User authorization, [1-4](#)
- User interface framework, [1-2](#)
- User interface framework version, [2-18](#)
- User logged on information, [2-8](#)
- User Permissions window, [4-9](#)
- User Preferences window
  - Error Notification tab, [2-13](#)
  - Sound tab, [2-14](#)
- User roles, [3-3](#)
- User Security Control Management window
  - Active Sessions tab, [4-3](#), [4-4](#)
  - Password Maintenance tab, [4-5](#)
- User Security Group Configuration window
  - Password Group tab, [3-9](#)
  - Security Group tab, [3-10](#)

**U *continued***

- User security overview, [1-4](#)
- User Security Profile Configuration window
  - Active Sessions tab, [4-3](#), [4-4](#)
  - General tab, [3-20](#), [4-2](#)
- User Security Profile window
  - Password tab, [4-5](#)
  - Roles tab, [3-23](#), [3-25](#)
- User Security Role Configuration window
  - Permission Groups tab, [3-19](#)
  - Permissions tab, [3-17](#)
  - Roles tab, [3-13](#)
- User sessions, [4-3](#)
- User status, [4-2](#)
- User Status window, [4-6](#)
- USRAULOG data source, [5-1](#)

**V**

- VC quiet mode, [6-2](#)
- Version Checker, [6-1](#)
- Version Checker Client window, [6-2](#)
- Versions, [2-18](#)

**W**

- Web servers
  - selecting, [2-7](#)
  - user interface framework, [1-2](#)

**X**

- XML audit message format, [5-2](#)
- XML index file, JavaHelp, [7-3](#)

*ACI Worldwide, Inc.*