

Publications Reissue Highlights

Manual: *BASE24 Transaction Security Services Processing Guide*

Number: BA-AE000-14

Date: 05/2005

Software: Release 6.0, Version 5 (TSS Release 05.2)

The following table highlights the major changes that have been made in the most recent update to the *BASE24 Transaction Security Services Processing Guide*. The first column of the table lists the sections and appendixes in which major changes have been made. The second column of the table describes the major changes for each section or appendix. These changes update the guide to release TSS release 05.2 for BASE24 release 6.0, version 5.

Section/ Appendix	Major Changes
----------------------	---------------

- | | |
|-----|---|
| All | All user security requests now originate from the Java User Interface servlets (ESWEB process). The C++ User Interface (XML Server) process no longer communicates with the User Security (USEC) application. Therefore, USEC application device, lines, and stations and the TCP/IP Adaptor process no longer need to be configured to XPNET. The TCP/IP Adaptor process for the USEC application no longer needs to be configured in the MDSDEST. |
| 2 | Updates the “Internal Memory Tables” discussion for the Channel Security File (CSECD) to indicate that channel security records can be accessed from memory or from disk based on the new CSEC_MEMORY_USE Environment attribute. When accessed from memory, the new MAX_CSEC_IN_MEM Environment attribute specifies the maximum number of records that can be retained in memory. Due to hardware memory limitations, it may not be possible for a single Transaction Security Services process to maintain all CSECD records in memory if the channel (terminal) population exceeds a maximum number of devices. |

Section/ Appendix	Major Changes
----------------------	---------------

-
- | | |
|---|---|
| 3 | <p>Updates the description of the Security Device Configuration window for several changes made to the window. The Subtype field has been replaced with fields specifying the hardware security device model, protocol or interface process used to communicate with the device, and the key scheme used by the device. In addition, fields specifying the automatic reset timer limit, maximum buffer length, and hardware version supported have been added. The reset timer limit is used to automatically re-establish communication with a hardware security device after the device has reached its maximum consecutive errors limit.</p> <p>Clarifies the description of the ATALLA_CHK_DGTS_LGTH Environment attribute. The User Interface process, Check Digit Validation and Generation utility, AKB Conversion utility, and Master File Key Conversion utility use this attribute when using Atalla NSPs.</p> <p>Adds descriptions of the new CSEC_MEMORY_USE and MAX_CSEC_IN_MEM Environment attributes.</p> <p>Deletes the description of the RSM_MFK_SCHEME Environment attribute. This attribute is no longer used in TSS release 05.2.</p> <p>Adds component and process usage to all Environment attribute descriptions.</p> |
| 4 | <p>Clarifies the Generate Check Digits Command topic for Atalla NSPs. The User Interface process, Check Digit Validation and Generation utility, AKB Conversion utility, and Master File Key Conversion utility use the 7E command to generate check digits using the leftmost four digits or the leftmost six digits method. The ATALLA_CHK_DGTS_LGTH Environment attribute specifies whether these utilities generate and validate four or six check digits.</p> <p>Adds the Get System Configuration Information (1110) command for Atalla NSPs. This command is entered during initialization to retrieve the current software version installed in each configured NSP.</p> <p>Adds the Echo Test (0000) function to the table of functions supported for the Eracom ProtectHost White AMB security module.</p> |
| 7 | <p>Adds examples of Eracom and Thales e-Security hardware security device entries to the System Interface Message Delivery Service Destination File (MDSDEST).</p> <p>Removes the entry for the USEC RAM (TCP/IP Adaptor) process from the MDSDEST because the C++ User Interface (XML Server) process no longer communicates with the User Security (USEC) application.</p> |

Section/ Appendix	Major Changes
----------------------	---------------

-
- | | |
|----|--|
| 9 | <p>Clarifies that you can enter the symbolic name of a single process when entering an ALTER or DELIVER command. If you send an ALTER command to symbolic process name, it is only sent to the specified process.</p> <p>Removes the note indicating that INFO and STATUS commands can be sent to a destination in the selectable list for the Destination field. This is incorrect. INFO and STATUS commands can only be sent to the assign name for a single process configured in the System Interface Message Delivery Service Destination File (MDSDEST).</p> <p>Removes process control commands for the Trace component. Trace commands are now entered from the new Trace Configuration window described in section 10.</p> <p>Updates the descriptions of the enable, disable, and initialize security device process control commands for automatic reconnection in the event a security device exceeds its consecutive error limit.</p> <p>The enable and disable security device commands can now only be entered as Alter commands. This ensures that all Transaction Security Services processes receive the enable or disable command and mark the security device as active or inactive in synchronization with all other Transaction Security Services processes.</p> <p>The initialize security device command also causes the firmware version and maximum buffer length for a device to be displayed on the Security Device Configuration window.</p> <p>Clarifies what characters are allowed for the <i>host-name</i>, <i>common-name</i>, and <i>org-name</i> variables in the KEYGEN command for the Transaction Security component and indicates that the <i>host-name</i> variable must currently be set to HOST.</p> <p>Adds the new Refresh Individual CSEC Records command for the Transaction Security component. This command allows you to reread an individual channel security record from disk into memory without deleting any other CSECD records from memory. You can use this command if you maintain Channel Security File (CSECD) records in memory (i.e., the CSEC_MEMORY_USE Environment attribute is set to a value of Y).</p> |
| 10 | <p>Adds a new section for process tracing. Trace commands are now entered from the new Trace Configuration window and are configured on the Trace Configuration window and the new Trace Filter Profile Configuration window. Trace commands are no longer entered from process control commands and you can now filter the transactions to be included in the trace output based on the message source and/or message destination.</p> |

Section/ Appendix	Major Changes
----------------------	---------------

-
- | | |
|---|--|
| B | <p>Removes an inadvertent reference to the Thales e-Security Load a Secret Key (EK) command. The Transaction Security Services process does not use this command because the secret key is stored in the TSS database rather than in HSM memory.</p> <p>Clarifies the step (phase 3, step 7 of the NCR 5XXX terminal implementation procedures) for encrypting the 32-byte message digest with the Secure Configuration Assistant (SCA) when using NCR 5XXX terminals and an Atalla NSP.</p> <p>Clarifies how Diebold 10XX/478X terminals switch from single-length keys to double-length keys.</p> <p>Adds procedures for migrating ATMs from single-length keys to double-lengths.</p> <p>Clarifies what characters are allowed for the <i>host-name</i>, <i>common-name</i>, and <i>org-name</i> variables in the KEYGEN command and indicates that the <i>host-name</i> variable must currently be set to HOST.</p> |
| C | <p>Clarifies that the Check Digit Validation and Generation utility and AKB Conversion utility use the ATALLA_CHK_DGTS_LGTH Environment attribute as well as the Master File Key Conversion utility for Atalla NSPs.</p> <p>Updates the descriptions of the enable, disable, and initialize security device process control commands for automatic reconnection in the event a security device exceeds its consecutive error limit. In addition, the enable and disable security device commands can now only be entered as Alter commands. This ensures that all Transaction Security Services processes receive the enable or disable command and mark the security device as active or inactive in synchronization with all other Transaction Security Services processes.</p> <p>Updates the description of the initialize security device process control command to indicate that the command also causes the firmware version and maximum buffer length for a device to be displayed on the Security Device Configuration window.</p> |
| D | <p>Updates the firmware versions required for Thales e-Security HSMs to support EMV2000 processing.</p> |
| F | <p>Adds a new appendix describing BASE24 support of the NCR PIN verification method.</p> |