# CSE421 Project Group 14 Topic 2 Game of Thrones

Tasnim Sakib Apon

ID: 20241068

Old ID: 18301297

Arpita Datta

ID: 18341008

Kaniz Fatema

ID:19201132

**Fardin Ahmed** 

ID: 17101450

# VLSM/Network Address Table

# 192.168.0.0/18

Host Name	Host	IP	GIVEN IP	Host Bit	Net Bit	IP Address	Subnet Mask
Beyond The wall	5000	5002	8192	13	19	192.168.0.0./19	255.255.224.0
The stromlands	2000	2002	2048	11	21	192.168.32.0/21	255.255.248.0
The north	1024	1026	1048	11	21	192.168.40.0/21	255.255.248.0
The Reach	1000	1002	1024	10	22	192.168.48.0/22	255.255.252.0
The Iron Island	800	802	1024	10	22	192.168.52.0/22	255.255.252.0
The Rocks	480	482	512	9	23	192.168.56.0/23	255.255.254.0
The mountain & the vale	250	252	256	8	24	192.168.58.0/24	255.255.255.0
The Drone	124	126	128	8	24	192.168.59.0/24	255.255.255.0
R0-R2	2	4	4	2	30	192.168.59.192/30	255.255.255.252
R3-R2	2	4	4	2	30	192.168.59.196/30	255.255.255.252
R3-R1	2	4	4	2	30	192.168.59.200/30	255.255.255.252
R0-R1	2	4	4	2	30	192.168.59.208/30	255.255.255.252
R0-R3	2	4	4	2	30	192.168.59.204/30	255.255.255.252

Device	Interface	IP Address	Subnet Mask	Default Gateway
R0	FE0/0	192.168.40.10	255.255.248.0	N/A
	FE1/0	192.168.48.10	255.255.252.0	N/A
	SE2/0	192.168.59.210	255.255.255.252	N/A
	SE3/0	192.168.59.194	255.255.255.252	N/A
	SE7/0	192.168.59.206	255.255.255.252	N/A
R1	FE0/0	192.168.52.10	255.255.252.0	N/A
	FE1/0	192.168.56.10	255.255.254.0	N/A
	SE2/0	192.168.59.210	255.255.255.252	N/A
	SE3/0	192.168.59.202	255.255.255.252	N/A
R2	FE0/0	192.168.0.10	255.255.224.0	N/A
	FE1/0	192.168.32.10	255.255.248.0	N/A
	SE2/0	192.168.59.198	255.255.255.252	N/A
	SE3/0	192.168.59.194	255.255.255.252	N/A
R3	FE0/0	192.168.59.10	255.255.255.0	N/A
	FE1/0	192.168.58.10	255.255.255.0	N/A
	SE2/0	192.168.59.198	255.255.255.252	N/A
	SE3/0	192.168.59.202	255.255.255.252	N/A
	SE7/0	192.168.59.206	255.255.255.252	N/A
192.168.40.9	NIC	192.168.40.9	255.255.248.0	192.168.40.10
192.168.40.8	NIC	192.168.40.8	255.255.248.0	192.168.40.10
192.168.48.9	NIC	192.168.48.9	255.255.252.0	192.168.48.10
192.168.48.8	NIC	192.168.48.8	255.255.252.0	192.168.48.10
192.168.56.9	NIC	192.168.56.9	255.255.254.0	192.168.56.10

192.168.52.8	NIC	192.168.52.8	255.255.252.0	192.168.52.10
192.168.52.9	NIC	192.168.52.9	255.255.252.0	192.168.52.10
192.168.32.8	NIC	192.168.32.8	255.255.248.0	192.168.32.10
192.168.32.9	NIC	192.168.32.9	255.255.248.0	192.168.32.10
192.168.0.5	NIC	192.168.0.5	255.255.224.0	192.168.0.10
192.168.58.9	NIC	192.168.58.9	255.255.255.0	192.168.58.10
192.168.58.8	NIC	192.168.58.8	255.255.255.0	192.168.58.10
192.168.59.9	NIC	192.168.59.9	255.255.255.252	192.168.59.10

# **Commands:**

# Router 0:

Router#enable

Router#conf t

Router#conf terminal

The North

Router(config)#interface fa0/0

Router(config-if)#ip address 192.168.40.10 255.255.248.0

Router(config-if)#no shutdown

Router(config-if)#exit

The Reach

Router(config)#interface fa1/0

Router(config-if)#ip address 192.168.48.10 255.255.252.0

Router(config-if)#no shutdown

Router(config-if)#exit

#### R0-R1

Router(config)#interface Serial2/0

Router(config-if)#ip address 192.168.59.210 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.211

Router(config)#exit

#### R0-R2

Router(config)#interface Serial3/0

Router(config-if)#ip address 192.168.59.194 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.195

Router(config)#exit

#### R0-R3

Router(config)#interface Serial7/0

Router(config-if)#ip address 192.168.59.206 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.207

Router(config)#exit

# Router 1:

Router#enable

Router#conf t

Router#conf terminal

#### The Rock/Lanisters

Router(config)#interface fa1/0

Router(config-if)#ip address 192.168.56.10 255.255.254.0

Router(config-if)#no shutdown

Router(config-if)#exit

#### Iron Island

Router(config)#interface fa0/0

Router(config-if)#ip address 192.168.52.10 255.255.252.0

Router(config-if)#no shutdown

Router(config-if)#exit

#### R1-R0

Router(config)#interface Serial2/0

Router(config-if)#ip address 192.168.59.210 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.211

Router(config)#exit

## R1-R3

Router(config)#interface Serial3/0

Router(config-if)#ip address 192.168.60.202 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.203

Router(config)#exit

# Router 2:

Router>enable

Router#conf t

Router#conf terminal

## **Beyond The Wall**

Router(config)#interface fa0/0

Router(config-if)#ip address 192.168.0.10 255.255.224.0

Router(config-if)#no shutdown

Router(config-if)#exit

**Stromlands** 

Router(config)#interface fa1/0

Router(config-if)#ip address 192.168.32.10 255.255.248.0

Router(config-if)#no shutdown

Router(config-if)#exit

#### R2-R3

Router(config)#interface Serial2/0

Router(config-if)#ip address 192.168.59.198 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.199

Router(config)#exit

## R2-R0

Router(config)#interface Serial3/0

Router(config-if)#ip address 192.168.59.194 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.195

Router(config)#exit

# Router 3:

Router>enable

Router#conf t

Router#conf terminal

#### Drone

Router(config)#interface fa0/0

Router(config-if)#ip address 192.168.59.10 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#exit

## Mount & Valy

Router(config)#interface fa1/0

Router(config-if)#ip address 192.168.58.10 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#exit

#### R3-R2

Router(config)#int se2/0

Router(config-if)#clock rate 64000

Router(config-if)#ip address 92.168.59.198 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

## R3-R0

Router(config)#interface Serial7/0

Router(config-if)#ip address 192.168.59.206 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.207

Router(config)#exit

# <u>R3-R1</u>

Router(config)#interface Serial3/0

Router(config-if)#ip address 192.168.60.202 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.59.203

# Router(config)#exit

## **Static Routing**

#### R1

Router(config)#ip route 192.168.32.0 255.255.248.0 192.168.59.198 Router(config)#ip route 192.168.0.0 255.255.224.0 192.168.0.10 Router(config)#ip route 192.168.58.0 255.255.255 192.168.59.198 Router(config)# ip route 192.168.58.0 255.255.255.0 192.168.58.10 Router(config)# ip route 192.168.59.0 255.255.255.0 192.168.59.10 Router(config)#ip route 192.168.40.0 255.255.248.0 192.168.40.10 Router(config)#ip route 192.168.48.0 255.255.252.0 192.168.48.10

#### R0

Router(config)#ip route 192.168.32.0 255.255.248.0 192.168.32.10 Router(config)#ip route 192.168.0.0 255.255.224.0 192.168.0.10 Router(config)#ip route 192.168.58.0 255.255.255.0 192.168.59.10 Router(config)#ip route 192.168.58.0 255.255.255.0 192.168.59.206 Router(config)#ip route 192.168.59.0 255.255.255.0 192.168.59.206 Router(config)# ip route 192.168.56.0 255.255.254.0 192.168.56.10 Router(config)#ip route 192.168.52.0 255.255.252.0 192.168.56.10

# **Dynamic Routing**

# Router 2

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#router rip

Router(config-router)#version 2

Router(config-router)#no auto-summary

Router(config-router)#network 192.168.60.196

Router(config-router)#network 192.168.0.0

Router(config-router)#network 192.168.60.192

Router(config-router)#network 192.168.32.0

Router(config-router)#default-information originate

Router(config-router)#exit

Router(config)#exit

Router#

<u>%SYS-5-CONFIG\_I: Configured from console by console</u>

copy running-config startup-config

<u>Destination filename [startup-config]?</u>

**Building configuration...** 

[OK]

Router#

## Router 3

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#router rip

Router(config-router)#version 2

Router(config-router)#network 192.168.60.196

Router(config-router)#network 192.168.58.0

Router(config-router)#network 192.168.59.0

Router(config-router)#network 192.168.60.200

Router(config-router)#network 192.168.60.204

Router(config-router)#no auto-summary

Router(config-router)#default-information originate

Router(config-router)#exit

Router(config)#exit

Router#

<u>%SYS-5-CONFIG\_I:</u> Configured from console by console

copy running-config startup-config

<u>Destination filename [startup-config]?</u>

**Building configuration...** 

[OK]

Router#