Lab 5

Samrith Sanjoo.S
1BM21CS185

Configuring DNS with a server and pc and a switch




Server0
Physical
Config
Services
Desktop
Custom Interface
IP Configuration
Interface
FastEthernet0
IP Configuration
DHCP
Static
IP Address
10.0.0.2
Subnet Mask
255.0.0.0
Default Gateway
0.0.0.0
DNS Server
IPv6 Configuration
DHCP
Auto Config
Static
IPv6 Address
Link Local Address
FE80::201:43FF:FECB:1518
IPv6 Gateway
IPv6 DNS Server
Fa0
PC-PT
PC0


PC0
Physical
Config
Desktop
Custom Interface
IP Configuration
IP Configuration
DHCP
Static
IP Address
10.0.0.1
Subnet Mask
255.0.0.0
Default Gateway
0.0.0.0
DNS Server
10.0.0.2
IPv6 Configuration
DHCP
Auto Config
Static
IPv6 Address
Link Local Address
FE80::207:ECFF:FE8E:5173
IPv6 Gateway
IPv6 DNS Server
Fa0
PC-PT
PC0





Rip routing with encapsulation ppp and clock rate:


Cisco Packet Tracer Student
File Edit Options View Tools Extensions Help
Logical
[Root]
New Cluster
Move Object
Set Tiled Background
Viewport
Se2/0
Router-PT
Router1
Se2/0
Router-PT
Router0
Router-PT
Router2
PC-PT
PC0
PC-PT
PC1
Time: 00:21:06
Power Cycle Devices Fast Forward Time
Realtime
Connections
Serial DCE
Scenario 0
New
Delete
Toggle PDU List Window
Fire
Last Status
Source
Destination
Type
Color
Time(sec)
Periodic
Num
Successful
PC0
PC1
ICMP
0.000
N
0
Type here to search
21°C
ENG
17:07
21-07-2023

Router 1:


Cisco Packet Tracer Student
File Edit Options View Tools Extensions Help
Logical
[Root]
New Cluster
Move Object
Set Tiled Background
Viewport
Router0
Physical
Config
CLI
IOS Command Line Interface
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#ip address 20.0.0.1 255.0.0.0
Router(config-if)#clock rate 64000
Router(config-if)#encapsulation ppp
Router(config-if)#exeno
% Incomplete command.
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#clock rate 64000
Router(config-if)#encapsulation ppp
Router(config-if)#exeno shutdown
%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#exit
Router(config)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Copy
Paste
PC-PT
PC0
Time: 00:22:07
Power Cycle Devices Fast Forward Time
Realtime
Connections
Serial DCE
Toggle PDU List Window
PC1
ICMP
0.000
N
0
Type here to search
21°C
ENG
17:08
21-07-2023


Cisco Packet Tracer Student
File Edit Options View Tools Extensions Help
Logical
[Root]
New Cluster
Move Object
Set Tiled Background
Viewport
Router0
Physical
Config
CLI
IOS Command Line Interface
%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#exit
Router(config)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 10.0.0.0
Router(config-router)#
Router(config-router)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 20.0.0.0
Router(config-router)#
Copy
Paste
PC-PT
PC0
Time: 00:22:12
Power Cycle Devices Fast Forward Time
Realtime
Connections
Serial DCE
Toggle PDU List Window
Type here to search
21°C
ENG
17:08
21-07-2023

Router 2:


Cisco Packet Tracer Student
File Edit Options View Tools Extensions Help
Logical
[Root]
New Cluster
Move Object
Set Tiled Background
Viewport
Router1
Physical
Config
CLI
IOS Command Line Interface
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial2/0
Router(config-if)#ip address 20.0.0.2 255.0.0.0
Router(config-if)#encapsulation ppp
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router(config-if)#exit
Router(config)#
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#ip address 30.0.0.1 255.0.0.0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#clock rate 64000
Router(config-if)#encapsulation ppp
Router(config-if)#no shutdown
%LINK-5-CHANGED: Interface Serial3/0, changed state to down
Copy
Paste
Router-PT
Router0
PC-PT
PC0
Time: 00:23:16
Power Cycle Devices Fast Forward Time
Realtime
Connections
Serial DCE
Toggle PDU List Window
Type here to search
21°C
ENG
17:09
21-07-2023


Cisco Packet Tracer Student
File Edit Options View Tools Extensions Help
Logical
[Root]
New Cluster
Move Object
Set Tiled Background
Viewport
Router1
Physical
Config
CLI
IOS Command Line Interface
Router(config)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router(config)#interface Serial3/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 20.0.0.0
Router(config-router)#
Router(config-router)#exit
Router(config)#interface Serial3/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 30.0.0.0
Router(config-router)#
Copy
Paste
Router-PT
Router0
PC-PT
PC0
Time: 00:23:23
Power Cycle Devices Fast Forward Time
Realtime
Connections
Serial DCE
Toggle PDU List Window
Time(sec) Periodic Num
0.000 N 0
Type here to search
21°C
ENG
17:09
21-07-2023

Router 3:


Cisco Packet Tracer Student
File Edit Options View Tools Extensions Help
Logical
[Root]
New Cluster
Move Object
Set Tiled Background
Viewport
Router2
Physical
Config
CLI
IOS Command Line Interface
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial3/0
Router(config-if)#ip address 30.0.0.2 255.0.0.0
Router(config-if)#encapsulation ppp
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
exe
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router(config-if)#exit
Router(config)#
Router(config)#interface Serial3/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 40.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if)#exit
Copy
Paste
PC-PT
PC0
Time: 00:24:18
Power Cycle Devices Fast Forward Time
Realtime
Connections
Serial DCE
Toggle PDU List Window
Type Color Time(sec) Periodic Num
PC1 ICMP 0.000 N 0
Type here to search
21°C
ENG
17:10
21-07-2023



Ping from pc1 to pc2:10.0.0.1 to 40.0.0.2