



FACULTÉ DES SCIENCES ET DES TECHNOLOGIES(FST)

TD N°_5 – SYSTÈME

COURS: SYSTÈME

PRÉNOM: Lens Sandro

NOM: PÉTIOTE

NIVEAU: L3

DATE: 07/12/2025


L'objectif de ce TD est de:

1. Comprendre le rôle d'un serveur de fichiers
2. Configurer des partages Samba (Windows / Linux)
3. Configurer des partages NFS (Linux/Unix)
4. Gérer les permissions, montages automatiques et sécurité
5. Tester l'accessibilité depuis plusieurs clients
6. Analyser la différence entre Samba et NFS

La plupart des volets on déjà été traités dans le TD 4

3-

Permission



```
lens@lens-server: ~  
Dec 6 20:40  
lens@lens-server:~$ sudo find /srv/samba -perm -o+w  
/srv/samba/public  
/srv/samba/shared  
lens@lens-server:~$ sudo find /srv/samba -perm -4000  
lens@lens-server:~$ sudo nano /etc/samba/smb.conf  
lens@lens-server:~$ sudo systemctl restart smbd  
lens@lens-server:~$ testparm  
Load smb config files from /etc/samba/smb.conf  
Loaded services file OK.  
Weak crypto is allowed by GnuTLS (e.g. NTLM as a compatibility fallback)  
Server role: ROLE_STANDALONE  
Press enter to see a dump of your service definitions  
# Global parameters  
[global]  
    log file = /var/log/samba/log.%m  
    logging = file  
    map to guest = Bad User  
    max log size = 1000  
    obey pam restrictions = Yes  
    pam password change = Yes  
    panic action = /usr/share/samba/panic-action %d  
    passwd chat = *Enter\snew\s*\spassword:* %n\n *Retye\snew\s*\spassword:* %n\n *password\supdated\ssuccessfully*  
    .  
    passwd program = /usr/bin/passwd %u  
    server role = standalone server  
    server string = %h server (Samba, Ubuntu)  
    unix password sync = Yes  
    usershare allow guests = Yes  
    idmap config * : backend = tdb
```

```
Dec 6 20:40
lens@lens-server: ~
Server role: ROLE_STANDALONE
Press enter to see a dump of your service definitions

# Global parameters
[global]
    log file = /var/log/samba/log.%m
    logging = file
    map to guest = Bad User
    max log size = 1000
    obey pam restrictions = Yes
    pam password change = Yes
    panic action = /usr/share/samba/panic-action %d
    passwd chat = *Enter\snew\s*\spassword:* %n\n *Retye\snew\s*\spassword:* %n\n *password\supdated\ssuccessfully*

    passwd program = /usr/bin/passwd %u
    server role = standalone server
    server string = %h server (Samba, Ubuntu)
    unix password sync = Yes
    usershare allow guests = Yes
    idmap config * : backend = tdb

[printers]
    browseable = No
    comment = All Printers
    create mask = 0700
    path = /var/tmp
    printable = Yes

[print$]
    comment = Printer Drivers
```

```
[Public]
    guest ok = Yes
    path = /srv/samba/public
    read only = No

[dev]
    path = /srv/samba/dev
    read only = No
    valid users = @dev
    write list = @dev

[sec]
    path = /srv/samba/sec
    read only = No
    valid users = @sec
    write list = @sec

[ops]
    path = /srv/samba/ops
    read only = No
    valid users = @ops
    write list = @ops


[Shared]
    create mask = 01777
    path = /srv/samba/shared
    read only = No

lens@lens-server:~$
```

4. Accédez au serveur samba depuis un client Windows

Recherche de mon ip address

```
lens@lens-server:~$ ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host noprefixroute
        valid_lft forever preferred_lft forever
2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP group default qlen 1000
    link/ether 08:00:27:6b:6c:c5 brd ff:ff:ff:ff:ff:ff
    inet 10.0.2.15/24 brd 10.0.2.255 scope global dynamic noprefixroute enp0s3
        valid_lft 86213sec preferred_lft 86213sec
    inet6 fd17:625c:f037:2:da47:6e01:3ae7:ff2c/64 scope global temporary dynamic
        valid_lft 86215sec preferred_lft 14215sec
    inet6 fd17:625c:f037:2:a00:27ff:fe6b:6cc5/64 scope global dynamic mngtmpaddr
        valid_lft 86215sec preferred_lft 14215sec
    inet6 fe80::a00:27ff:fe6b:6cc5/64 scope link
        valid_lft forever preferred_lft forever
3: enp0s8: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP group default qlen 1000
    link/ether 08:00:27:1d:e3:15 brd ff:ff:ff:ff:ff:ff
    inet 192.168.56.105/24 brd 192.168.56.255 scope global dynamic noprefixroute enp0s8
        valid_lft 414sec preferred_lft 414sec
    inet6 fe80::5b14:5d4:dd4a:f49f/64 scope link noprefixroute
        valid_lft forever preferred_lft forever
```



Malheureusement windows ne peut pas trouver mon ip address. Je n'arrive pas a connecter au server Samba depuis Windows.

5. Audit du serveur Samba

```
Dec 8 02:32
lens@lens-server: ~
inet6 fe80::5b14:5d4:dd4a:f49f/64 scope link noprefixroute
valid_lft forever preferred_lft forever
lens@lens-server:~$ getfacl -R /srv/samba
getfacl: Removing leading '/' from absolute path names
# file: srv/samba
# owner: root
# group: root
user::rwx
group::r-x
other::r-x
# file: srv/samba/public
# owner: root
# group: root
user::rwx
group::rwx
other::rwx
# file: srv/samba/sec
# owner: root
# group: sec
# flags: -s-
user::rwx
group::rwx
```

```
Dec 8 02:33
lens@lens-server: ~
group::rwx
other::rwx
# file: srv/samba/sec
# owner: root
# group: sec
# flags: -s-
user::rwx
group::rwx
other::---
getfacl: /srv/samba/sec: Permission denied
# file: srv/samba/shared
# owner: root
# group: root
# flags: --t
user::rwx
group::rwx
other::rwx
# file: srv/samba/partage
# owner: lens
# group: lens
user::rwx
```

```
Dec 8 02:34
lens@lens-server: ~
tail: cannot open '/var/log/samba/log.smb' for reading: No such file or director
y
lens@lens-server:~$ sudo tail -n 50 /var/log/samba/log.smbd
[2025/12/06 16:59:37.848285, 0] source3/smbd/server.c:1746(main)
smbd version 4.19.5-Ubuntu started.
Copyright Andrew Tridgell and the Samba Team 1992-2023
[2025/12/06 19:46:05.280282, 0] source3/smbd/server.c:1746(main)
smbd version 4.19.5-Ubuntu started.
Copyright Andrew Tridgell and the Samba Team 1992-2023
[2025/12/06 20:30:05.617893, 0] source3/smbd/server.c:1746(main)
smbd version 4.19.5-Ubuntu started.
Copyright Andrew Tridgell and the Samba Team 1992-2023
[2025/12/06 20:48:49.145190, 0] source3/smbd/server.c:1746(main)
smbd version 4.19.5-Ubuntu started.
Copyright Andrew Tridgell and the Samba Team 1992-2023
[2025/12/06 20:59:11.228472, 0] source3/smbd/server.c:1746(main)
smbd version 4.19.5-Ubuntu started.
Copyright Andrew Tridgell and the Samba Team 1992-2023
[2025/12/07 02:26:16.474173, 0] source3/smbd/server.c:1746(main)
smbd version 4.19.5-Ubuntu started.
Copyright Andrew Tridgell and the Samba Team 1992-2023
[2025/12/07 02:43:26.964254, 0] source3/smbd/server.c:1746(main)
smbd version 4.19.5-Ubuntu started.
Copyright Andrew Tridgell and the Samba Team 1992-2023
```

```
Dec 8 02:34
lens@lens-server: ~
getfacl: /srv/samba/ops: Permission denied
lens@lens-server:~$ sudo pdbedit -L
carla:1015:
lens:1000:Lens Sandro
Tom:1001:
marie:1004:
flore:1006:
jean:1002:
martine:1005:
joseph:1007:
ralph:1008:
junior:1009:
josue:1010:
paul:1011:
bruno:1012:
andre:1013:
islande:1014:
lens@lens-server:~$ sudo smbstatus

Samba version 4.19.5-Ubuntu
  PID Username Group Machine Protocol Version Encryption Signi
ng
-----
-----

Service pid Machine Connected at Encryption Signing
-----
-----

No locked files
lens@lens-server:~$
```

Coclusion.

Ce travail m'a permis de Configurer des partages Samba (Windows / Linux), configurer des partages NFS (Linux/Unix), gérer les permissions, montages automatiques et sécurité, tester l'accessibilité depuis plusieurs clients, analyser la différence entre Samba et NFS. Donc la tâche est réussie.