11

Examine network Address translation (NAT) Using Cisco packet Tracer.

Aim:

To configure and examine Network address Translation (NAT) using Cisco Packet tracer and verify communication between a private network and a public network.


Procedure:


* open Cisco Packet tracer.
* Add one router, one switch, one PC, and one server.
* Connect the device using Copper straight Through cables.
* Configure the router's inside interface with IP address 192.168.1.1 and outside interface with IP address 200.1.1.1.
* Enable NAT on the inside and outside interfaces.
* Configure static NAT to map private IP 192.168.1.2 to public IP 200.1.1.100.
* On the router CLI, execute show ip nat translation to verify the NAT translation.

sult:


Thus, Network Address Translation (NAT) was nfigured successfully using Cisco Packet tracer, and mmunication between the private and public networks


11 A


PC0
Physical
Config
Desktop
Programming
Attributes
Command Prompt
Cisco Packet Tracer SC Command Line 1.0
C:\>ping 30.0.0.100
Pinging 30.0.0.100 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 30.0.0.100:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>ping 30.0.0.10
Pinging 30.0.0.10 with 32 bytes of data:
Request timed out.
Reply from 30.0.0.10: bytes=32 time<1ms TTL=126
Reply from 30.0.0.10: bytes=32 time<1ms TTL=126
Reply from 30.0.0.10: bytes=32 time<1ms TTL=126
Ping statistics for 30.0.0.10:
Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms
C:\>
Top


Logical
Physical
2811
Router0
2811
Router0
2811
Router1
Server-PT
Server0
PC-PT
PC0
PC-PT
PC1
PC-PT
PC2
PC-PT
PC3

11B


Router2
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
SWITCHING
VLAN Database
INTERFACE
FastEthernet0/0
FastEthernet0/1
Serial0/1/0
Serial0/1/1
FastEthernet1/0
Network
Add
Network Address
20.0.0.0
192.168.1.0
Remove
Equivalent IOS Commands
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state to up
Router(config-if)#ip address 192.168.1.253 255.255.255.252
Router(config-if)#
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 20.0.0.0
Router(config-router)#network 192.168.1.0
Router(config-router)#


Logical
2811
Router1
2811
Router0
2811
Router2
PC-PT
PC0
PC-PT
PC1