




CT/2021/039

Step 01





PC1

Physical Desktop Custom Interface

IP Configuration

IP Configuration

☐ DHCP ☒ Static

IP Address 192.168.6.3

Subnet Mask 255.255.255.0

Default Gateway 192.168.6.126

DNS Server

IPv6 Configuration

☐ DHCP ☐ Auto Config ☒ Static

IPv6 Address /

Link Local Address FE80::260:47FF:FE3E:E8E4

IPv6 Gateway

IPv6 DNS Server

PC2

Physical

Desktop

Custom Interface

IP Configuration

X

IP Configuration

☐ DHCP

☒ Static

IP Address

192.168.7.66

Subnet Mask

255.255.255.192

Default Gateway

192.168.7.126

DNS Server

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

/

Link Local Address

FE80::201:64FF:FE11:5721

IPv6 Gateway

IPv6 DNS Server



PC-06

PhysicalDesktopCustom Interface

IP Configuration

IP Configuration

☐ DHCP

☒ Static

IP Address

192.168.67.2

Subnet Mask

255.255.255.192

Default Gateway

192.168.7.62

DNS Server

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

/

Link Local Address

FE80::290:CFF:FE71:5EC2

IPv6 Gateway

IPv6 DNS Server



PC-05

PhysicalDesktopCustom Interface

IP Configuration

IP Configuration

☐ DHCP

☒ Static

IP Address

192.168.6.130

Subnet Mask

255.255.255.128

Default Gateway

192.168.6.254

DNS Server

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

/

Link Local Address

FE80::2E0:B0FF:FE48:C9D1

IPv6 Gateway

IPv6 DNS Server



PC-04

Physical Desktop Custom Interface

IP Configuration

IP Configuration

☐ DHCP ☒ Static

IP Address 192.168.6.131

Subnet Mask 255.255.255.128

Default Gateway 192.168.6.254

DNS Server

IPv6 Configuration

☐ DHCP ☐ Auto Config ☒ Static

IPv6 Address /

Link Local Address FE80::202:16FF:FE77:98B0

IPv6 Gateway

IPv6 DNS Server

Question 05



The screenshot shows a network switch's Command Line Interface (CLI) window. The window has a title bar with 'SW-03' and standard window controls. Below the title bar are two tabs: 'Physical' and 'CLI', with 'CLI' being the active tab. The main area is titled 'IOS Command Line Interface' and contains a text box with the following text:

```
up
%LINK-5-CHANGED: Interface FastEthernet0/2, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to up

Switch>ena
Switch>enable
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname SW-03
SW-03(config)#exit
SW-03#
%SYS-5-CONFIG_I: Configured from console by console

SW-03#clock set?
set
SW-03#clock set?
set
SW-03#clock set ?
  hh:mm:ss Current Time
SW-03#clock set 9:16:00 ?
  <1-31> Day of the month
  MONTH Month of the year
SW-03#clock set 9:16:00 10 April 2025 ?
  <cr>
SW-03#clock set 9:16:00 10 April 2025
SW-03#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
SW-03(config)#enable password
% Incomplete command.
SW-03(config)#enable password FCI
SW-03(config)#enable secret 1234
SW-03(config)#banner motd #Unauthorized access #
SW-03(config)#line console 0
SW-03(config-line)#password FCI
SW-03(config-line)#login
SW-03(config-line)#exit
SW-03(config)#
```

At the bottom right of the window, there are two buttons: 'Copy' and 'Paste'.

Question 06

```
R-01
Physical CLI

third-party authority to import, export, distribute or use encryption.
Importers, exporters, distributors and users are responsible for
compliance with U.S. and local country laws. By using this product you
agree to comply with applicable laws and regulations. If you are unable
to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at:
http://www.cisco.com/wvl/export/crypto/tool/stgrg.html

If you require further assistance please contact us by sending email to
export@cisco.com.

Cisco CISC02911/KS (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
3 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
256K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R-01
R-01(config)#interface gigabitethernet0/0
R-01(config-if)#description SW-01 link
R-01(config-if)#ip address 192.168.6.126 255.255.255.128
R-01(config-if)#no shutdown

R-01(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

R-01(config-if)#exit
R-01(config)#interface gigabitethernet0/1
R-01(config-if)#description R-01 link R-03
R-01(config-if)#ip address 192.168.7.129 255.255.255.252
R-01(config-if)#no shutdown

R-01(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

R-01(config-if)#exit
R-01(config)#interface gigabitethernet0/2
R-01(config-if)#description R-01 link R-04
R-01(config-if)#ip address 192.168.7.133 255.255.255.252
R-01(config-if)#no shutdown

R-01(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up

R-01(config-if)#exit
R-01(config)#
```

Importers, exporters, distributors and users are responsible for compliance with U.S. and local country laws. By using this product you agree to comply with applicable laws and regulations. If you are unable to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at:
<http://www.cisco.com/wvl/export/crypto/tool/stqrg.html>

If you require further assistance please contact us by sending email to export@cisco.com.

Cisco CISC02911/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
3 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: no

Press RETURN to get started!

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface gigabitethernet0/0
Router(config-if)#description R-02 link R-01
Router(config-if)#ip address 192.168.7.130 255.255.255.252
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#interface gigabitethernet0/1
Router(config-if)#description Sw-02 link
Router(config-if)#ip address 192.168.7.62 255.255.255.192
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

Router(config-if)#exit
Router(config)#interface gigabitethernet0/2
Router(config-if)#ip address 192.168.7.137 255.255.255.252
Router(config-if)#description RW-02 link RW-03
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up

Router(config-if)#exit
Router(config)#interface gigabitethernet0/
```

R-03

Physical

CLI

```
export@cisco.com.

Cisco CISC02911/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
3 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#configure terminal
      ^
% Invalid input detected at '^' marker.

Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface gigabitethernet0/1
Router(config-if)#description RW-03 link RW-02
Router(config-if)#ip address 192.168.7.138 255.255.255.252
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

Router(config-if)#exit
Router(config)#interface gigabitethernet0/2
Router(config-if)#description RW-03 link RW-04
Router(config-if)#ip address 192.168.7.141 255.255.255.252
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up

Router(config-if)#exit
Router(config)#interface gigabitethernet0/0
Router(config-if)#description RW-03 link SW_03
Router(config-if)#ip address 192.168.7.254 255.255.255.128
% 192.168.7.128 overlaps with GigabitEthernet0/1
Router(config-if)#exit
Router(config)#interface gigabitethernet0/0
Router(config-if)#description RW-03 link SW_03
Router(config-if)#ip address 192.168.6.254 255.255.255.128
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#
```

Importers, exporters, distributors and users are responsible for compliance with U.S. and local country laws. By using this product you agree to comply with applicable laws and regulations. If you are unable to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at:
<http://www.cisco.com/wvl/export/crypto/tool/stqrg.html>

If you require further assistance please contact us by sending email to export@cisco.com.

Cisco CISC02911/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
3 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
256K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: no

Press RETURN to get started!

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface gigabitethernet0/2
Router(config-if)#description RW-04 link Rw-03
Router(config-if)#ip address 192.168.7.142 255.255.255.252
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2, changed state to up

Router(config-if)#exit
Router(config)#interface gigabitethernet0/1
Router(config-if)#description RW-04 link Rw-01
Router(config-if)#ip address 192.168.7.134 255.255.255.252
Router(config-if)#no shutdown


Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

Router(config-if)#exit
Router(config)#interface gigabitethernet0/0
Router(config-if)#description RW-04 link SW-04
Router(config-if)#ip address 192.168.6.126 255.255.255.192
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
```



Question 07

```
SW-02
Physical  CLI

Cisco IOS Software, C2960 Software (C2960-LANBASE-M), Version 12.2(25)FX, RELEASE SOFTWARE (fc1)
Copyright (c) 1986-2005 by Cisco Systems, Inc.
Compiled Wed 12-Oct-05 22:05 by pt_team
Image text-base: 0x80008098, data-base: 0x814129C4

Cisco WS-C2960-24TT (RC32300) processor (revision C0) with 21039K bytes of memory.

24 FastEthernet/IEEE 802.3 interface(s)
2 Gigabit Ethernet/IEEE 802.3 interface(s)

63488K bytes of flash-simulated non-volatile configuration memory.
Base ethernet MAC Address       : 00D0.BA09.912C
Motherboard assembly number     : 73-9832-06
Power supply part number        : 341-0097-02
Motherboard serial number       : FOC103248MJ
Power supply serial number      : DCA102139JA
Model revision number           : B0
Motherboard revision number     : C0
Model number                    : WS-C2960-24TT
System serial number            : FOC103321EY
Top Assembly Part Number        : 800-26671-02
Top Assembly Revision Number    : B0
Version ID                      : V02
CLEI Code Number               : COM3K00BRA
Hardware Board Revision Number  : 0x01


Switch  Ports  Model          SW Version      SW Image
-----  -
* 1    26    WS-C2960-24TT  12.2           C2960-LANBASE-M

Cisco IOS Software, C2960 Software (C2960-LANBASE-M), Version 12.2(25)FX, RELEASE SOFTWARE (fc1)
Copyright (c) 1986-2005 by Cisco Systems, Inc.
Compiled Wed 12-Oct-05 22:05 by pt_team

Press RETURN to get started!

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

Switch>enabl
Switch#sh mac address-table
      Mac Address Table
-----
Vlan    Mac Address      Type      Ports
----    -
1       000c.cfal.9902   DYNAMIC   Gig0/1
Switch#
```



```
R-01>enable
R-01#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R-01(config)#ip route 192.168.7.0 255.255.255.192 192.168.7.130
R-01(config)#i
R-01#
%SYS-5-CONFIG_I: Configured from console by console

R-01#sh ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

    192.168.6.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.6.0/25 is directly connected, GigabitEthernet0/0
L       192.168.6.126/32 is directly connected, GigabitEthernet0/0
    192.168.7.0/24 is variably subnetted, 5 subnets, 3 masks
S       192.168.7.0/26 [1/0] via 192.168.7.130
C       192.168.7.128/30 is directly connected, GigabitEthernet0/1
L       192.168.7.129/32 is directly connected, GigabitEthernet0/1
C       192.168.7.132/30 is directly connected, GigabitEthernet0/2
L       192.168.7.133/32 is directly connected, GigabitEthernet0/2
R-01#
```

Copy Paste

IOS Command Line Interface

```
Router>enable
Router#sh ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

    192.168.7.0/24 is variably subnetted, 6 subnets, 3 masks
C       192.168.7.0/26 is directly connected, GigabitEthernet0/1
L       192.168.7.62/32 is directly connected, GigabitEthernet0/1
C       192.168.7.128/30 is directly connected, GigabitEthernet0/0
L       192.168.7.130/32 is directly connected, GigabitEthernet0/0
C       192.168.7.136/30 is directly connected, GigabitEthernet0/2
L       192.168.7.137/32 is directly connected, GigabitEthernet0/2
Router#
```

Copy

Paste

IOS Command Line Interface

```
Router(config-if)#exit
Router(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2, changed state
to up

Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#sh ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

    192.168.6.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.6.128/25 is directly connected, GigabitEthernet0/0
L       192.168.6.254/32 is directly connected, GigabitEthernet0/0
    192.168.7.0/24 is variably subnetted, 4 subnets, 2 masks
C       192.168.7.136/30 is directly connected, GigabitEthernet0/1
L       192.168.7.138/32 is directly connected, GigabitEthernet0/1
C       192.168.7.140/30 is directly connected, GigabitEthernet0/2
L       192.168.7.141/32 is directly connected, GigabitEthernet0/2
Router#
```

Copy

Paste

IOS Command Line Interface

```
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state
to up

Router(config-if)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#sh ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

      192.168.6.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.6.64/26 is directly connected, GigabitEthernet0/0
L       192.168.6.126/32 is directly connected, GigabitEthernet0/0
      192.168.7.0/24 is variably subnetted, 4 subnets, 2 masks
C       192.168.7.132/30 is directly connected, GigabitEthernet0/1
L       192.168.7.134/32 is directly connected, GigabitEthernet0/1
C       192.168.7.140/30 is directly connected, GigabitEthernet0/2
L       192.168.7.142/32 is directly connected, GigabitEthernet0/2
Router#
```

Copy

Paste