

# **FORGECLOUDS**

EAZYGO - Requirement Spec



#### **LOGIN SCREEN**

- User Name is the email ID
- Password for credentials with case sensitive
- Face ID for login (optional)
- Forgot Password (Get the Email ID and send email to User with new password
- Submit button will login to home screen
- Two types of Logins (Admin-user login & End-user login)
- First time user creation will be done by Admin-user login and share the credentials to end-user thru email
- Time out for the app will be set to 1 mins



### Admin-User - User Setup SCREEN

- List all users in the Admin-user Home Screen
- New User will open a new box where we collect following information
  - First Name
  - Last Name
  - Email ID
  - Active (Y/N)
  - Admin (Y/N)
- Password will be first three digit of first name and three digit of last name (all small character)




#### Admin-User - User Setup SCREEN

- Click of the three ... will pop-up the new drop down box (Activate, Delete and Edit)
- Click of Activate will enable the user. If the user is already active the popup will show "De-Activate"
- Delete will permanently delete the user
- Edit will allow to edit emailID, name, Admin(Y/N), Active(Y/N)




#### Admin-User - Site Setup SCREEN

- List all Site in the Admin-user Site Setup Screen
- Add Plant will pop-up new box and get the following information
  - Site name
- At any give point in time, only one Site will be Active. The Active site will be highlighted in different color
- Click of the site will take to Section page (Next page)




#### Admin-User - Site Setup SCREEN

- Click on three ... will pop-up new window (Activate and Edit)
- Activate will make this site Active and disable other active site (as the requirement is to keep only active site at a time)
- Edit will allow us to change the name of the site



#### Admin-User - Section Setup SCREEN

- Section is child entity of Site
- List all Section created under the particular site (Seguin, TX as shown in the screen)
- Add Section will get input new section name
- Click of the Section will take to Sub-Section page (Next page)



### Admin-User - Section Setup SCREEN

- Click on three ... will pop-up window (Edit & Delete)
- Delete is allowed only if there is no Sub-Section of this section

\_

# **EA7YGO**




#### **Site:** Seguin, TX => Line 1

Blowers	
Molder	•••
Filling	
Cap Sealing	•••
Palletizer	
Conveyer Belt 1	•••
Conveyer Belt 2	•••

Add Sub-Section

### Admin-User - Sub-Section Setup SCREEN

- Sub-Section is child entity of Section
- List all Sub-Section created under the particular section (Seguin, TX => Line 1 as shown in the screen)
- Add Sub-Section will get input new section name
- Click of the Sub-Section will take to Motor List page (Next page)



### Admin-User - Sub-Section Setup SCREEN

- Click on three ... will pop-up window (Edit & Delete)
- Delete is allowed only if there is no motor of this sub-section

\_



### **EAZYGO**

#### **Motor List**

Site:

Seguin, TX

Section:

Line 1


Sub-Section: Molder

Si.NO	DXM	Motor Number	Radio Number	Image	Edit/Delete
1	1	M253-2345	ID23451	?	
2	1	M213-8574	ID56789	?	
3	1	M253-5748	ID55645	?	
4	5	M512-3483	ID54378	?	
5	5	M245-9685	ID55667	?	
6	7	M254-8574	ID67584	?	:
7	7	M324-5748	ID45683	?	

Scan New Motor

#### End-User - Motor List SCREEN

- By default Active site is selected
- Section and Sub-Section will be empty by default
- Drop-down box of Section will be listed with all the Sections under that site
- Drop-down box of Sub-Section will be listed with all the Sub-Sections under the Section. (If Section is not selected, Sub-section will be empty)
- Both Section and Sub-Section is optional
- If No Section and Sub-Section are selected, All motors under that site will be listed
- Three ... will pup-up the window with Edit and Delete options
- Edit will take to Edit Motor Section (as shown in next page)
- Delete will delete the motor information. Ask for the confirmation before Delete ("Are you sure you want to Delete this Motoer")



#### End-User - Motor List SCREEN

- By default Active site is selected (This box is disabled. It cannot be edited)
- Section and Sub-Section will be empty by default
- Drop-down box of Section will be listed with all the Sections under that site
- Drop-down box of Sub-Section will be listed with all the Sub-Sections under the Section
- Both Section and Sub-Section is optional
- DXM is alpha-numeric text box
- Motor is alpha-numeric text box
- Radio is alpha-numeric text box
- Image 1, 2 & 3 should enable the camera and capture the images
- Images are optional