ISC_DHCP setup Docs

Connection scheme

Config - server

enp0s8 – internal network
enp0s3 - NAT

Netplan static IP (enp0s8):

```
Terminal
  GNU nano 7.2                /etc/netplan/50-cloud-init.yaml
# This file is generated from information provided by the datasource.  Changes
# to it will not persist across an instance reboot.  To disable cloud-init's
# network configuration capabilities, write a file
# /etc/cloud/cloud.cfg.d/99-disable-network-config.cfg with the following:
# network: {config: disabled}
network:
    ethernets:
        enp0s3:
            dhcp4: true
        enp0s8:
            dhcp4: false
            addresses:
                - 192.168.0.1/24
            gateway4: 192.168.0.1
            nameservers:
                addresses: [8.8.8.8 , 1.1.1.1]
    version: 2

                                [ Read 17 lines ]
^G Help      ^O Write Out ^W Where Is  ^K Cut       ^T Execute   ^C Location
^X Exit      ^R Read File ^\ Replace   ^U Paste     ^J Justify   ^/ Go To Line
```

DHCP(dhcpd.conf) config:

```
Terminal
  GNU nano 7.2                /etc/dhcp/dhcpd.conf
# dhcpd.conf
#
# Sample configuration file for ISC dhcpd
#
# Attention: If /etc/ltsp/dhcpd.conf exists, that will be used as
# configuration file instead of this file.
#

# option definitions common to all supported networks...
option domain-name "example.org";
option domain-name-servers ns1.example.org, ns2.example.org;

default-lease-time 600;
max-lease-time 7200;

subnet 192.168.0.0 netmask 255.255.255.0 {
  range 192.168.0.1 192.168.0.254;
  option routers 192.168.0.1;
}
```

Interface for dhcp to use (/etc/default/isc-dhcp-server):

```
Terminal
  GNU nano 7.2                    isc-dhcp-server
# Defaults for isc-dhcp-server (sourced by /etc/init.d/isc-dhcp-server)

# Path to dhcpd's config file (default: /etc/dhcp/dhcpd.conf).
#DHCPDv4_CONF=/etc/dhcp/dhcpd.conf
#DHCPDv6_CONF=/etc/dhcp/dhcpd6.conf

# Path to dhcpd's PID file (default: /var/run/dhcpd.pid).
#DHCPDv4_PID=/var/run/dhcpd.pid
#DHCPDv6_PID=/var/run/dhcpd6.pid

# Additional options to start dhcpd with.
#       Don't use options -cf or -pf here; use DHCPD_CONF/ DHCPD_PID instead
#OPTIONS=""

# On what interfaces should the DHCP server (dhcpd) serve DHCP requests?
#       Separate multiple interfaces with spaces, e.g. "eth0 eth1".
INTERFACESv4="enp0s8"
INTERFACESv6=""

                                [ Read 18 lines ]
^G Help      ^O Write Out ^W Where Is  ^K Cut       ^T Execute   ^C Location
^X Exit      ^R Read File ^\ Replace   ^U Paste     ^J Justify   ^/ Go To Line
```

Config - client

enp0s8 – internal network
enp0s3 - NAT
Netplan (enp0s8):



Typical Problems

1) Misspelling in commands
2) Same network already exists which may bug both of the networks
3) Not using local netowork’s reserved range of ips (For example – using global IP’s , which also can bug the network)

Problems occurred

- Incorrectly set range of IP’s