


Quick Start Guide

Use this guide in conjunction with the SeisWare Trial Data Set.
For additional information refer to the Workflows section of the SeisWare Help files
Or contact the SeisWare International Inc. Support Team at:
(403) 265-6606 ~ 1 (866) 914-9047 ~ support@seisware.com


Main Launcher

The SeisWare Main Launcher allows you to access your project, the information stored within your project and the advanced functionality that SeisWare offers.




Under each heading you will find information about the properties of your project, the import and export options, and the advanced functionality, for example 3D Auto Picker, Grid and Contour and Time to Depth.

Attaching to a Project



1. From the Main Launcher select **Project > Attach**



2. Click **Find** and map to the SeisWare Trial dataset

Navigating the Basemap

Define Home Position: this will define a home position that can be returned to by pressing the **Go to Home Position** icon ()

Zoom In: press and hold the left mouse button while dragging out the area to fit within the window



Fit Basemap to Window: this will adjust the zoom level such that all data will be visible in the window

Zoom Out by 50%: the centre spot of the map will stay the same, the map will zoom out by 50%

Displaying Horizons on the

Select the horizon "Top 1" from the drop down list on the Horizon Toolbar to see it displayed on the map



Use these to toggle on and off the selected horizon from 2D and 3D seis-

Basemap Properties

General Basemap Properties controls the appearance of the map including map colors, line display properties and postings, and well appearance and criteria.




Use the icon on the Basic Toolbar or select General Properties from the right mouse button menu of the Basemap

Hit the  to see the properties contain within each heading, then change the settings seen in the right hand box of the dialog

Layer Properties: control which layers are visible on the Basemap, and in which order they will be drawn

Well Properties: change the appearance of wells on the Basemap, display curves, and create criteria for well display



Color Properties: change the colorbar by selecting from the dropdown list, specify the colorbar range, set colorbar markers and toggle horizon and well ribbons



Seismic, SEG-P and Grid Properties: specify the line, symbols, posting and label characteristics for 2D, 3D, SEG-P

Selecting Seismic from Basemap



Arbitrary Line for 2D and 3D Seismic:

Start by one left mouse button click on the icon
Open entire 2D line: right mouse button on the line
Open a portion of a line: left mouse button to start selection, left mouse button to end selection, right mouse button to open the seismic viewer
Open a 2D intersection: left mouse button on a starting point of the first line, left mouse button on the end point of the second line, right mouse button on a end point of the second line

3D Inline and Crossline

Start by one left mouse button click on the Inline or Crossline icon
Open entire line: right mouse button on the 3D
Open a portion of a line: left mouse button to start selection, left mouse button to end selection, right mouse button to open the seismic viewer right mouse button to open the seismic viewer.

Creating a Grid and Contour



Displaying a Grid on the Basemap: select a grid from the dropdown menu. The grid and any associated contours will draw on the Basemap


Open the Grid and Contour wizard using this icon, or by selecting Grid and Contour from the Tools menu. You will be guided through the creation of a grid and its associated contours and can change the gridding method and output parameters for the map

Seismic Properties

Seismic Display Properties controls the appearance of the Seismic viewer including trace spacing and scaling, annotation sizing and timing lines.



Use the icon on the Seismic Toolbar or select General Properties from the right mouse button menu



Click on each tab to adjust the properties contained within each section


Horizons



Use this icon, press the H key on the keyboard, or select **Pick Horizons** from the Horizon menu

1. Select the horizon you wish to edit from the Horizon drop-down list, or type in a horizon name to create a new horizon.

2. Press the Properties button to view and adjust the properties for the horizon, including the Event Type and Color



Pick Modes

Auto Pick: left mouse button automatically picks to the left of the cursor, right mouse button to the right

Snap Stream: with the left mouse button held down use the cursor to follow an event

Guide: press the left mouse button to start, stretch out the band, and release the mouse button

Manual: use the left mouse button to place picks exactly instead of snapping to an event

Deleting Horizons: use the **shift** key. Horizons will be deleted using the current Pick Mode


Faults



Use this icon, press the F key on the keyboard, or select **Pick Faults** from the Faults menu

1. Select the fault you wish to edit from the Fault drop-down list, or type in a fault name to create a new fault.

2. Press the Properties button to view and adjust the properties for the fault, including Type and Color



Picking Faults: use the left mouse button to place a node, and the right mouse button to finish the selection

Editing Faults: hold down the left mouse button on a node and drag

Deleting Nodes: select a node with the left mouse button and hit delete

Inserting a Node: with the fault selected press the insert key at the node location

Deleting Fault Segments: select the segment and press delete