

R1:

```
conf t
interface fastEthernet0/0
ip address 192.168.2.2 255.255.255.0
description Link to
R5 no shutdown
exit
interface fastEthernet1/0
ip address 192.168.1.1 255.255.255.0
description Link to
Switch1 no shutdown
end
write memory
```

R2:

```
conf t
interface fastEthernet0/0
ip address 192.168.1.2 255.255.255.0
description Link to
Switch1 no shutdown
exit
interface fastEthernet1/0
ip address 192.168.6.1 255.255.255.0
description Link to
R6 no shutdown
end
write memory
```

R3:

```
conf t
```

```
interface fastEthernet0/0
ip address 192.168.1.3 255.255.255.0
description Link to
Switch1 no shutdown
exit
interface fastEthernet1/0
ip address 192.168.9.1 255.255.255.0
description Link to
R7 no shutdown
exit
interface fastEthernet2/0
ip address 192.168.11.1 255.255.255.0
description Link to
R8 no shutdown
end
write memory
```

```
R4:
conf t
interface fastEthernet0/0
ip address 192.168.4.2 255.255.255.0
description Link to
PC1 no shutdown
exit
interface fastEthernet1/0
ip address 192.168.3.1 255.255.255.0
description Link to
R5 no shutdown
end
write memory
```

```
R5:
conf t
interface fastEthernet2/0
ip address 192.168.2.1 255.255.255.0
description Link to
R1 no shutdown
exit
interface fastEthernet1/0
ip address 192.168.3.2 255.255.255.0
description Link to
R4 no shutdown
exit
interface fastEthernet0/0
```

```
ip address 192.168.5.2 255.255.255.0
description Link to
PC2 no shutdown
end
```

write memory

R6:

conf t

interface fastEthernet0/0

ip address 192.168.6.2 255.255.255.0

description Link to

R2 no shutdown

exit

interface fastEthernet1/0

ip address 192.168.7.1 255.255.255.0

description Link to

PC3 no shutdown

exit

interface fastEthernet2/0

ip address 192.168.8.1 255.255.255.0

description Link to

R7 no shutdown

end

write memory

R7:

conf t

interface fastEthernet2/0

ip address 192.168.8.2 255.255.255.0

description Link to

R6 no shutdown

exit

interface fastEthernet0/0

ip address 192.168.9.2 255.255.255.0

description Link to

R3 no shutdown

exit

interface fastEthernet1/0

ip address 192.168.10.1 255.255.255.0

description Link to

PC4 no shutdown

end

write memory

R8:

conf t

interface fastEthernet0/0

ip address 192.168.11.2 255.255.255.0

description Link to

R3 no shutdown

exit

interface fastEthernet1/0

ip address 192.168.12.1 255.255.255.0

description Link to
PC5 no shutdown
end
write memory

PC1:

ip 192.168.4.1 255.255.255.0 192.168.4.2
save

PC2:

ip 192.168.5.1 255.255.255.0 192.168.5.2
save

PC3:

ip 192.168.7.2 255.255.255.0 192.168.7.1
save

PC4:

ip 192.168.10.2 255.255.255.0 192.168.10.1
save

PC5:

ip 192.168.12.2 255.255.255.0 192.168.12.1
save

1. Настройка RIP

v2 R1:

conf t
router rip
version 2
no auto-summary
network
192.168.2.0 end
write memory

R4:

conf t
router rip
version 2
no auto-summary
network 192.168.3.0
network
192.168.4.0 end
write memory

R5:

conf t

```
router rip
version 2
no auto-summary
network 192.168.2.0
```

```
network 192.168.3.0
network
192.168.5.0 end
write memory
```

```
conf t
router ospf 1
network 192.168.1.0 0.0.0.255 area 0
network 192.168.2.0 0.0.0.255
area 0 end
write memory
```

```
R2:
conf t
router ospf 1
network 192.168.1.0 0.0.0.255 area 0
network 192.168.6.0 0.0.0.255
area 2 end
write memory
```

```
R3:
conf t
router ospf 1
network 192.168.1.0 0.0.0.255 area 0
network 192.168.9.0 0.0.0.255 area 2
network 192.168.11.0 0.0.0.255
area 1 area 1 stub no-summary
end
write memory
```

```
R6:
conf t
router ospf 1
network 192.168.6.0 0.0.0.255 area 2
network 192.168.7.0 0.0.0.255 area 2
network 192.168.8.0 0.0.0.255
area 2 end
write memory
```

```
R7:
conf t
```

```
router ospf 1
network 192.168.8.0 0.0.0.255 area 2
network 192.168.9.0 0.0.0.255 area 2
network 192.168.10.0 0.0.0.255
area 2 end
write memory
```

```
R8:
conf t
router ospf 1
network 192.168.11.0 0.0.0.255 area 1
network 192.168.12.0 0.0.0.255 area 1
area 1
stub end
write memory
```

```
conf t
router ospf 1
redistribute rip
subnets exit
router rip
redistribute ospf 1 metric
3 end
write memory
```