

ARCADE HUB

COMPLETE USER MANUAL

Document Version 1.0 • 2026

Main Menu

Pac-Man Header

An animated header is located at the top of the screen: Pac-Man runs along a rainbow track, and the words **DENDY, SEGA, SNES, NEO GEO, DOS, HTML, GBA** appear. This is an atmospheric element with no functional actions.

Top Action Panel



Add Games

Opens a system file picker. Supports multiple selection and ZIP archives.



Pencil

Enables library edit mode: selection, deletion, export.



Network game panel. Create a room or connect to a friend.



Window with a list of supported platforms and extensions.



Donation button with a pulsing heart animation.

System Filters

A horizontal ribbon of buttons for quick sorting:

System	Color	Action
DENDY	Red	Filter NES / .nes
SEGA	Blue	Filter Mega Drive / .md, .gen, .smd, .bin
SNES	Purple	Filter Super Nintendo / .sfc, .smc
NG	Teal	Filter Neo Geo Pocket / .ngp, .ngc
GBA	Pink	Filter Game Boy Advance / .gba
DOS	Green	Filter MS-DOS / .zip
HTML	Orange	Filter HTML5 / .html
	White	Randomly shuffle the list

Clicking on a filter places the selected system first in the list. Clicking  shuffles the games randomly.

Search and Display Views

- **Search** — works in real-time, filtering the list as you type.

- **View Toggle** — three modes: grid (2 columns), list (vertical), large cards (1 column with large covers).

Library Edit Mode

Activated by the pencil button. Game cards become selectable, and the edit panel appears.

Button	Description
 ALL	Selects all games in the library
 DESELECT	Deselects all games
 TO ZIP	Export to ZIP: as a single file, by console, or split into 200 MB chunks
 LOGO	Auto-search for covers in the Libretro Thumbnails database by game title
 PHOTO	Upload a custom cover for a single selected game
 RESET 	Removes "favorite" marks from all games
 DELETE	Deletes selected games from IndexedDB (browser memory)

Tip: A long press (1.5 sec) on a game card in normal mode automatically enables edit mode and selects that game.

Adding Games (Import)

Game Screen

Upon launching a game, the menu smoothly fades to black, and a **CRT turn-on animation** plays: a white line expands from the center to full screen with the sound of a picture tube warming up.

Floating Toolbar

A semi-transparent panel with round buttons appears at the top. It can be collapsed into a thin "▼ MENU" strip.

Button	Action
↔ Back	Exits the game. Before exiting, it auto-saves the state and plays the CRT turn-off animation (collapses into a line → dot → fades out).
↺ Restart	Full restart. Offers three options: save and restart, erase all saves and start from scratch, or cancel.
↓ Save	Creates a snapshot (save state) in IndexedDB. For NES — JSON, for Libretro — .state, for DOS — ZIP of the entire file system.
↑ Load	Loads the latest save. If auto-load is enabled, it happens automatically at startup.
🎮 Gamepad	Shows/hides the touch gamepad.
⌨ Keyboard	Shows the panel with F1-F12, ESC, Enter, Space (for DOS).
🖥 Screen	Opens the graphics and effects settings panel.



Opens the touch controls configuration panel.



Network game panel right during gameplay.



Graphics Settings (Screen Edit Panel)

A draggable window with a handle at the top. Contains the following options:

Screen Type (CRT Matrix)

- **OFF** — clean image without effects.
- **Scanlines** — dark horizontal lines, like on old TVs.
- **Trinitron** — premium Sony Trinitron CRT effect with bright stripes.
- **LCD Matrix** — imitation of bulging pixels from old LCDs (Game Boy, NGP).

Curvature

Makes the screen edges bulge like an old picture tube, with corner darkening (vignette).

Internal Resolution

Upscale: 1x (original), 2x, 4x, 8x, 16x. Increases the internal rendering resolution, making pixels less "jagged." For powerful devices.

RGB Shift (Chromatic Aberration)

Shifts the red and blue channels relative to green, creating an old optics effect.

Smoothing Algorithm

- **OFF** — sharp pixels.
- **SHARP** — bilinear filter, smooths slightly.
- **SOFT** — strong blur "retro blur".
- **FSR** — smart sharpness (similar to AMD FidelityFX), sharp image without blur.

xBR Vector

Smart scaling: the algorithm "draws in" the edges of sprites, preserving the pixel style but making them smooth.

Bloom

Bright areas of the screen (explosions, neon) start glowing, creating an overexposure effect.

Color Correction (Gamma)

Gamma correction: deeper shadows, softer highlights, richer colors.

Screen Size

Buttons $\leftrightarrow +$, $\leftrightarrow -$, $\updownarrow +$, $\updownarrow -$ change the scale. In screen edit mode, you can **use your finger to move** the playing field around the screen for perfect centering under a camera notch.

Important: All graphics settings are saved separately for each game. Global settings act as a template for new games.

Control Settings (Pad Edit Panel)

A draggable window for customizing touch buttons.

General Settings

- **Auto-Brake** — automatically presses the brake button when the D-Pad is released. Useful for racing games.
- **D-Pad: Fixed / Floating** — in floating mode, the directional pad appears where your finger touches the left side of the screen.
- **Control Mode:**
 - **SWIPE (SMOOTH)** — standard 8-way directional control.
 - **STEP-BY-STEP** — strictly one direction, no diagonals.
 - **SHOOTER (STICK + LOOK)** — left stick moves the character, the right half of the screen is for aiming/shooting.

Button Editor

Tapping any button on the screen highlights it with a yellow border. Then the following is available:

- **Size** — + and - buttons change the scale.

- **Opacity** — from 10% to 100%. Buttons can be made invisible.
- **Brightness** — from 50% to 200%.
- **Feedback (Vibration)** — from 0 to 60 ms. Adjusts the phone's vibration strength when pressed.
- **Dragging** — the selected button can be moved around the screen.



Network Game (P2P)

Save System

Manual Save

The "Save" button in the toolbar creates a state snapshot:

- **NES** — full JSON state of the jsnes emulator.
- **Sega/SNES/GBA/NGP** — .state file via Libretro API.
- **DOS** — ZIP of the entire virtual file system (excluding .exe/.bat).

Auto-Save

- When minimizing the tab (Alt+Tab, Home button).
- When exiting via the "Back" button.
- For heavy systems (SNES/Sega), a "Saving... 15 sec" timer is shown.

Auto-Load

Clicking the colored system badge (NES/SEGA/SNES tag) on a game card in the menu enables a neon glow. This means the save will load automatically on the next launch.



Modal Windows

Window	Content
 Info	List of platforms and extensions. Notifies about ZIP archive support.
 Export	Three options: single file, by console, by console split up to 200 MB.
 Restart	Three options: save and restart, erase saves and start from scratch, cancel.
 Language	Choice of 35 languages. Translates the entire interface instantly.



Gamepad Navigation

Virtual Keyboard

Appears when tapping the search bar (if system input is disabled). Contains:

- Letters, numbers,  (erase),  (close).
-  **Clear** — clears the entire query.
-  **Close** — hides the keyboard.
- Handle for dragging around the screen.
- Scale buttons: , , ,  (change width and height separately).

Smart Transparency: when scrolling the game list, the keyboard automatically becomes 80% transparent so as not to obscure the cards. Returns 600 ms after stopping.

Visual and Audio Effects

Dynamic Backlight (Spotify Glow)

The menu background changes color depending on the selected console: Dendy — red, Sega — blue, SNES — purple, DOS — green, etc. Works during filtering, hovering, and returning from a game.

Sound Engine (AudioGen)

- **Click** — when pressing any UI button.
- **TV Turn On** — CRT warm-up sound at game start.
- **TV Turn Off** — switch click + CRT fading "pew-w-w" on exit.

CRT Animations

- **Turn On** — a white line expands from the center.
- **Turn Off** — the screen collapses into a line, then a dot. The line color matches the current console color.



Technical Features