

Illumisoft

Radar System 2

Documentation

Welcome & Get Started Video	3
Installation.....	3
Usage.....	4
Adding the Radar.....	4
Adding the Compass.....	4
Adding Locatable Components.....	5
FAQ	6
Q: The radar or compass isn't showing any icons. What's wrong?	6
Q: What's the difference between the Radar and the Compass?.....	6
Q: How do I keep the radar from rotating with the player?	6
Q: Can I show quest markers even if they're far away?	6
Q: How do I change the size of icons on the radar or compass?	6
Q: Do I need to assign both the Player and Camera transforms?	6
Q: Can I use my own custom icons?.....	6
Support	7

Welcome & Get Started Video

Welcome to this quick introduction to Radar System 2, a plug and play radar and compass system, allowing you to add a radar and compass to your project in minutes. The easiest way to get started is to follow our get started video: https://youtu.be/Vn_K2zLsfUI



Installation

To install the Unity Radar System Plugin, follow these steps:

1. Add the plugin package from the Unity Asset Store to "My Assets"
2. Create or open a Unity project and download and install the plugin from the package manager
3. The plugin will be installed in your project and you will be able to access it through the Unity editor.

Usage

Adding the Radar

To add the **Radar** to your scene:

1. Open the **Prefabs** folder: Assets/Ilumisoft/Radar System/Prefabs
2. Drag and drop the **Radar** prefab into your scene.
3. Select the Radar GameObject and assign the **Player** and **Camera Transform** fields in the Inspector.

☒ The radar is now active!

Optional settings you can tweak:

- **Detection Range** – Set how far objects can be detected.
- **Icon Scale** – Adjust the size of radar icons.
- **Lock Rotation** – Prevent the radar from rotating with the player.

Adding the Compass

To add the **Compass**:

1. Navigate to the **Prefabs** folder: Assets/Ilumisoft/Radar System/Prefabs
2. Drag and drop the **Compass** prefab into your scene.
3. Select the Compass GameObject and assign the **Player** and **Camera Transform** fields in the Inspector.

☒ Your compass is now ready to use!

Additional configuration options:

- **Detection Range** – Control how far icons are visible.
- **Distance-Based Scaling** – Automatically scale icons based on their distance from the player.
- **Detection Angle** – Limit what is visible based on a field-of-view cone.

Adding Locatable Components

To make an object appear on the radar and/or compass, add the **Locatable** component.

Steps:

1. Select the GameObject you want to track.
2. In the Inspector, click **Add Component > Radar System > Locatable**.

Configure the following properties:

- **Icon Prefab** – The icon that will represent this object on the radar or compass.
- **Ignore Detection Range** (*optional*) – Enable this if the object should always be visible, even when outside the detection range (e.g. quest markers).

Important: Objects without the **Locatable** component will not show up on the radar or compass.

FAQ

Q: The radar or compass isn't showing any icons. What's wrong?

A: Make sure the GameObjects you want to appear on the radar or compass have the **Locatable** component attached and a valid **Icon Prefab** assigned. Also ensure their positions are within the **detection range** set on the Radar or Compass or that **Ignore Detection Range** is enabled.

Q: What's the difference between the Radar and the Compass?

A: The **Radar** shows objects in a top-down, minimap-like view. The **Compass** shows objects relative to the player's forward direction, like a navigation bar. You can use either one - or both - depending on your game's needs.

Q: How do I keep the radar from rotating with the player?

A: Select the Radar prefab in your scene and enable the **Lock Rotation** option in the Inspector. This will keep the radar's orientation fixed.

Q: Can I show quest markers even if they're far away?

A: Yes! Enable the **Ignore Detection Range** option on the Locatable component. This makes the icon always visible, no matter how far the object is.

Q: How do I change the size of icons on the radar or compass?

A: Icon size can be controlled in two ways:

Use the **Icon Scale** setting on the Radar/Compass prefab.

Customize the icon prefab itself (e.g., scale the UI image inside the prefab).

For the compass, you can also enable **Distance-Based Scaling** to make icons shrink as they get farther from the player.

Q: Do I need to assign both the Player and Camera transforms?

A: Yes, both are required for proper icon positioning and direction calculation. The Player is used as the center reference, and the Camera helps calculate angles and screen space for icons.

Q: Can I use my own custom icons?

A: Absolutely! Just create a prefab with a UI element (e.g., an Image component), add the **Locatable Icon** component and then assign it to the **Icon Prefab** field in the **Locatable** component.

Support

If you like the project, please take a minute and give us a rating in the Asset Store. This really helps us to create and improve our Unity Assets.

If you encounter any problems or errors, please contact us via email:

support@ilumisoft.de