

How do I Install VNC Viewer and VNC Server?

This document should assist in the steps of installing and configuring both VNC Viewer and VNC Server on a Windows Operating System. VNC viewer can be used to remote into another system for visual display. To login to the machines using VNC Viewer VNC Server must be installed.

Installing VNC Viewer


1. Navigate to the following location:

\\Server-Name\Folder-Name\Software\UltraVNC Viewer


2. Install the file named **UltraVNC_1_2_11X64_Setup.exe**.
3. Open the application named select **Run**.

Name	Date modified	Type	Size
 UltraVNC_1_2_11_X64_Setup.exe	9/29/2016 1:45 PM	Application	2,729 KB

4. Select Setup Language leave the default language and select **Ok**.




5. On the License Agreement screen, Click the radio button next to **I accept the agreement**.




6. Click **Next**.

7. On the **Select Components** screen, select **UltraVNC Viewer**.




8. Select to install VNC Viewer on the laptop or machine in which they will be viewing from.

9. On the Select Additional Tasks screen, select to create UltraVNC desktop icons, click **next**.



10. Click **Install**.



11. Click **Next**.
12. Click **Finish**.

Installing VNC Server


1. Navigate to the following location:

\\Server-Name\Folder-Name\Software\UltraVNC Viewer


2. Install the file named **UltraVNC_1_2_11X64_Setup.exe**.
3. Open the application named select **Run**.

Name	Date modified	Type	Size
 UltraVNC_1_2_11_X64_Setup.exe	9/29/2016 1:45 PM	Application	2,729 KB

4. Select Setup Language leave the default language and select **Ok**.




5. On the License Agreement screen, Click the radio button next to **I accept the agreement**.




6. Choose **Next**.


- On the **Select Components** screen, Select **UltraVNC Server**.



- On the Select Additional Tasks screen, you can select to create UltraVNC desktop icons, click **next**.




9. Once you have made your selections, click **Install**.



10. Click **Next**.
11. Click **Finish**.

- VNC Server Will require that you setup a password in admin configuration on the computer that has VNC Server installed.



12. **Click** the arrow on the taskbar to open all programs.
13. Search for **VNC Server**.
14. **Right-click** the blue VNC Server icon.
15. Set a **VNC password** on the machines where VNC Server is installed.
16. Click **Apply**.

Logging into VNC Viewer

1. Enter the **Computer name**.
2. Select **Connect** and enter the **VNC Password**.

