

Enabling the CLIENTS and ATTACK Zones

The two unused interfaces on OPNsense were enabled and configured as new network zones. In the web interface under **Interfaces**, each one was turned on, given a description, and assigned a static IPv4 address:

Interface	Device	Description	Address
OPT1	em2	CLIENTS	10.10.20.1/24 (static)
OPT2	em3	ATTACK	10.10.30.1/24 (static)

The changes were saved and applied. The **Interfaces** → **Overview** page confirmed that all four zones are up with the correct addresses: WAN (10.0.2.15/24), LAN (10.10.10.1/24), CLIENTS (10.10.20.1/24), and ATTACK (10.10.30.1/24). Each zone now has its own subnet, with OPNsense acting as the gateway between them.

Status	Interface	Device	VLAN	Link Type	IPv4	IPv6	Gateway	Routes	Commands
	WAN (wan)	em0		dhcp	10.0.2.15/24	fd17:625c:f037:2:a00:27f:fe80::a00:27f:fe61:acd0/	10.0.2.2 fe80::2	default 10.0.2.0/24 10.0.2.3 default fd17:625c:f037:2::/64 fe80::%em0/64	...
	LAN (lan)	em1		static	10.10.10.1/24	fe80::a00:27f:fe3b:9354/		10.10.10.0/24 fe80::%em1/64	
	CLIENTS (opt1)	em2		static	10.10.20.1/24			10.10.20.0/24	
	ATTACK (opt2)	em3		static	10.10.30.1/24			10.10.30.0/24	
	Loopback (lo0)	lo0		static	127.0.0.1/8	::1/128 fe80::1/64		10.0.2.15 10.10.10.1 10.10.20.1 10.10.30.1 127.0.0.1 ::1 fd17:625c:f037:2:a00:27f:fe80::a00:27f:fe61:acd0/ fe80::a00:27f:fe3b:9354/ fe80::%lo0/64 ...	
	Unassigned interface	enc0							
	Unassigned interface	pflog0							

1

Showing 1 to 7 of 7 entries