

OUTPUT SCREENS

- Create the network by taking some PC's and Router's and also Access Pointer's.




FIG 1

- Assign accordingly, by dividing into three Floors as shown below.




FIG 2

- Give DHCP, IP address to PC'S using Router and Access Pointer.




FIG 3

➤ Command Prompt to check the DHCP of PC's




FIG – 4.1




FIG – 4.2

Router1

Physical Config CLI Attributes

GLOBAL

- Settings
- Algorithm Settings

ROUTING

- Static
- RIP

INTERFACE

- FastEthernet0/0
- FastEthernet1/0
- Serial2/0
- Serial3/0
- FastEthernet4/0
- FastEthernet5/0

Serial2/0

Port Status ☒ On

Duplex ☐ Full Duplex

Clock Rate 1200

IP Configuration

IPv4 Address 30.30.30.3

Subnet Mask 255.0.0.0

Tx Ring Limit 10

Equivalent IOS Commands

```

Press RETURN to get started!

Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial2/0
Router(config-if)#
  
```

☐ Top

Router0

Physical Config CLI Attributes

IOS Command Line Interface

```

Press RETURN to get started!

Press RETURN to get started!

Press RETURN to get started!

Press RETURN to get started!

Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#router ospf 1
Router(config-router)#network 10.0.0.0 0.255.255.255 area 0
% Invalid input detected at '^' marker.
Router(config-router)#network 10.0.0.0 0.255.255.255 area 0
Router(config-router)#network 40.0.0.0 0.255.255.255 area 0
Router(config-router)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
  
```

☐ Top

Copy Paste

FIG – 4.3

- Connect Laptop ,Smartphone, tablet 's to the three Router.






FIG – 5.1






FIG – 5.4

