Simple Camera

Description:


Is a camera control plug-in,Perfect for beginners,Includes mobile and PC support, which can rotate, zoom, pan, rise, fall and follow the target. After selecting the target, the camera will automatically center the target, and can also focus on the target based on the set weight to watch the target in close range. You can limit the moving area of the camera and reset the camera position: **it is very suitable for factory roaming from the third perspective**, and it can be viewed from any Angle in the Game view during Demo, similar to the camera function in the Scene window

Features:


- The camera is automatically centered when the target is selected
- Rotate around the target as it is selected
- Limit the camera's overlooking Angle and range or (Use Fixed Angle)
- Camera Pan,Limit the camera's movement area(Multiple modes of translation:mouse,KeyBoard,Screen)
- Camera Zoom/Height,Mouse or keyboard zoom,Vertical rise and fall
- Focus target,Press F to focus the target,And there are focused event callbacks
- Click or double - click the selected object(To choose from)
- Whether to detect the UI. The camera control function is not triggered when the UI is on
- You can configure individual object parameters, such as distance adjustment when selected, speed of rotation around the current object, zoom speed, focus weight, Can also be configured to select objects when the camera You can also customize the orientation of the camera when the object is selected etc

Usage:


1.Import the UnityPackage,Open SR_Camera/Prafabs(You can also drag Prefab into the scene to configure the parameters directly)
SR_Camera.Prefab -----PC
SR_MobileCamera.Prefab-----Mobile




2.If you don't want to use prefab you can give it to the Main camera:Add Component **SR_Camera** Scipt




3.Click GlobalConfig:Configure the layer that detects the ground,Set the Map center location and Camera range Height,Sets the area and scope of the virtual target point




4.**Notice**:When the camera has no target, it calculates the target point through ray detection and rotates around the virtual target point ,Therefore, the ground and wall that need ray detection need to add collider, and set Layer correctly




5.**Notice:If there is no EventSystem in your scene,** Scene need to add EventySystem, which is used to check whether the mouse is on the UI event(Editor selection:GameObject-->UI-->EventSystem)




6.Sets the Tag of the optional object,Configure the Tag in the SR Camera script,The camera will only interact with the set Tag object







7.(**Optional**)If you want to configure the different effects of the selection of objects, such as how far away from the selection of objects, which Angle, focus weight, rotation speed, zoom speed
You need to add the **ParameterConfiguration** script to the selected object ,
This configuration script is available for both PC and mobile




8.(**Optional**)If you want to directly set camera position and rotation,You can do this by calling the SR Camera method **SetCameraPostionRotation**, And pass the parameters position and rotation,This is provided that the position and rotation are limited to the configured range and Angle




9.(**Optional**)If you want to pass an object directly for the camera to track, instead of clicking to trigger the camera to select it ,By calling **SR_Camera** Class **SetTarget**(Transform Target) method ,Transmit the target **Transfom** you want to trace directly



10.(**Optional**)If you don't want the camera to follow or focus on the current target, you can go up/down vertically by panning the camera ,Or click on a space on the ground,Or reset the target by calling SR_Camera's **ResetTarget** method (**Note: Rotation and scaling do not lose target**)



Event the camera is exposed



1.SelectTargetAction: Emitted when an object is selected
2.ResetTargetAction: Emitted when a target is lost or reset
3.FocusStartAction:Focus on the beginning of the pullback
4.FocusEndAction:Focus on the completed callback
5.ResetCameraTransfomCompleteAction:Emitted when resetting camera position and rotation is complete(Make sure the location rotation is within the specified range, otherwise it will never be completed)

Support and Contact

If you need help or have any suggestions, please send me a mail at
sunrui19950302@163.com
I will be glad to answer