

XRDP in ubuntu machine

Ubuntu machine graphically using RDP (XRDP)

Port **3389** = RDP port.

Follow the steps:

Step-1: Install XRDP on Ubuntu

```
# sudo apt update
# sudo apt install xrdp -y
```

```
siddharrth@master:~$ sudo apt install xrdp -y
Reading package lists... Done
Building dependency tree... Done
Reading state information... Done
The following additional packages will be installed:
  libpipewire-0.3-modules-xrdp pipewire-module-xrdp xorgxrdp
Suggested packages:
  guacamole
The following NEW packages will be installed:
  libpipewire-0.3-modules-xrdp pipewire-module-xrdp xorgxrdp xrdp
```

```
Generating 2048 bit rsa key...
ssl_gen_key_xrdp1 ok
saving to /etc/xrdp/rsakeys.ini
Created symlink /etc/systemd/system/multi-user.target.wants/xrdp-sesman.service → /usr/lib/systemd/system/xrdp-sesman.service.
Created symlink /etc/systemd/system/multi-user.target.wants/xrdp.service → /usr/lib/systemd/system/xrdp.service.
Setting up libpipewire-0.3-modules-xrdp:amd64 (0.2-2) ...
Setting up xorgxrdp (1:0.9.19-1) ...
Setting up pipewire-module-xrdp (0.2-2) ...
Processing triggers for man-db (2.12.0-4build2) ...
Processing triggers for libc-bin (2.39-0ubuntu8.7) ...
Scanning processes...
Scanning linux images...
```

Step-2: Check the status of xrdp

```
# sudo systemctl status xrdp
```

```
siddharrth@master:~$ sudo systemctl status xrdp
● xrdp.service - xrdp daemon
   Loaded: loaded (/usr/lib/systemd/system/xrdp.service; enabled; preset: enabled)
   Active: active (running) since Wed 2026-05-20 04:56:31 UTC; 1min 38s ago
     Docs: man:xrdp(8)
           man:xrdp.ini(5)
   Process: 59856 ExecStartPre=/bin/sh /usr/share/xrdp/socksetup (code=exited, status=0/SUCCESS)
   Process: 59865 ExecStart=/usr/sbin/xrdp $XRDP_OPTIONS (code=exited, status=0/SUCCESS)
   Main PID: 59866 (xrdp)
    Tasks: 1 (limit: 4706)
   Memory: 860.0K (peak: 1.5M)
```

If, it shows inactive. Follow the steps

```
# sudo systemctl start xrdp
```

```
# sudo systemctl enable xrdp
```

Step-3: Check if XRDp is listening:

```
# ss -tulnp | grep 3389
```

```
siddharrth@master:~$ ss -tulnp | grep 3389
tcp    LISTEN 0      2            *:3389      *:*
```

Step-4: Install Desktop Environment

```
# sudo apt install ubuntu-mate-desktop -y
```

Step-5: Set MATE for XRDp

```
# echo "mate-session" > ~/.xsession
```

Restart the xrdp

```
# sudo systemctl restart xrdp
```

```
siddharrth@master:~$ echo "mate-session" > ~/.xsession
siddharrth@master:~$ sudo systemctl restart xrdp
```

Step-6: Status of firewall and selinux

Make sure the ports are allowed or firewall and selinux are disabled

```
siddharrth@master:~$ sudo ufw status
Status: inactive
siddharrth@master:~$ getenforce
Disabled
```

Step-7: Try login with XRDp using RDP

Click 'window key' -> search for RDP -> Open RDP -> Enter the machine IP "10.10.40.88"



