

ACTIVATION

This is an Add-on, please contact us to activate.

Once activated, you can enable it in the continuous project. [read more about continuous projects.](#)

TENABLE VULNERABILITY MANAGEMENT INTEGRATION

1. AUTHENTICATING THE INTEGRATION


Integrating Cyver Core with Tenable Vulnerability Management is a very easy process. Just navigate to Administration/Integrations and follow the instructions.

To generate an API key from Tenable Vulnerability Management, follow this link: [Generate API Keys.](#)

To integrate Tenable with your environment, you must provide a valid **Access Key** and **Secret Key**. You can link multiple access keys to support tenant-level configurations.

- **Manage Multiple Tenants:** You can link multiple access keys. These will be displayed in a grid view for easy management across different tenants.
- **Validation:** Upon entering your credentials, the system performs a `GET` request to the Tenable API.
- **Verification:** If the

authentication is successful, the newly added keys will appear in your integration list.




2. CONFIGURING THE PROJECT TEMPLATE

Once authenticated, you can enable Tenable for your workflows:

1. Create a new **Continuous Project Template**.
2. Navigate to the **Vulnerability Scanner** dropdown menu.
3. Select **Tenable Vulnerability Management**.

***Note:** This option is only visible if a valid pair of API keys has been successfully linked to your account.*




STARTING A SCAN

PREREQUISITES

Before initiating a scan within Cyver, ensure the following conditions are


met:

- **Existing Scans:** You must have pre-configured Scans within your Tenable instance.
- **Target Definitions:** Scans will execute against the **Targets defined in Tenable**, not those set within the Project's Scope.



EXECUTION STEPS


1. **Select API Credentials:** Go to **Project Settings** and choose the specific API key required to retrieve your available Tenable Scan.



2. **Select the Scan:** Choose the desired Scan from the populated list.



3. **Launch:** Once selected, you are authorised to trigger the scan. This initiates an **on-demand scan** in Tenable for your predefined targets.



SCHEDULE AND ON-DEMAND SCANS

You can activate the Schedule Scan for weekly automated scans:

☒ Include weekly score

Day of week

for weekly

Time

00:00

Amount field for Target including

Instructions

Cancel

OK