SLEM

NBA 2K27 / Cronus Zen / v5.0 / tiktok/slem_2k

discord.gg/hsKWu8y3Ek

What this is

Three shooting modes. Only one runs at a time. Turn one on, the others turn off by themselves.

- TEMPO - you time it, script does the flick. Main system
- GREEN - fully auto, script holds the button
- QS GREEN - same but stops you first

Every mode owns its numbers. Pick your mode, tune that section, never touch the others.

MOVE, DEF and SYS run alongside whatever you picked.

New in v5

- TUNE - the script finds your MS for you. One tuner per mode
- REMAP X in every mode, not just TEMPO. Off by default
- Quickstop rebuilt - LT + right stick flick down, with a WAIT you set yourself
- QS TEMPO removed. Nobody used it
- Fatigue is much gentler. LOW was moving your timing far too much
- Six dribble moves across three sets, up from two
- HAND setting for left handed players
- LATENCY per mode instead of one global
- Fixed: turning a mode off actually turns it off
- Fixed: the scrolling footer no longer prints garbage

First flash

- First boot wipes to defaults on purpose. v5 changed the storage layout
- Don't tune before that or you lose it
- Saves every time you close the menu

PlayStation

This guide uses Xbox button names. On PS: X is Square, B is Circle, LB is L1, RB is R1, LT is L2, RT is R2, LS is L3, RS is R3, START is OPTIONS.

So opening the menu is L2 + OPTIONS.

Setting the Zen up on PS4 or PS5 is a separate guide. Do that first.

Menu

- LT + START - open / close (saves on close)
- LT + RT - go into a section
- LT + RB - back out
- LT + UP / DOWN - move
- LT + LEFT / RIGHT - change value

- LT + RT + LEFT / RIGHT - change faster

The top line scrolls the controls, so you never need this page open to navigate.

Nine sections: TEMPO, GREEN, QS GREEN, MOVE, DEF, the three TUNE menus, and SYS.

Leave the menu open, let go of LT, shoot. Hold LT again to change the number. Tune way faster.

TUNE - read this first

The script finds your numbers for you. A separate menu per mode, so you only ever tune the one you actually use.

Menu	Shots	What it finds
TUNE TEMPO	9	FLICK, FADE L, FADE R
TUNE GREEN	15	STAND, MOVE L, MOVE R, FADE L, FADE R
TUNE QSGRN	3	QS GREEN stand

How it runs

Go into the menu you want and hit LT + RT on START.

The menu closes and all three shooting modes switch off, so nothing interferes. You are playing clean, taking normal shots yourself.

```
   STAND          which shot it wants
----------
LAST   712        the ms it just measured off you
  2 OF 3
[======    ]
```

Take 3 of that shot type. Try to green them. After the third it shows what it worked out:

```
   STAND
----------
   712
A KEEP  B REDO
```

- A writes that number into the real setting and moves to the next shot type
- B throws those 3 away and redoes the same one

When the last one is done it says TUNING DONE, saves, and puts your mode back on.

LT + START aborts at any point.

What it actually measures

- GREEN and QS GREEN watch how long you hold the shoot button. The auto hold is off while tuning, so you are shooting manually and the script learns your own timing
- TEMPO watches your stick. It times the flick from stick down to stick up. That travel time is your tempo

Three shots, the middle one wins, anything wildly off gets thrown out.

Notes

- Watch the LAST number. If it never appears, it is not reading you. Check the mode's BUTTON setting matches the button you are pressing
- Tuning a TEMPO fade turns FADE SPLIT on by itself, because it just measured left and right separately
- Green more of them and the number gets better. Rubbish reps in, rubbish number out
- Your mode comes back on automatically when tuning finishes

TEMPO

Main system. Default on.

How it works

- Hold the button. Stick drops on its own
- Watch the meter. Tick moves up
- Let go ON the white line. Not before, not after
- Script does the flick. Same speed every rep

You do the line. Script does the flick.

Settings

- ENABLE - on turns the other two modes off
- BUTTON - X or LB. Default X
- FLICK MS - stick travel speed. This is your tempo. Default 40
- HOLD MS - dwell at the top. Nothing to do with tempo or timing. Leave 150
- FADE SPLIT - separate flick speed left vs right. Default off
- FLICK L MS - left fade flick. Default 70
- FLICK R MS - right fade flick. Default 69
- SPOT BTN - OFF / X / LB / LS / RS / B / RB. Default OFF
- SPOT MS - how long that shot holds. Default 700
- REMAP X - OFF / LS / RS. Default OFF
- LATENCY - offset for this mode only. Default 0

Tuning

- Tempo reads fast - raise FLICK MS
- Tempo reads slow - lower FLICK MS
- Timing reads late - let go earlier
- Timing reads early - let go later

Two problems, two fixes, they don't cross.

Don't touch FLICK MS to fix timing. That's your tempo. You'll lose the wide window.

Or just run TUNE TEMPO and let it find FLICK MS for you.

The white line

- Let go ON it
- Stick still travels after you let go, that's FLICK MS
- That travel carries it into the green
- Reading late every rep? Let go a hair sooner. Same amount every time, hands learn it quick

SPOT

Catch and shoot on its own button. Off by default - turn it on if you want it.

Press SPOT BTN and the shot fires straight away on SPOT MS. No timing, no stick.

Your normal tempo button still works as always. The script won't let SPOT land on your shoot button or on a stick you gave to REMAP X.

GREEN

Fully auto. Press the button, script holds it N ms, script lets go.

Read this

GREEN is impossible to make perfectly consistent.

- Fixed number per shot type
- The animation ain't fixed
- Jumpshot, court position, contest, range, fatigue all move it
- Zen sees none of it

Set shots from the same spot it's solid. Everything else it drifts.

MODE - read before you tune

- SIMPLE (default) - two numbers. STAND MS for everything, FADE R MS for fades
- SMART - five numbers, picked off your stick

SIMPLE can't pick wrong because there's nothing to pick. That's why the simple scripts feel consistent.

SMART is better when it guesses right. When it guesses wrong you get a number you never tuned for that shot, and it feels random.

Start SIMPLE. Move to SMART only after STAND and FADE are dialled.

How SMART picks

RT	Left stick	Uses
off	still	STAND MS
off	left	MOVE L MS
off	right	MOVE R MS
on	left	FADE L MS
on	right	FADE R MS

RT has to be properly down and stick properly moving for a fade. Stops accidental fades off a dribble.

Settings

- ENABLE - on turns the other two modes off
- BUTTON - X or LB. Default X
- STAND MS - set shot. Default 700
- MOVE L / R MS - pull ups. Default 680

- FADE L / R MS - RT fades. Default 850
- DEADZONE - how still counts as still. Default 30
- FATIGUE - OFF / LOW / MED / HIGH. Default OFF
- MODE - SIMPLE / SMART. Default SIMPLE
- REMAP X - OFF / LS / RS. Default OFF
- LATENCY - default 0

Notes

- DEADZONE - stick drift? Raise it. Otherwise set shots read as pull ups
- FATIGUE - adds a few ms if you been sprinting, wears off when you stop. LOW is 4ms, MED 9, HIGH 16. Deliberately tiny - the old values moved your timing way too much. Zen can't read your stamina bar, it's going off turbo

Tuning

Run TUNE GREEN. 15 shots and every number is done.

Doing it by hand instead:

- One shot type at a time
- 10 of the same shot, read feedback
- Late = lower. Early = raise.
- Start with STAND MS, easiest to repeat

QS GREEN

Auto green, but it stops you first.

- ENABLE - on turns the other two modes off
- BUTTON - X or LB. Default X
- STAND MS - the shot itself. Default 740
- WAIT - pause after the stop, before the shot starts. Default 260
- REMAP X - OFF / LS / RS. Default OFF
- LATENCY - default 0

Own number. One value, every shot. You just stopped so it's always a standing shot.

Tune it here, or run TUNE QSGRN. Don't touch the GREEN section.

How the stop works

Hit the button and, whatever you were doing, the script:

1. Holds LT and does a fast right stick flick down - that's the stop
2. Kills your left stick and turbo so you can't fight it
3. Waits WAIT ms
4. Holds your shoot button for STAND MS

The flick is fixed and fast. WAIT is yours to tune - it's the gap between the stop finishing and the shot starting.

- Shooting before you've properly stopped? Raise WAIT
- Feels sluggish, too long standing there? Lower WAIT

Default 260. Works from any state - you don't have to be sprinting.

Two knobs, and they don't cross: WAIT is when the shot starts, STAND MS is the shot itself. Tune WAIT first, then run TUNE QSGRN for STAND MS.

REMAP X

In every mode now, and off by default.

Your shooting mode eats X. X is also steal, layup and dunk. So if you shoot on X and you want those back, point REMAP X at a stick:

- OFF - nothing changes. X is only your shoot button
- LS - press left stick, a real X goes through
- RS - press right stick, a real X goes through

One remap covers steal, layup and dunk, because they are all the same button.

Only needed if your BUTTON is X. Shooting on LB? Leave it off, X is already free.

Each mode has its own, so you can set it once for the mode you actually play.

Side detection

Runs by itself. One setting: HAND, in SYS.

Fading from the left corner your stick points up at the corner, not left. Same driving up the floor.

- A firm lean decides it straight away
- A light lean has to clear a bar that scales with how hard you're pushing, so drift doesn't pick a side
- Dead straight up or down, it uses where you been moving the last few seconds

Applies to TEMPO fades, GREEN fades and GREEN pull ups. SMART mode only.

Standing still never touches this. STAND is checked first.

MOVE

- STAMINA - OFF / SAVER / MAX. Default OFF
- DRIBBLE - on / off. Default OFF
- DRIB SPD - dribble speed. Default 100
- MOVE SET - A / B / C. Default A

STAMINA

Turns your stick down so you burn less.

- SAVER - 85%. You barely feel it
- MAX - 70%. More help, you'll feel slower

DRIBBLE

Still early. Works but not finished. Expect to tune it.

Turn it on and the d-pad runs moves. MOVE SET swaps which moves, same three buttons:

D-pad	Set A	Set B	Set C
UP	Curry Cross	Hesi Crossover	Behind-Back Spin
LEFT	Crab Stepback L	Momentum Cross L	Snatch Back L
RIGHT	Crab Stepback R	Momentum Cross R	Snatch Back R
DOWN	nothing	nothing	nothing

Hold to loop. Let go and it stops right there - it don't finish the move first.

DRIB SPD is your one knob.

- Moves not coming out? Raise it
- Moves clipping or chaining bad? Lower it

Straight up: none of these six timings are measured in 2K27. They are a starting point. Tune DRIB SPD and tell me what works.

Heads up: with DRIBBLE on, up / left / right stop reaching the game, so play calling and icon passing on those directions are gone. Down still works normal.

DEF

- CUTOFF - OFF / BOOST / MIRROR. Default OFF

Both modes only while you holding LT + RT. Normal defence untouched.

- BOOST - right stick gets 30% stronger. Small flick reads as a full cutoff
- MIRROR - right stick copies your left stick. One thumb does movement and cutoffs

Try BOOST first. MIRROR is stronger but can reach and foul.

SYS

- HAND - RIGHT / LEFT. Default RIGHT
- LOADOUT - THEATRE / PARK / ANTE UP. Default THEATRE
- RUMBLE - default off
- STATIC - default off
- LED - light bar
- RESET - LT + RT to confirm

HAND

Flips side detection for left handed players. Left fades start picking FADE L instead of FADE R.

LOADOUT

Three saved setups. Switch and it saves what you had, then loads the other one. You never lose a tune.

Each one remembers your MS values for every mode. Buttons and toggles are shared on purpose - those are your setup, not your tuning.

LATENCY - now per mode

There is no global latency any more. Each of the three modes has its own, in its own section.

Laggy TV or wireless and everything reads late? Drop that mode's LATENCY instead of retuning every value.

STATIC

Off is normal, everything animates. On freezes the idle screen. Menu still works normal.

Headset crackling

- That's the Zen, not the script. Headset in the controller pulls too much through it
- RUMBLE off, STATIC on. That's everything the script can do

Quick start

1. Flash it
2. Let it boot once, it resets itself
3. LT + START
4. TEMPO is already on with X
5. Go to TUNE TEMPO, LT + RT on START
6. Take 3 normal jumpers, then 3 left fades, then 3 right fades
7. Press A on each number it shows you
8. Done. It saves and turns TEMPO back on

Want it fully auto instead: GREEN ENABLE on, leave MODE on SIMPLE, then run TUNE GREEN.

Want it to stop you first: use QS GREEN and run TUNE QSGRN.

Shooting on X and missing your steals? Set that mode's REMAP X to LS or RS.

Real

- Trash attributes and no badges? No script is greening that
- Your window comes from your build first
- Court position, contest and range move it too
- Zen sees none of it

This makes your good looks drop more. It don't turn a bad build into a shooter.

SLEM v5.0 / tiktok/slem_2k / discord.gg/hsKWu8y3Ek