Router1 — IOS Command Line Interface

```
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
ip address 192.168.0.1 255.255.255.0
Router(config-if)#ip address 192.168.0.1 255.255.255.0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#ip dhcp pool vashname
Router(dhcp-config)#network 192.168.0.0
% Incomplete command.
Router(dhcp-config)#network 192.168.0.0 255.255.255.0
Router(dhcp-config)#default-router 192.168.0.1
Router(dhcp-config)#dns-server 7.7.7.7
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 192.168.0.1
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
```


FastEthernet0

Port Status: ☑ On
Bandwidth: ○ 100 Mbps ○ 10 Mbps ☑ Auto
Duplex: ○ Half Duplex ○ Full Duplex ☑ Auto
MAC Address: 00D0.584D.3681

IP Configuration
◉ DHCP
○ Static
IPv4 Address: 192.168.0.2
Subnet Mask: 255.255.255.0

IPv6 Configuration
○ Automatic
◉ Static
IPv6 Address:
Link Local Address: FE80::2D0:58FF:FE4D:3681

2811
Router1

2960
Switch0

PC-PT
PC0

PC-PT
PC1

Physical x: 346, y: 78

2811
Router1

2960-24TT
Switch0

PC-PT
PC0

PC-PT
PC1

Router1

Physical | Config | CLI | Attributes

IOS Command Line Interface

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
ip address 192.168.0.1 255.255.255.0
Router(config-if)#ip address 192.168.0.1 255.255.255.0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#ip dhcp pool vashname
Router(dhcp-config)#network 192.168.0.0
% Incomplete command.
Router(dhcp-config)#network 192.168.0.0 255.255.255.0
Router(dhcp-config)#default-router 192.168.0.1
Router(dhcp-config)#dns-server 7.7.7.7
Router(dhcp-config)#exit
Router(config)#
```

Copy   Paste

☐ Top

Realtime