



NAT



```
HO-EDGE#
HO-EDGE#config t
Enter configuration commands, one per line. End with CNTL/Z.
HO-EDGE(config)#
HO-EDGE(config)#interface eth0/0
HO-EDGE(config-if)#ip add 10.0.0.1 255.0.0.0
HO-EDGE(config-if)#no shut
HO-EDGE(config-if)#exit
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#interface eth0/1
HO-EDGE(config-if)#ip add 20.0.0.1 255.0.0.0
HO-EDGE(config-if)#no shut
HO-EDGE(config-if)#exit
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
```

```
HO-EDGE
HO-EDGE(config)#
HO-EDGE(config)#interface eth0/0
HO-EDGE(config-if)#ip nat outside
% Interface is inside enabled.
HO-EDGE(config-if)#interface eth0/1
HO-EDGE(config-if)#ip nat outside
HO-EDGE(config-if)#exit
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#ip dhcp pool LAN
HO-EDGE(dhcp-config)#network 10.0.0.0 255.0.0.0
HO-EDGE(dhcp-config)#default
HO-EDGE(dhcp-config)#default-router 10.0.0.1
HO-EDGE(dhcp-config)#dns
HO-EDGE(dhcp-config)#dns-server 8.8.8.8
HO-EDGE(dhcp-config)#exit
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#access-list 10 permit 10.0.0.0 0.255.255.255
```

```
HO-EDGE
HO-EDGE(config-if)#exit
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#ip dhcp pool LAN
HO-EDGE(dhcp-config)#network 10.0.0.0 255.0.0.0
HO-EDGE(dhcp-config)#default
HO-EDGE(dhcp-config)#default-router 10.0.0.1
HO-EDGE(dhcp-config)#dns
HO-EDGE(dhcp-config)#dns-server 8.8.8.8
HO-EDGE(dhcp-config)#exit
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#access-list 10 permit 10.0.0.0 0.255.255.255
HO-EDGE(config)#ip nat inside source list 10 interface e0/1 overload
HO-EDGE(config)#exit
HO-EDGE#
*Oct 9 14:40:45.823: %SYS-5-CONFIG_I: Configured from console by console
HO-EDGE#
```




```
DC-EDGE
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#interface eth0/0
DC-EDGE(config-if)#ip nat inside
DC-EDGE(config-if)#
*Oct  9 15:10:33.703: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to up
DC-EDGE(config-if)#exit
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#interface eth0/1
DC-EDGE(config-if)#ip nat outside
DC-EDGE(config-if)#exit
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#
```

```
DC-EDGE
DC-EDGE(config)#
DC-EDGE(config)#ip dhcp pool DC
DC-EDGE(dhcp-config)#network 192.168.1.0 255.255.255.0
DC-EDGE(dhcp-config)#def
DC-EDGE(dhcp-config)#default-router 192.168.1.1
DC-EDGE(dhcp-config)#dns
DC-EDGE(dhcp-config)#dns-server 8.8.8.8
DC-EDGE(dhcp-config)#
DC-EDGE(dhcp-config)#exit
DC-EDGE(config)#
DC-EDGE(config)#exit
DC-EDGE#
DC-EDGE#
*Oct  9 15:25:45.021: %SYS-5-CONFIG I: Configured from console by console
DC-EDGE#ip nat inside source static 192.168.1.2 30.0.0.10
^
% Invalid input detected at '^' marker.
DC-EDGE#ip nat inside source static 192.168.1.3 30.0.0.10
^
% Invalid input detected at '^' marker.
DC-EDGE#config t
```

```
DC-EDGE#
DC-EDGE#
*Oct  9 15:25:45.021: %SYS-5-CONFIG_I: Configured from console by console
DC-EDGE#ip nat inside source static 192.168.1.2 30.0.0.10
^
% Invalid input detected at '^' marker.

DC-EDGE#ip nat inside source static 192.168.1.3 30.0.0.10
^
% Invalid input detected at '^' marker.

DC-EDGE#config t
Enter configuration commands, one per line.  End with CNTL/Z.
DC-EDGE(config)#ip nat inside source static 192.168.1.2 30.0.0.10
DC-EDGE(config)#ip nat inside source static 192.168.1.3 30.0.0.11
DC-EDGE(config)#exit
DC-EDGE#
DC-EDGE#
*Oct  9 15:41:19.743: %SYS-5-CONFIG_I: Configured from console by console
DC-EDGE#
DC-EDGE#
DC-EDGE#
DC-EDGE#
```

