


Subnetting



```
R1
R1(config)#
R1(config)#ip dhcp pool hr
R1(dhcp-config)#network 50.0.1.128 255.255.255.192
R1(dhcp-config)#def
R1(dhcp-config)#default-router 50.0.1.129
R1(dhcp-config)#exit
R1(config)#
R1(config)#
R1(config)#
R1(config)#ip dhcp pool production
R1(dhcp-config)#network 50.0.1.0 255.255.255.128
R1(dhcp-config)#def
R1(dhcp-config)#default-router 50.0.1.1
R1(dhcp-config)#exit
R1(config)#
R1(config)#
R1(config)#
R1(config)#ip dhcp pool sales
R1(dhcp-config)#network 50.0.0.0 255.255.255.0
R1(dhcp-config)#def
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#exit
R1(config)#
R1(config)#
```

```
R2
R2(config)#interface eth0/0
R2(config-if)#ip add 50.0.1.1 255.255.255.128
R2(config-if)#no shut
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#interface eth0/1
R2(config-if)#ip add 50.0.1.194 255.255.255.252
R2(config-if)#no shut
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#
R2(config)#interface eth0/2
R2(config-if)#ip add 50.0.1.197 255.255.255.252
R2(config-if)#no shut
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#
R2(config)#
```

```
R2
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#ip route 50.0.1.128 255.255.255.192 50.0.1.193
R2(config)#ip route 50.0.0.0 255.255.255.0 50.0.1.198
R2(config)#
R2(config)#interface eth0/0
R2(config-if)#ip hel
R2(config-if)#ip helper
R2(config-if)#ip helper-address 50.0.1.193
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
```

```
R3
Ethernet0/3          unassigned      YES TFTP    down      down



R3#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#interface eth0/0
*Sep 29 15:09:35.701: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R3(config)#interface eth0/0



R3(config-if)#ip add 50.0.0.1 255.255.255.0
R3(config-if)#no shut
R3(config-if)#exit
R3(config)#
R3(config)#
R3(config)#interface eth0/1
R3(config-if)#ip add 50.0.1.198 255.255.255.252
R3(config-if)#no shut
R3(config-if)#exit
R3(config)#
R3(config)#
R3(config)#exit
R3#
*Sep 29 15:22:59.749: %SYS-5-CONFIG_I: Configured from console by console
R3#ping 50.0.1.129
```


```
R3
R3(config)#exit
R3#
*Sep 29 15:22:59.749: %SYS-5-CONFIG_I: Configured from console by console
R3#ping 50.0.1.129
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 50.0.1.129, timeout is 2 seconds:
.....
Success rate is 0 percent (0/5)
R3#


R3#
R3#
R3#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#ip route 0.0.0.0 0.0.0.0 50.0.1.197
R3(config)#

R3(config)#
R3(config)#
R3(config)#interface eth0/0
R3(config-if)#ip helper
R3(config-if)#ip helper-address 50.0.1.193
R3(config-if)#exit
R3(config)#
```









A screenshot of a terminal window titled "VPC-3". The window has a standard macOS-style title bar with a red close button, a yellow maximize button, and a green window control button. The terminal content is as follows:

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-3> dhcp
DDORA IP 50.0.0.3/24 GW 50.0.0.1

VPC-3> 
```

The prompt "VPC-3>" is followed by a green cursor block.