UNIT 110 update history

Current version 1.0.6. Newest first.

Version 1.0.6

- Twice-as-sharp artwork: the front panel and the circuit board are now stored at double resolution, crisp on Retina / HiDPI screens and at the largest window size.

Version 1.0.5

- New clean, factory-new look: a pristine front panel, new knobs and a clean circuit board inside the case.
- All lettering, key legends and icons drawn sharp on the new panel; the board print redone (ACC, BD, SD, OH, CH, CY, CP).
- Front panel and case line up exactly, with perfectly level edges.

Version 1.0.4

- New bass drum, snare and hand clap sound engines, rebuilt from the Transistor Labs DR-110 device: the kick is a 55 Hz resonant filter struck with an octave pitch drop, the snare a 235 Hz tone with 3550 Hz noise, the clap three short noise bursts, a longer one and a room tail at 1140 Hz.
- Their trimmers: TUNE, DECAY and LEVEL as before; ATTACK = the kick's pitch drop, SNAPPY = noise against tone, TAIL = the clap's room. At the default settings each drum is the original sound.
- The front panel and the open case are now perfectly straight (the bottom edge used to drop to the right).

Version 1.0.3

- Sharp panel: all lettering, numbers, key legends and icons are now drawn as vector graphics, crisp at any window size.
- Spelling: BASS DRUM, DC.
- The TEMPO knob is now SWING (STRAIGHT to SHUFFLE, 50-75 %). MIDI export swings too.
- UNIT 110 always follows the DAW tempo; START / STOP with the DAW stopped also use it. In the standalone app the tempo is set by dragging the TEMPO box on the LCD.
- Mute with SHIFT + drum key, solo with Option (Alt) + drum key; the LCD shows M / S.
- The drum keys' right-click menu now holds only Own output. Right-click menus are larger.
- Checked: runs on macOS 10.13 and later (11 on Apple silicon), including macOS 12.

Version 1.0.2

- New parameter-lock screen: double-click SHIFT and the LCD shows one drum's locks for one setting (tune, decay, level or the drum's extra) as a bar per step. Drag to set, double-click to clear. Double-click SHIFT again to go back.
- Copy pattern / Paste pattern in the LCD's right-click menu (steps and locks).
- New front panel and circuit board artwork, now exactly the same size: opening the case looks like lifting the lid.
- The ON-OFF POWER lettering also opens the case; inside, the three big black chips close it, as well as the screws.
- Bigger case screws on the front panel.

Version 1.0.1

- Fixed: the plug-in and app did not open on macOS 12 (and other versions older than the build machine). They now run on macOS 10.13 and later.

Version 1.0.0

- First release of UNIT 110 by Transistor Labs.
- Hyperrealistic front panel: photographed keys that sink when pressed, turning knobs, a working POWER switch and a live LCD.
- The LCD shows all 7 rows (accent + 6 drums) on a 16-step grid, the playing step, the mode, the pattern and the tempo. Click steps to edit them; right-click for MIDI export, copy and clear.
- Panel modes like the original: SHIFT + 1..5 = PLAY SONG, PLAY PATTERN, WRITE SONG, WRITE STEP, WRITE TAP; SHIFT + 6 = 12/16 steps, SHIFT + 7 = clear pattern, SHIFT + 8 = clear song.
- 32 patterns in 4 banks (A-D) of 8, chosen with the A|B|C|D key and the number keys.
- START / STOP run the sequencer on the TEMPO knob while the host is stopped.
- New BALANCE knob: drums (bass drum, snare, clap) against metal (hats, cymbal).
- Open the case with a screw in a bottom corner: the circuit board has trimmers for Tune, Decay and Level of every drum, Attack, Snappy, Tone and Tail, and the accent's Drive, Decay and Level.
- Sound engine from TRoss 110 0.3.3.