



Customer Service

Generated on: 2026-09-29 09:39:52 GMT+0000

SAP S/4HANA | 2025 FPS01 (Feb 2026)

Public

Original content: https://help.sap.com/docs/SAP_S4HANA_ON-PREMISE/f4a255a5de524e3992155767996fb1fd?locale=en-US&state=PRODUCTION&version=2025.001

Warning

This document has been generated from SAP Help Portal and is an incomplete version of the official SAP product documentation. The information included in custom documentation may not reflect the arrangement of topics in SAP Help Portal, and may be missing important aspects and/or correlations to other topics. For this reason, it is not for production use.

For more information, please visit <https://help.sap.com/docs/disclaimer>.

Move-In/Out

Purpose

This component enables you to process a customer move-in or move-out. In the case of a move-in, you can create a business partner and contract account for the customer, or select existing ones. The contracts are then created and allocated to a utility installation.

In a move-out, you terminate the customer's contract. If a new customer moves into the installation, the installation is allocated to this customer's contract.

For more information, see [Move-In](#) and [Move-Out](#).

Integration

Letters to the customer, such as welcome letters and move-out confirmations are created using the [Print Workbench](#) component. The [SAP Business Workflow](#) component (BC-BMT-WFM) enables you to monitor and configure the workflow processes.

Features

You can have the system trigger a number of activities automatically. You can:

- process the entire transaction immediately and in full.
- create a final bill for the move-out customer.
- create a welcome letter for the move-in customer.

You can also configure the screen layout to suit your requirements.

Move-In/Out Processing

Use

You can use [Move-In/Out Processing](#) to process the following:

- Move-in/out (move-out with subsequent move-in) for a premise
- Move-in/out for a business partner
- Move-in
- Move-out
- Contract change

From the [Move-In/Out](#) initial screen, you can enter search parameters that act as transfer parameters for calling the move-in/out. Use the search parameters to select the master data keys, such as the business partner, contract account or premise. These

For more information, see [Move-In](#) or [Move-Out](#).

Prerequisites

The same prerequisites that apply to the [Move-In](#) and [Move-Out](#) functions also apply here.

Features

There are two ways to process a move-in/out:

- **Create move-in/out for premises**

You use this function to change the business partner of the premise and/or the installations belonging to the premise. To select an installation, specify a premise or a business partner. You can then create a move-out to occur on the specified move-out date and then create the subsequent move-in. This applies to all the installations you selected.

You can select an existing business partner to move-in to the premise/corresponding installations by using the move-in search parameters.

- **Create move-in/out for business partner**

You use this function to perform a move-in/out for a business partner within the supply area. You can create the move-out so that the business partner moves out of several installations, and the move-in so that the business partner moves into several installations. You can select the business partner using the move-out search parameters.

You can use the move-in search parameters to determine the installations into which the business partner is to move in.

If the installations of the new premise are not vacant, a dialog window appears where you must specify whether you also want to create a move-out for the business partner allocated to these installations.

Subsequent processing of move-ins and move-outs

Processing a move-in or move-out, once it has been created, is facilitated by integrated functions that you can use to reverse billing, invoicing and FI-CA documents. If the (new) move-out date or move-in date is in a period that has already been billed, you have the following options:

- Create a move-out
- Change the move-out date
- Reverse a move-out
- Reverse a move-in

The system reacts by reversing the billing document. If the document has already been invoiced, the system reverses invoicing before it reverses the billing document. Any other FI-CA documents that were generated by invoicing are also reversed. If the documents have already been cleared by payments, the system reverses the payment clearing first.

Any documents assigned to one of the move-in contracts are reversed first. The clearing is reversed upon payment. This is also the case if the contract has not yet been billed.

You call this function using the processing variants for move-in/out processing. To be able to use the move-in/out function, you

The BOR object types MOVEINDOC and MOVEOUTDOC have the following methods that you can use to create your own workflows:

- GETDOCSBILLINGFICA (determine the documents to reverse)
- REVERSEDOCSBILLINGFICA (reverse the documents)
- REVERSELOGDISPLAY (display the reversal log)

Activities

Search parameters

Use the search parameters for move-in or move-out to create or process a move-in or move-out separately.

If you want to create a move-in/out for a business partner, you can use the move-out search parameters to select the installations and determine the business partner. You do not have to determine the business partner on the move-in page.

If you want to create a move-in/out for a premise, you can use the move-out search parameters to search for the installations for both the move-in and move-out. You do not have to determine the premise on the move-in page.

Insert Contract

Use

You use this function to allocate contracts in order to cover the vacant status periods of one or more installations.

This functions affects installations that are vacant over a given period. No contract is allocated to the installation over the vacant status period; however, the installation has a contract that begins at the end of the vacant status period. The function entails a move-in and move-out. Note that the move-in of the second contract (to be allocated at the end of the vacant status period) does not have to be reversed.

If the second contract has already been invoiced then these bills are automatically reversed for adjustment. If the installation is billed again, the system creates a redundant bill for the contract. This bill is automatically suppressed. This ensures that the customer moving in to the installation only receives one bill.

The [Insert Move-In/Out](#) action has been enhanced to include the [Remove Contract](#) function. If the contract to be removed, or a subsequent contract has already been invoiced then you must perform a full reversal, or bill the affected period. The [Remove Contract](#) function contains the full reversal functionality; however restrictions apply.

Integration

The [Insert Contract](#) function is integrated in the move-in/out transaction (EC60).

Prerequisites

The adjustment reversal functionality contained in this function requires all documents to be invoiced. Documents that have been billed but not invoiced cannot be adjusted for reversal. You cannot debug this function since debugging causes data

Use

Move-in and move-out processing have the following enhancements:

- ECSBTI01 (IS-U move-in: determine application form)

This enhancement enables you to specify a default value for the application form used for the welcome letter.

- ECSBTI02 (IS-U move-in: determine budget billing amount)

This enhancement enables you to specify a default value for the budget billing amount.

- ECSBTI04 (IS-U move-in: determine transfer contract)

This enhancement enables you to specify a default value for the transfer contract.

- EMDK0001 (IS-U utility contract: include subscreens and check fields)

This enhancement enables you to enter default values in contract fields. When you create a move-in, information about the installations that have to be allocated to the contract is transferred. The enhancement is run during every PBO (process before output) on the move-in screen.

- EC500001 (IS-U move-in: determine security deposit amount and reason)

This enhancement enables you to specify a default value for the amount of, and reason for a cash security deposit. It is run during every PBO (process before output) on the move-in screen.

- ECSBT001 (IS-U: move-out - determine default values for Customizing of table TE490A)

This enhancement is used, for example, to assign default data to the application form for the move-out confirmation.

- ECSBTI03 (IS-U move-in: user-defined checks)

This enhancement is used for checking field values on the move-in screen.

- ECSBT002 (IS-U move-out: user-defined checks)

This enhancement is used for checking field values on the move-out screen.

- ECSBTMR1 (Indicator used to allocate default values to the [Create service notification/order](#) functions)

For more information, see [Service Notifications and Orders](#) .

- ECSBT001 (IS-U: move-in/move-out – customer-specific messages in the information log (environment log))

This enhancement is used to add user-defined messages in the environment log.

Enhancements for the Screen Layout

You can include standard and user-defined fields for the contract account and business partner in direct maintenance. To do this, use the following enhancements:

- EMDK0001 (IS-U utility contract: include subscreens and check fields)

i Note

You can find these enhancements in Customizing under ► [SAP Utilities](#) ► [Tools](#) ► [System Modifications](#) ► [SAP Enhancements](#) ► [Define SAP Enhancements](#) ►.

Business Add-Ins (BADIs)

- ISU_MOVEIN_CUSTOMIZE: (IS-U: Customizing – override move-in processing)

Used to override Customizing settings in the move-in.

For more information see the BadI documentation.

- ISU_MOVEIN_MENUUE (IS-U: menu enhancement for move-in)

Used to enhance the menu of the move-in screen. Enables you to add entries to the menu bar.

For more information see the BadI documentation.

- ISU_MOVEOUT_MENUUE (IS-U: menu enhancement for move-out)

Used to enhance the menu of the move-out screen. Enables you to add entries to the menu bar.

For more information see the BadI documentation.

Contract Change without Invoicing

Use

The function for changing a contract without invoicing enables you to change the payment form of some of the contracts in a contract account without triggering separate invoicing.

Integration

You can use the contract change without invoicing from the [move-in/out](#) function. You can also reverse a contract change without invoicing.

Prerequisites

You can use the contract change without invoicing function in a move-in/out when the contracts have already been included in an invoiced billing document.

Prerequisite: You have configured the contract change reasons in Customizing under [Define Reasons for Contract Change](#) so that the new field [nl \(contract change without invoicing\)](#) is selected. The settings for reposting receivables during the customer change also have to be maintained here in the field [UBU \(Repost Open Items for Move-In/Out\)](#).

When a contract change without invoicing is performed, the contracts are ended with a move-out, and new contracts created with a move-in.

When the move-out is created, the latest billing document for the transfer contract is adjusted for reversal whenever possible, and a new billing document is created with a contract change. This billing document usually has bill amount zero and is never invoiced. No new meter readings are recorded either. Instead, the last billed meter readings when the move-in was created are copied.

When the move-in is created, the open items in the transfer contract are reposted to the target contract determined by the move-in (depending on the Customizing settings). This is only possible within the same company code. Items that have already been paid are not reposted. Security deposits can be transferred.

Customer Change

Use

You use the customer change function to transfer the utilities contracts for a contract account, including any resulting receivables, between business partners.

This can for example be necessary when [merging business partners](#).

The following functions are possible:

- Create customer change
- Process customer change subsequently
- Reverse customer change
- Transfer post open items due to customer change

Integration

You can access the customer change function under ► **SAP Utilities** ► **Customer Service** ► **Process Execution** ► **Move-In/Out** ► and then the menu option ► **Other** ► **Create / Cancel Customer Change** ►.

Prerequisites

Before you can execute customer change, the contracts to be transferred must have been invoiced at least once.

If you also want to transfer budget billing plans, the budget billing plan items must all be open. If necessary, you must reset all clearings and set the accrued receivables to payments on account. Therefore, we recommend that you execute the customer change as close as possible to the last bill in order to avoid this preparatory work.

Customizing

You define customer change reasons in Customizing for **SAP Utilities** under ► **Customer Service** ► **Process Execution** ► **Move-In/Out** ► **Define Reasons for Customer Change** ►.

You can also choose whether or not the following objects are also transferred during the customer change:

- Open items
- Dunning information

i Note

See also the Customizing documentation for the individual components and the F1 field help.

Features

When a customer change is created, the system terminates the transfer contract using a move-out, and creates a new contract using a move-in. The move-out date is set as the end of the billing period of the most recently invoiced billing document belonging to the transfer contract

You can also append an actual move-out date to the move-out, and an actual move-in date to the move-in. This enables you to document when the move-out customer actually vacated the apartment, and when the move-in customer occupied it. If this data becomes valid at a future date, the changes to the business partner and contract account data of the move-out customer are stored as scheduled changes, with the actual move-out date as the validity date. The changes to the business partner and contract account data are stored as scheduled changes for the move-in customer with the actual move-out date as the validity date.

When you create a move-out, an adjustment reversal of the most recent billing document takes place for the transfer contract and a new billing document is created with the value **08** (Customer Change). This billing document contains the billing amount "0. The most recent billed meter readings are also copied when the move-in is created. Note that constellations in the rate structure (such as period-end billing for monthly customers, basic monthly price and so on) can result in the billing documents from the adjustment reversal not having the amount "0.

Depending on the Customizing settings, no new meter reading results are entered. Instead, the last billed meter readings are copied when the move-in is created (see SAP Note 503243).

When you save the move-in document, the open items in the transfer contract can be posted to the target contract created as a result of the move-in (this depends on the Customizing settings described above). This is only possible within the same company code. Items that have already been paid are not reposted. You use the [Transfer Items](#) transaction (FP40) to do this.

Depending on the Customizing setting you made previously, security deposits and dunning information can be transferred.

Interest history and supplements are not copied during transfer of the open costs.

Budget billing plans are treated as follows: They are deactivated by the move-out, once you have set the payment on account. Depending on the Customizing settings, a new budget billing plan is created from the deactivated budget billing plan when you save the move-in document. You then allocate the credit payments using the account maintenance.

The customer change assigns a posting block to the transfer contracts. You can display this block in the move-out document. You can change the block using methods [ReleaseFicaLock](#) and [SetFicaLock](#) of BOR object MOVEOUTDOC.

Constraints

- Open items that have been sent to a collection agency cannot be transferred.
- The returns history is not transferred to the new target business partner.
- The interest history and supplements are not copied when you transfer the open items.

If a contract has not yet been invoiced, proceed as follows:

- Reverse the move-in document: Execute move-in with the correct business partner. You can use the move-in document as a template.
- Create an intermediate bill.
- Wait for the next bill and then execute the customer change.

Move-in

Use

You use the move-in function to carry out most of the activities required to begin providing a business partner with a utility service. You create new, or change existing business master data. Most importantly, you allocate a contract to an installation.

In move-in processing, you establish whether a contract can be billed. From the move-in, you can also trigger the charges levied at the commencement of a utility service, as well as a welcome letter to the customer.

Prerequisites

To create a move-in, you require one or more installations that are vacant on the desired move-in date.

- In the case of an initial move-in, ensure that you have completed initial data creation, including creation of the installation(s).
- Devices can (but do not have to) be [installed](#) and allocated before move-in.
- If one of the installations is already allocated to a contract, this allocation must be reversed. To do this, process a move-out. An installation can only be allocated to one contract at any given time.

Features

Customer Contact

When a move-in is created, a corresponding customer contact is created automatically. This is automatically linked to the move-in document. You can find additional information in the section on [Customer contact](#).

Overall Check

When a contract is assigned the move-in status 05 (meter reading entered completely), you can verify that the contract can be billed.

Move-In Status

If you process or display a move-in document, the system also displays the move-in status of each contract. The move-in status informs the agent which stage of move-in processing has been reached.

The minimum is formed from the move-in status of the contracts and also displayed. In this way you can obtain information on the status of the entire move-in processing.

When you display the move-in documents for a business partner or a premise, the documents from the last three months appear. If no documents exist for this period then the system displays the documents from the last six months.

Once you have entered the move-in, move-out, or move-in/out, you can use the SAP Business Workflows to trigger and monitor additional business processes.

You can re-process incomplete move-ins and monitor the status of processing. This may be necessary if, for example:

- The meter readings are unavailable
- The budget billing plan cannot be created, or
- The data required to print the welcome letter is incomplete

Move-In Charges

When you save the move-in document, the system posts the move-in charges automatically, provided you have configured the system accordingly in Customizing under [►Move-In/Out► Define System Parameters for Move-In and Move-Out. ►](#).

You can configure the system to post the charges to a contract or contract account. You configure how the system calculates the charges using the parameters [Charge category](#) and [Charge schema](#) . In this way, you can, for example, levy a move-in charge staggered to correspond with the number of contracts.

Reduced Layouts

In Customizing, you can define reduced layouts for the configurable tab on page on the move-in screen to hide some of the data on the individual tab pages. The layouts can now be stored in the special processing variants for the move-in/out. This enables agents to process move-ins and move-in/outs more quickly.

Budget Billing

A budget billing amount agreed with the customer is also taken in account if the move-in is entered by the master data generator. If a budget billing plan cannot be created for a contact in move-in processing then the BudgetBillingPlansFailed event of the MOVEINDOC BOR object type is triggered.

Activity Log

In Customizing you can configure the system to save the activity log for the move-in. You can then display it on the move-in screen. To do this choose [►Extras► Display Activity Log. ►](#)

Activities

Initial Screen

Based on the data you specified on the initial screen, the system automatically determines which of the following cases applies:

Exists before move-in	Is created during move-in
Business partner, contract account, installation	Contract
Business partner, installation	Contract account, contract

You can change the date of a move-in after it has been created without affecting the move-out that precedes it. To do this, choose [►Edit ► Change Move-In Date ►](#).

Actual Move-In Date

In addition to the move-in date, the actual move-in date can be entered as the date from which the premise is occupied.

Save

When you save the move-in, the initial move-in or move-in/out screen reappears. In Customizing under [Define Control Parameters at Document Level](#), you can configure the system so that when you save the data, a log is displayed containing information on the changes made to the data.

Certain move-in activities, for example, maintaining a budget billing plan, are based on the database changes made by the move-in. In these instances, you can, in Customizing under [Move-In/Out -> Move-In -> Define Control Parameters at Document Level](#) configure the system to either output a confirmation prompt or save the data automatically before the action is carried out.

You can also save your changes in the move-in without leaving the move-in screen. To do this, choose [Save and Hold](#).

Master Data (Move-In)

Use

During move-in processing, one or more contracts are created to commence on the specified move-in date. The installations you specified at the start of processing are allocated to these contracts.

If the move-in date is in a period in which one of the installations has already been billed then the move-in cannot be created.

You can save changes to business partner and contract account data as **scheduled** changes. This means that the changes are not activated until a future date. This date is determined by subtracting the interval period defined in Customizing from the move-in date. For more information on how to define the interval period, see Customizing under [►SAP Utilities ► Customer Service ► Process Execution ► Move-In/Move-Out ► Define System Parameters for Move-in and Move-Out ►](#). Scheduled changes are activated by report BUSPCDACT (activation of scheduled change documents for an application object).

When a move-in is created, the tax jurisdiction code of the connection object address is copied to all the contracts of the move-in document, as well as to all the business partner addresses that were automatically created through the move-in.

Standard Business Partner Address

In Customizing ([►SAP Utilities ► Customer Service ► Process Execution ► Move-In/Out ► Move-In ► Define Move-In Control Parameters at Document Level ►](#)), you can configure the system so that the business partner receives the address of the premise he/she is moving into as the default address. If you want to process the move-in for different premises in one move-in document, the system uses the premise address of the installation that was entered first.

You can find additional information in the section on the [master data](#) component.

Using the Business Add-In (Badi) ISU_MOVEIN_SETBPADDR, you can allocate a default value to the standard address.

Meter Reading Data (Move-In)

When you create a move-in, the system proposes an existing meter reading result for all the billing-relevant registers allocated to the devices for billing purposes. Ensure you have configured the system accordingly in Customizing under [SAP Utilities > Device Management > Meter Reading > Basic Settings > Define Control Parameters for Meter Reading Data Processing](#).

- If the system proposes a meter reading result then choose one of the following two options:
- If you adopt the meter reading result, the system adds the meter reading reason **Move-in** to the result.
- If you change the meter reading result, a new result is created with the meter reading reason **Move-in**.
- If the system does not propose a meter reading result, you can have it estimate a result or enter one manually. In both cases, the system creates a new meter reading result from the adopted/changed result and gives it the meter reading reason **Move-In**.
- If the system does not propose a meter reading result, and you do not enter one manually, a service notification or service order is created for the current register. For more information see [service notifications and orders](#).

You can also suppress the meter reading proposal or define an interval as required. If you do this, the system only makes a proposal if the meter reading result on which the proposal is based was taken during the interval. Ensure you have configured the system accordingly in Customizing under [SAP Utilities > Device Management > Meter Reading > Basic Settings > Define Control Parameters for Meter Reading Data Processing](#). Ensure that you make an appropriate entry in the **Move-in prop. inter.** (Interval for determining default value) and the **Display default move-in value** checkbox alongside it.

You can find additional information on meter reading data processing in the section on the [meter reading](#) component.

Budget Billing Plan

Use

You can create a budget billing plan for every contract involved in a move-in, provided the **BB procedure** (budget billing plan active) field in the contract account contains the value 1 (Statistical procedure for budget billing collection) or 2 (Debit entry procedure for budget billing collection). You have the following options:

- Create budget billing plan manually

To do this, choose the **Budget billing plan** pushbutton in move-in processing.

- Create budget billing plan when data is saved

To have the system create a budget billing plan automatically when you save the move-in document, make the appropriate entry in the **Create budget billing plan** field in Customizing under [Move-In/Out > Move-In > Define Move-In Control Parameters on Contract Level](#).

If necessary, you can also override the settings you have established in Customizing. To do this, choose [Extras > Control Parameters](#) in move-in processing.

You can choose whether to assign a budget billing amount that is valid for all due dates, or whether to have each amount calculated by the system.

The budget billing due dates are result from the Scheduling component. The printout date of the first budget billing due date

For more information see the section on the [Budget Billing Plan](#) component.

Security Deposits

Use

You can request a security deposit in move-in processing, or, provided certain conditions have been met, adopt the security deposit of an existing contract.

Re-Request Security Deposit

Customizing Settings

In Customizing under **► Move-In/Out ► Move-In ► Define Move-In Control Parameters on Contract Level ►** you can configure the system so that security deposits are requested through move-in processing. You can request a cash security deposit, or arrange a non-cash security deposit with the customer.

- A cash security deposit is created for each contract. In doing this, this system posts a request document for a cash security deposit in FI-CA.
- A non-cash security deposit is created for all the contracts involved in the move-in, for which a non-cash deposit is to be created.

Entry Options on the Move-In Screen

On the move-in screen, on the tabstrip **Contract Data**, enter a reason for requesting the security deposit and the amount requested. Now, when you save the move-in document, the system automatically creates a security deposit. If you specified a reason for exempting the customer from a security deposit then one is not created. You can allocate a default value to the security deposit reason and amount using enhancement EC500001 (determine security deposit reason and amount).

For more information see the section on [Contract Accounts Receivable and Payable](#) (FI-CA) including [Security Deposits](#).

Adopt Existing Security Deposits (Transfer)

In Customizing under **Define Move-In Control Parameters on Contract Level**, you can, using the **Security deposits** field, configure the system to transfer the security deposits of existing contracts to newly created contracts. This is done by means of Transfer Contracts. You can use this procedure if, for example, a business partner moves to a new premise in the supply territory, terminates his/her existing contracts for this reason and wishes the security deposits paid on these contracts to be adopted for the new contracts. You can transfer deposits in this way if the following transfer conditions have been met:

- You have entered a move-in/out in the system.
- You have selected the contracts so that both the move-in and move-out documents both contain one contract for each division, and each have the same number of contracts.
- In Customizing, under **Define Move-In Control Parameters on Contract Level**, you have defined whether the security deposits of a contract can be automatically transferred.
- Both the transfer contract and the new contract have been allocated to the same company code.

Welcome Letter

Use

When you create or change a move-in, you can print a correspondence to be sent to the business partner, or generate a print order for the correspondence. You have the following options:

- Create welcome letter manually

To do this, choose the **Welcome letter** pushbutton in move-in processing.

- Create welcome letter when data is saved

To have the system create a budget billing plan automatically when you save the move-in document, mark the **WL** checkbox (Create welcome letter automatically) in Customizing under ►►**Move-In/Out** ► **Move-In** ► **Define Move-In Control Parameters at Document Level.** ►

If necessary, you can also override the settings you have established in Customizing. To do this, choose ►►**Extras** ► **Control Parameters** ► in move-in processing.

When you create a welcome letter, specify an application form of the form class IS_U_CS_MOVE_IN_WELCOME_LETTER. In addition, you have to define the application form in Customizing under ►►**Utilities Industry** ► **Customer Service** ► **Process Execution** ► **Move-In/Out** ► **Move-In** ► **Define Welcome Letter** ►. You can find more information on creating an application form in the section on the ►[Print Workbench](#) component.

Screen Layout

Use

In Customizing under ►►**Move-In** ► **Configure Tabs for Move-In Screen** ►, you can configure various views for the data on the move-in screen. These views are composed of tabs that you can use to organize the data into different logical units based on your requirements.

You can maintain contract data in one of two ways:

- Individual maintenance

The system displays the data of one contract only.

- Overview maintenance

The system displays the data of up to five move-in documents allocated to the same contract.

For more information, see Customizing under ►►**Move-In/Out** ► **Define System Parameters for Move-In and Move-Out** ►.

You can include standard and user-defined fields for the contract account and business partner in direct maintenance. To do this, use the following enhancements:

- EMBP003 (user subscreen in the business partner subscreen for move-in/out))
- EMDCA001 (user subscreen for IS-U contract account)

Features

This function enables you to adjust the screen layout to best suit your requirements. The fields visible on the screen have been grouped into units that you can distribute among the individual tabs.

Activities

You have the following options:

- If you want to use the standard SAP layout, do not make any changes.
- If you want to define your own layout then establish the following settings:
 - a. In Customizing, choose [► Move-In/Out ► Move-In ► Configure Tabs for Move-In Screen ►](#). Here you can define your own layout.
 - b. Enter the layout in Customizing as a default layout in Customizing under [► SAP Utilities ► Basic Settings/Enterprise Structure ► Define Default Layout for Tabs ►](#)

Service Notifications and Orders

Use

In Customizing under [► Device Management ► Meter Reading ► Basic Settings ► Define Control Parameters fir Meter Reading Data Processing, ►](#) you can configure the system to create a service order or service notification for the move-in meter reading (provided that plausible meter readings do not already exist for the metering devices). You can establish this settings separately for each division. Customizing entries with an empty company code key are relevant to this process, since the system does not yet know the company code in move-in initial processing. You can use enhancement ECSBTMR1 (Assign default values for creation of service notifications/orders).

You can also do this in Customizing under [► Device Management ► Meter Reading ► Basic Settings ► Define Control Group for Creation of Multiple MR Orders ►](#)., you define whether the system creates service notifications or service orders, and whether these or stored at device, device location or connection object level.

Alternatively, you can integrate the creation of service notifications and orders into a workflow, in which case creation is not immediate but postponed. You do this in Customizing under [Define System Parameters for Move-In and Move-Out](#) . Prerequisites for this are the method MoveInDocument.MeterReadingServiceInitiate (Trigger service management for meter reading) and the parameter DelayedMeterReadServ V in event MoveInDocument.Created for object type MOVEINDOC (move-in document).

If you reverse a move-in, the system adjusts the status of the service notifications/orders generated during move-in creation as follows:

- The status **Completed** is allocated to the service notifications.
- The status **Not executed** is allocated to service orders that were not released.
- The status **Technically completed** is allocated to service orders that were released.

If you change a move-in date, the system proceeds as though the move-in had been reversed and re-created for another date.

you still want to create a service order/notification, then you must reset the register results using the [Reset](#) function key. Otherwise, the system saves the register results and a service notification/order is no longer required.

Move-In Reversal

Use

You use this function to reverse the allocation of a contract to an installation performed during a move-in. You require this function in the following cases:

- The move-in was mistakenly created with an incorrect business partner.
- The move-in was mistakenly created with the installations of an incorrect premise.
- The business partner subsequently announces that he/she is not taking over part of the installations of a premise. In this case, you reverse part of the move-in and recreate it using the relevant part of the installations.

Integration

A move-out and subsequent move-in for the installations of a premise often have to be reversed in one function call. In this case, the move-in must be reversed first and subsequently the move-out can be reversed.

Prerequisites

The period starting with the move-in date is not permitted to have already been billed for any of the installations. If the contract for which you intend to reverse the allocation to an installation has any accounts receivable and payable documents then you must reverse them before you can proceed. For more information, see [Move-In/Out Processing](#) .

Exceptions include statistical budget billing requests, or requests for cash security deposits created during the move-in, as well as move-in charges. These are dealt with automatically during move-in reversal.

Features

In move-in reversal, contracts whose allocation to an installation is to be canceled are indicated with a deletion. The flag shows that they cannot be included in joint invoicing with other contracts.

Meter reading orders and meter reading results that were created during move-in are automatically deleted. This is the same as for budget billing plans not posted as debit and for which no payments were made. Security deposit requests created during move-in are automatically reversed, provided they have not yet been paid. The system also determines the move-in charge documents that belong to the move-in document and reverses them automatically.

Changes levied on the business partner, contract account, and contract data during move-in are **not** automatically reversed in the move-in reversal. However, the system resets the standard address of the move-in customer to how it was before the move-in , provided the following conditions have been met:

- The **SA** (Standard address of move-in customer adjusted) is selected in Customizing under [Define Control Parameters for Move-In on Document Level](#) .
- The move-in customer already had a standard address before the move-in was entered in the system

Move-Out

Use

During the move-out transaction, you execute most of the activities required to cancel the customer's supply of utilities services. You make changes to the business partner master data that result from a move-out. You specifically end the allocation of a contract to an installation on the move-out date.



Move-out processing stops the active payment plans. A move-out confirmation letter and an immediate bill can also be triggered from the move-out.

Prerequisites

You require one or more existing contracts with installations for the requested move-out date to create a move-out.

Features

Budget Billing Plan

In Customizing under **Move-In/Out > Move-Out > Define Move-Out Control Parameters at Contract Level**, you can specify

Open Items in Dunning

Once you have created the move-out, you have the option of applying an alternative dunning procedure to the contracts in the move-out. You can also deactivate the dunning procedure that is currently active by specifying a dunning block reason due to the move-out. This data can also be defined as default data by making the necessary Customizing settings.

Move-Out Status

If you edit or display a move-out document, the system displays the move-out status for every contract. This shows how far you have completed move-out processing for this contract.

The system calculates the minimum status from the move-out status and also displays this. This means that you have quick access to the status of overall move-out processing.

Move-Out Documents

If you display move-out documents for a business partner or premise, the system displays documents for the last three months. If no documents exist for this period, the system displays the documents from the last six months.

Final Billing

You have the option of triggering an immediate bill for contracts in the move-out from move-out processing, once move-out status 05 (meter readings entered completely) has been reached for the entire move-out. During this process, billing, invoicing and then the bill print are accessed.

Activities

Screen Layout

In Customizing under **►►Move-In/Out ► Move-Out - Configure Tabs for Move-Out Screen ►**, you can configure various views of the data available on the move-out screen. This consists of various tab pages that you can use to divide the data into various logical units according to your requirements.

For more information, see [Screen Layout](#).

Move-Out Date

You can subsequently change the move-out date for a move-out that has already been created without affecting the date of the subsequent move-in. You cannot change the date for contracts that have already been billed or for a contract and customer change.

Actual Move-Out Date

In addition to the move-out date, you can also enter an alternative actual move-in date.

Save

Certain actions in the move-out (such as triggering a move-out confirmation letter) assume that the changes triggered by the move-out have been updated in the database. In Customizing under **►►Move-In/Out ► Move-Out Define Control Parameters at Document Level ►**, you can specify whether in this situation, the system is to output a confirmation prompt or save the data automatically before the action is carried out.

In Customizing under ► [Move-In/Out](#) ► [Move-Out Define Move-Out Control Parameters at Contract Level](#) ►, you can specify that an immediate bill is created automatically when the move-out id saved.

Master Data (Move-Out)

Use

If the move-out date is in a period for which one of the installations was already billed, the system does not permit you to create the move-out. You must reverse the billing before you can process the move-out.

You can find additional information in the section on the [Master data](#) component.

You can save changes to business partner and contract account data as **scheduled** changes. This means that the changes are not activated until a future date. This date is determined by subtracting the interval period defined in Customizing from the move-out date. For more information on how to define the interval period, see Customizing under ► [SAP Utilities](#) ► [Customer Service](#) ► [Process Execution](#) ► [Move-In/Move-Out](#) ► [Define System Parameters for Move-in and Move-Out](#) ►. Scheduled changes are activated by report BUSPCDACT (activation of scheduled change documents for an application object).

Move-out Confirmation Letter

Use

When you create or change a move-out, you can print a move-out confirmation letter. To do this, use the application form of the form class IS_U_CS_MOVE_OUT_NOTIFICATION. You must define this application form in Customizing under ► [Move-In/Out](#) ► [Move-Out](#) ► [Define Move-Out Confirmation Letter](#) ►). Under ► [Move-Out](#) ► [Define Move-Out Control Parameters at Document Level](#) ►, you can configure the system to automatically use a user-defined application form each time you attempt to print a move-out confirmation letter.

You can find additional information on creating an application form in the section on the [Print workbench](#) component.

Meter Reading Data (Move-Out)

Use

When you create a move-out, the system automatically creates a meter reading order for all the meter reading-relevant registers that belong to the devices allocated to the installation for billing purposes. A prerequisite is that you have not entered a meter reading.

In Customizing under ► [Utilities Industry](#) ► [Customer Service](#) ► [Process Execution](#) ► [Move-In/Out](#) ► [Move-Out](#) ► [Define Move-Out Control Parameters at Contract Level](#) ►, you can determine how these meter reading orders are processed.

- All registers to be read by the customer (according to the planned meter reading type) can be printed on a card for meter reading by customer.
- All registers to be read by the utility company (according to the planned meter reading type) flow into a PM-SMA service order, or be printed on an IS-U form for meter reading by the meter reader.

move-out are further processed.

Features

When you create a move-out, the system proposes an existing meter reading result for all the billing-relevant registers allocated to the installation for billing purposes. Ensure you have configured the system accordingly in Customizing under [SAP Utilities](#) [Device Management](#) [Meter Reading](#) [Basic Settings](#) [Define Control Parameters for Meter Reading Data Processing](#).

- If the system proposes a meter reading result then choose one of the following two options:
 - If you adopt the meter reading result, the system adds the meter reading reason **End** to the result.
 - If you change the meter reading result, a new result is created with the meter reading reason **End**.
- If the system does not propose a meter reading result, you can have it estimate a result or enter one manually. In both cases, the system creates a new result with the meter reading reason **Move-in**.
- If a result is not created by your adopting/changing a proposed result, and if you do not enter one manually, the system creates a service notification or service order for the register. For more information see [service notifications and orders](#).

Automatic Estimation of Meter Reading Results During Move-Out

If a contract is terminated when a supply scenario is created or changed, you can have missing meter readings estimated automatically when you create the move-out.

If you want to use this function, create an implementation for method STOP_CONTRACT of business add-in (BAI) ISU_IDE_DRGSCEN_GEN.

For more information, see the documentation for the BAI.

If you want to use the function for automatically estimating missing meter readings during move-out in the master data generator, adjust your master data templates as follows in Customizing for [SAP Utilities](#) under [Customer Service](#) [Master Data Generator](#) [Define Master Data Template](#):

Attribute ESTIMATE_MR ([Master data generator: Estimate MR Results During Move-Out](#)) must contain the value "X in all nodes of the master data template category MOVE_OUT ([Move-Out in Connection with CRM](#)).

Move-Out Reversal

Use

You use this function to reverse the termination of a contract during move-out. In doing this, the move-out date is set back in the contract. You require this function in the following instances:

- The move-out was mistakenly created with the wrong business partner or with the wrong contract.
- A changed move-out date subsequently becomes known. In this case, the move-out must be recreated using the changed move-out date after the move-out reversal is performed.
- The move-out only relates to some of the contracts of the business partner. In this case, the move-out must be recreated for the contracts that are actually concerned after the move-out reversal is performed.

A move-out and subsequent move-in for the installations of a premise often have to be reversed in one function call. In this case, the move-in must be reversed first and subsequently the move-out can be reversed.

Prerequisites

None of the contracts may be billed for the period beginning with the move-out date. The final billing triggered by the move-out must be reversed before the move-out can be reversed.

Features

Changes that were automatically made to the contract data during creation of the move-out are reversed during move-out reversal.

If a budget billing plan was terminated during creation of a move-out, it is automatically activated during move-out reversal.

Meter reading orders and meter reading results that were created in the move-out are automatically deleted.

Changes that were made during move-out to the business partner and contract account data are not automatically reversed during the move-out reversal.