



Customer Service

Generated on: 2026-09-29 09:41:37 GMT+0000

SAP S/4HANA | 2025 FPS01 (Feb 2026)

Public

Original content: https://help.sap.com/docs/SAP_S4HANA_ON-PREMISE/f4a255a5de524e3992155767996fb1fd?locale=en-US&state=PRODUCTION&version=2025.001

Warning

This document has been generated from SAP Help Portal and is an incomplete version of the official SAP product documentation. The information included in custom documentation may not reflect the arrangement of topics in SAP Help Portal, and may be missing important aspects and/or correlations to other topics. For this reason, it is not for production use.

For more information, please visit <https://help.sap.com/docs/disclaimer>.

Move-Out

Use

During the move-out transaction, you execute most of the activities required to cancel the customer's supply of utilities services. You make changes to the business partner master data that result from a move-out. You specifically end the allocation of a contract to an installation on the move-out date.



Move-out processing stops the active payment plans. A move-out confirmation letter and an immediate bill can also be triggered from the move-out.

Prerequisites

You require one or more existing contracts with installations for the requested move-out date to create a move-out.

Features

Budget Billing Plan

billing amounts whose print date is later than the move-out date are no longer requested. Budget billing amounts that have already been paid are cleared when the final billing is invoiced.

Open Items in Dunning

Once you have created the move-out, you have the option of applying an alternative dunning procedure to the contracts in the move-out. You can also deactivate the dunning procedure that is currently active by specifying a dunning block reason due to the move-out. This data can also be defined as default data by making the necessary Customizing settings.

Move-Out Status

If you edit or display a move-out document, the system displays the move-out status for every contract. This shows how far you have completed move-out processing for this contract.

The system calculates the minimum status from the move-out status and also displays this. This means that you have quick access to the status of overall move-out processing.

Move-Out Documents

If you display move-out documents for a business partner or premise, the system displays documents for the last three months. If no documents exist for this period, the system displays the documents from the last six months.

Final Billing

You have the option of triggering an immediate bill for contracts in the move-out from move-out processing, once move-out status 05 (meter readings entered completely) has been reached for the entire move-out. During this process, billing, invoicing and then the bill print are accessed.

Activities

Screen Layout

In Customizing under ► **Move-In/Out** ► **Move-Out - Configure Tabs for Move-Out Screen** ►, you can configure various views of the data available on the move-out screen. This consists of various tab pages that you can use to divide the data into various logical units according to your requirements.

For more information, see [Screen Layout](#).

Move-Out Date

You can subsequently change the move-out date for a move-out that has already been created without affecting the date of the subsequent move-in. You cannot change the date for contracts that have already been billed or for a contract and customer change.

Actual Move-Out Date

In addition to the move-out date, you can also enter an alternative actual move-in date.

Save

Certain actions in the move-out (such as triggering a move-out confirmation letter) assume that the changes triggered by the

You can also save your changes in the move-out without leaving the move-out screen. To do this, choose [Save and Hold](#).

Final Billing

In Customizing under [►Move-In/Out ► Move-Out Define Move-Out Control Parameters at Contract Level ►](#), you can specify that an immediate bill is created automatically when the move-out id saved.

Master Data (Move-Out)

Use

If the move-out date is in a period for which one of the installations was already billed, the system does not permit you to create the move-out. You must reverse the billing before you can process the move-out.

You can find additional information in the section on the [Master data](#) component.

You can save changes to business partner and contract account data as **scheduled** changes. This means that the changes are not activated until a future date. This date is determined by subtracting the interval period defined in Customizing from the move-out date. For more information on how to define the interval period, see Customizing under [►SAP Utilities ► Customer Service ► Process Execution ► Move-In/Move-Out ► Define System Parameters for Move-in and Move-Out ►](#). Scheduled changes are activated by report BUSPCDACT (activation of scheduled change documents for an application object).

Move-out Confirmation Letter

Use

When you create or change a move-out, you can print a move-out confirmation letter. To do this, use the application form of the form class IS_U_CS_MOVE_OUT_NOTIFICATION. You must define this application form in Customizing under [►Move-In/Out ► Move-Out ► Define Move-Out Confirmation Letter ►](#)). Under [►Move-Out ► Define Move-Out Control Parameters at Document Level ►](#), you can configure the system to automatically use a user-defined application form each time you attempt to print a move-out confirmation letter.

You can find additional information on creating an application form in the section on the [Print workbench](#) component.

Meter Reading Data (Move-Out)

Use

When you create a move-out, the system automatically creates a meter reading order for all the meter reading-relevant registers that belong to the devices allocated to the installation for billing purposes. A prerequisite is that you have not entered a meter reading.

In Customizing under [►Utilities Industry ► Customer Service ► Process Execution ► Move-In/Out ► Move-Out ► Define Move-Out Control Parameters at Contract Level ►](#), you can determine how these meter reading orders are processed.

- All registers to be read by the customer (according to the planned meter reading type) can be printed on a card for meter reading by customer.

- Alternatively, you can configure it for a download for mobile data entry (MDE).

In Customizing under **▮SAP Utilities▮Customer Service▮Process Execution▮Move-In/Out▮Move-Out▮Define Move-Out Control Parameters at Contract Level▮**, you can also configure the way in which meter reading orders that were created in the move-out are further processed.

Features

When you create a move-out, the system proposes an existing meter reading result for all the billing-relevant registers allocated to the installation for billing purposes. Ensure you have configured the system accordingly in Customizing under **▮SAP Utilities▮Device Management▮Meter Reading▮Basic Settings▮Define Control Parameters for Meter Reading Data Processing▮**.

- If the system proposes a meter reading result then choose one of the following two options:
 - If you adopt the meter reading result, the system adds the meter reading reason **End** to the result.
 - If you change the meter reading result, a new result is created with the meter reading reason **End**.
- If the system does not propose a meter reading result, you can have it estimate a result or enter one manually. In both cases, the system creates a new result with the meter reading reason **Move-in**.
- If a result is not created by your adopting/changing a proposed result, and if you do not enter one manually, the system creates a service notification or service order for the register. For more information see [service notifications and orders](#).

Automatic Estimation of Meter Reading Results During Move-Out

If a contract is terminated when a supply scenario is created or changed, you can have missing meter readings estimated automatically when you create the move-out.

If you want to use this function, create an implementation for method STOP_CONTRACT of business add-in (BAI) ISU_IDE_DRGSCEN_GEN.

For more information, see the documentation for the BAI.

If you want to use the function for automatically estimating missing meter readings during move-out in the master data generator, adjust your master data templates as follows in Customizing for **SAP Utilities** under **▮Customer Service▮Master Data Generator▮Define Master Data Template▮**:

Attribute ESTIMATE_MR (**Master data generator: Estimate MR Results During Move-Out**) must contain the value "X in all nodes of the master data template category MOVE_OUT (**Move-Out in Connection with CRM**).