



Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

1. Screen shot of device manager -
 - a. HP TrueVision HD Camera (built-in) installed
 - b. USB camera not installed




2. Screenshot of device manager after installing USB camera
 - a. HP TrueVision HD Camera (built-in) installed
 - b. USB camera installed



3. Sample picture taken via USB camera

Bluetooth & devices > Cameras > USB Camera




USB Camera

Troubleshoot

Disable

Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

1. Before connecting the USB printer, the Windows Settings panel under Bluetooth & devices > Printers & scanners was examined. Only the default virtual devices were present: Fax and Microsoft Print to PDF. The HP DeskJet 2130 was absent, confirming the disconnected/undetected state.



The HP DeskJet 2130 USB cable was connected to the system. Windows automatically detected the device and installed the necessary drivers. Upon refreshing the Printers & Scanners page, the HP DJ 2130 series now appeared in the list alongside the previously existing printers.

Bluetooth & devices > Printers & scanners

Add a printer or scanner

Add device



Fax



HP DJ 2130 series



Microsoft Print to PDF



Device Manager



File Action View Help



Halo


- > Audio inputs and outputs
- > Audio Processing Objects (APOs)
- > Batteries
- > Bluetooth
- > Cameras
- > Computer
- > Disk drives
- > Display adapters
- > Firmware
- > Human Interface Devices
- > Imaging devices
- > Keyboards
- > Mice and other pointing devices
- > Monitors
- > Network adapters
- > Print queues
- ▼ Printers
 - HP DJ 2130 series
- > Processors
- > SD host adapters
- > Security devices
- > Software components
- > Software devices
- > Sound, video and game controllers
- > Storage controllers

Task 3 - Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem. Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting

Simulating Error using - Disable the Device in Device Manager


1. Press **Win + X** - open **Device Manager**
2. Expand **Printers**
3. Right-click your printer → click **Disable device**
4. It will show a **down arrow icon** — simulating a "not detected" state

✓ Printers




- Error Icon confirming connectivity issue

After enabling, "scan for hardware changes"



Checked Printer status: - Error is resolved

✓ Printers



A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications. Hint: Check if another app is using the webcam or if Zoom permissions are enabled.

Step 1: Verify Webcam is working

- Opened the default Camera application.
- Confirmed that the webcam displayed video correctly.
- Using 'device manager' checked the camera hardware and driver were functioning.

Step 2 : Check Camera conflict

- Open task manager, check if any additional apps which can use the camera are running - like google meets, microsoft teams etc. Close the apps
- Restart zoom app and check

Step 3 : Verify Zoom Camera Selection


- Opened Zoom.
- Navigate to Settings → Video.
- Check the correct webcam was selected from the Camera dropdown menu.
- Verify that the video preview appeared.

Step 4: Check Camera Permissions

- Open Settings → Privacy & Security → Camera.
- Confirmed:
 - Camera access is enabled.
 - App permission to the camera is enabled.
 - Zoom is allowed to access the camera.

Step 5: Conflict of webcams

- Check if more than 1 camera is installed, if required disable the camera not being used, so that zoom app can detect only the active camera.



Settings– Bluetooth & devices – Camera - Check all the connected camera and disable cameras not being used.



One camera is disabled to avoid any conflict