javax.swing.*
JSlider + JProgressBar

Methods declared in supertypes are hidden in subtypes

InputStream *(java.io.)*

FilterInputStream *(java.io.)*

ProgressMonitorInputStream
ProgressMonitorInputStream (Component parentComponent,
Object message, InputStream in)

ProgressMonitor getProgressMonitor ()

ProgressMonitor
ProgressMonitor (Component parentComponent, Object message,
String note, int min, int max)

Accessors
int get / setMaximum ()
int get / setMillisToDecideToPopup ()
int get / setMillisToPopup ()
int get / setMinimum ()
String get / setNote ()
boolean isCanceled ()
void setProgress (int nv)
Other Public Methods
void close ()

Component *(java.awt.)*

Container *(java.awt.)*

JComponent

SwingConstants
int CENTER, TOP, LEFT,
BOTTOM, RIGHT, NORTH,
NORTH_EAST, EAST,
SOUTH_EAST, SOUTH,
SOUTH_WEST, WEST,
NORTH_WEST,
HORIZONTAL, VERTICAL,
LEADING, TRAILING,
NEXT, PREVIOUS

JProgressBar
JProgressBar ()
JProgressBar (int orient)
JProgressBar (BoundedRangeModel newModel)
JProgressBar (int min, int max)
JProgressBar (int orient, int min, int max)

Accessors
int get / setMaximum ()
int get / setMinimum ()
BoundedRangeModel get / setModel ()
int get / setOrientation ()
double getPercentComplete ()
String get / setString ()
ProgressBarUI get / setUI ()
int get / setValue ()
boolean is / setBorderPainted ()
boolean is / setIndeterminate ()
boolean is / setStringPainted ()
Event Methods
ChangeListener add / removeChangeListener (ChangeListener l)
ChangeListener createChangeListener ()
void fireStateChanged ()
ChangeListener[] getChangeListeners ()

JSlider
JSlider ()
JSlider (int orientation)
JSlider (BoundedRangeModel brm)
JSlider (int min, int max)
JSlider (int min, int max, int value)
JSlider (int orientation, int min, int max, int value)

Accessors
int get / setExtent ()
boolean get / setInverted ()
Dictionary get / setLabelTable ()
int get / setMajorTickSpacing ()
int get / setMaximum ()
int get / setMinimum ()
int get / setMinorTickSpacing ()
BoundedRangeModel get / setModel ()
int get / setOrientation ()
boolean get / setPaintLabels ()
boolean get / setPaintTicks ()
boolean get / setPaintTrack ()
boolean get / setSnapToTicks ()
SliderUI get / setUI ()
int get / setValue ()
boolean get / setValueIsAdjusting ()
Event Methods
void add / removeChangeListener (ChangeListener l)
ChangeListener createChangeListener ()
void fireStateChanged ()
ChangeListener[] getChangeListeners ()
Other Methods
Hashtable createStandardLabels (int increment)
Hashtable createStandardLabels (int increment, int start)
void updateLabelUIs ()

Serializable

DefaultBoundedRangeModel
DefaultBoundedRangeModel ()
DefaultBoundedRangeModel (int value, int extent, int min, int max)

Event Methods
void fireStateChanged ()
ChangeListener[] getChangeListeners ()
EventListener[] getListeners (Class listenerType)
Object
String toString ()

BoundedRangeModel
Accessors
int get / setExtent ()
int get / setMaximum ()
int get / setMinimum ()
int get / setValue ()
boolean get / setValueIsAdjusting ()
void setRangeProperties (int value, int extent, int min, int max, boolean adjusting)
Event Methods
void add / removeChangeListener (ChangeListener x)