javax.accessibility.*

Values

Methods declared in supertypes are hidden in subtypes



String getAccessibleActionDescription(int i) int getAccessibleActionCount()

boolean doAccessibleAction(inti)

Object getAccessibleActionAnchor(inti) Object getAccessibleActionObject(int i) int getEndIndex()

AccessibleHyperlink

int getStartIndex() boolean isValid()

AccessibleIcon

String get / setAccessibleIconDescription() int getAccessibleIconHeight() int getAccessibleIconWidth()

AccessibleKeyBinding

int getAccessibleKeyBindingCount() java.lang.Object getAccessibleKeyBinding(int i)

Accessible Value

boolean setCurrentAccessibleValue(Number n) Number get / setCurrentAccessibleValue() Number getMaximumAccessibleValue() Number getMinimumAccessibleValue()

AccessibleSelection

Accessible getAccessibleSelection(int i)

boolean is Accessible Child Selected (inti) int getAccessibleSelectionCount()

void add / removeAccessibleSelection(inti)

void selectAllAccessibleSelection() void clearAccessibleSelection()

Accessible Editable Text

void setAttributes (int startIndex, int endIndex, AttributeSet as) String getTextRange (int startIndex, int endIndex) void setTextContents (Strings)

void insertTextAtIndex (int index, Strings) void delete (int startIndex, int endIndex)

String getBeforeIndex (int part, int index)

int getCaretPosition()

int getCharCount()

AttributeSet getCharacterAttribute (int i) Rectangle getCharacterBounds(int i) int getIndexAtPoint(Point p)

String getAfterIndex (int part, int index)

AccessibleText

String getAtIndex (int part, int index)

void cut (int startIndex, int endIndex)

void replaceText (int startIndex, int endIndex, String s) void paste (int startIndex)

void selectText (int startIndex, int endIndex)

| AccessibleHypertext

Accessible Hyperlink getLink (int linkIndex)

int getLinkCount()

int CHARACTER, WORD, SENTENCE

int getSelectionStart()

String getSelectedText() int getSelectionEnd() int getLinkIndex (int charIndex)

Accessible get / setAccessibleCaption() Accessible getAccessibleAt(intr, intc)

Accessible Table

Accessible get / setAccessibleColumnDescription(int c) int getAccessibleColumnCount()

int getAccessibleColumnExtentAt(int r, int c) Accessible Table get / setAccessibleColumnHeader()

Accessible get / setAccessibleRowDescription(int r) int getAccessibleRowExtentAt(int r, int c) Accessible Table get / setAccessibleRowHeader() int getAccessibleRowCount()

int[] getSelectedAccessibleColumns() Accessible get / setAccessibleSummary()

int[] getSelectedAccessibleRows()

boolean is Accessible Column Selected (int c)

boolean is Accessible Selected (int r, int c) boolean isAccessibleRowSelected(intr)

| AccessibleTableModelChange

int getFirstColumn() int getFirstRow ()

int getLastColumn() int getLastRow()

int getType ()

int INSERT, UPDATE, DELETE

AccessibleExtendedTable

int getAccessibleColumn(intindex) int getAccessibleIndex(int r, int c)

int getAccessibleRow(intindex)