

Methods declared in supertypes are hidden in subtypes



void columnSelectionChanged(ListSelectionEvente) void columnRemoved(TableColumnModelEvente) void columnMoved (TableColumnModelEvente) void columnAdded (TableColumnModelEvente) void columnMarginChanged(ChangeEvente)



JTableHeader

JTableHeader (TableColumnModelcm) JTableHeader ()

Accessors

TableCellRenderer get / setDefaultRenderer() TableColumnModel get / setColumnModel()

int get / setDraggedDistance() Rectangle getHeaderRect (int column)

TableColumn get / setDraggedColumn ()

boolean get / setReorderingAllowed() boolean get / setResizingAllowed()

TableColumn get / setResizingColumn()

boolean get / setUpdateTableInRealTime() JTable get / setTable () TableHeaderUI get / setUI ()

int columnAtPoint (Point point) Other Public Methods

void resizeAndRepaint() Other Protected Methods

TableColumnModel createDefaultColumnModel() # TableCellRenderer createDefaultRenderer() void initializeLocalVars()



TableColumn

TableColumn ()

TableColumn (int modelIndex)

TableColumn (int modelIndex, int width)

TableColumn (int modellndex, int width, TableCellRenderercellRenderer, TableCellEditorcellEditor)

Accessors

TableCellRenderer get / setHeaderRenderer() TableCellRenderer get / setCellRenderer () TableCellEditor get / setCellEditor ()

Object get/setHeaderValue() Object get / setIdentifier ()

int get / setMaxWidth ()
int get / setMinWidth ()
int get / setModelIndex ()
int get / setPreferredWidth ()

boolean get / setResizable () int get / setWidth ()

Event Methods

void add / removePropertyChangeListener(PropertyChangeListeneri)

PropertyChangeListener[] getPropertyChangeListeners()

Other Methods

TableCellRenderer createDefaultHeaderRenderer() void sizeWidthToFit()

String COLUMN_WIDTH_PROPERTY, HEADER_VALUE_PROPERTY,

HEADER_RENDERER_PROPERTY, CELL_RENDERER_PROPERTY