

```
Router(config-if)#exit
Router(config)#interface serial 1/0
%Invalid interface type and number
Router(config)#ip address 20.0.0.1 255.0.0.0
% Invalid input detected at '^' marker.
Router(config) #ip address 20.0.0.1 255.0.0.0
% Invalid input detected at '^' marker.
Router(config) #exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#enable
Router#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface serial 2/0
Router(config-if)#ip address 20.0.0.1 255.0.0.0
Router(config-if)#encapsulation ppp
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown
%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if) #exit
Router(config-if) #exit
Router(config) #
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router(config) #router rip
Router(config=router) #network 10.0.0.0
Router(config=router) #network 20.0.0.0
Router(config=router) #exit
Router(config) #
Router(config) #
Router(config) #router ospf 1
Router(config-router) #router id 1.1.1.1
% Invalid input detected at '^' marker.
Router(config-router) #router-id 1.1.1.1
Router(config-router) #network 10.0.0.0 0.255.255.255 area 3
Router(config-router) #network 20.0.0.0 0.255.255.255 area 1
Router(config-router) #exit
Router(config) #
00:20:44: %OSPF-5-ADJCHG: Process 1, Nbr 2.2.2.2 on Serial2/0 from LOADING to FULL, Loading Done
Router(config) #interface loopback 0
Router(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
Router(config-if) #ip add 172.16.1.252 255.255.0.0
Router(config-if) #no shutdown
Router(config-if) #exit
Router(config) #Frouter ospf 1
Router(config-router) #area 1 virtual-link 2.2.2.2
Router(config-router) #exit
Router(config) #
```

