

[On This Page](#) >

data-mesher

Set up data-mesher

System

❖ Experimental

This service is experimental and will change in the future.

This service will set up data-mesher.

Usage

```
1 inventory.instances = {
2   data-mesher = {
3     module = {
4       name = "data-mesher";
5       input = "clan-core";
6     };
7     roles.admin.machines.server0 = {
8       settings = {
9         bootstrapNodes = {
10          node1 = "192.168.1.1:7946";
11          node2 = "192.168.1.2:7946";
12        };
13
14        network = {
15          hostTTL = "24h";
16          interface = "tailscale0";
17        };
18      };
19    };
20  };
21 }
```

```
18     };  
19     };  
20     roles.peer.machines.server1 = { };  
21     roles.signer.machines.server2 = { };  
22 };  
23 }
```

Roles

The data-mesher service has the following roles:

- admin
- peer
- signer

Options for the `admin` role

bootstrapNodes

A list of bootstrap nodes that act as an initial gateway when joining the cluster.

Type: `null or (list of string)`

❖ Example

```
1 [  
2   "192.168.1.1:7946"  
3   "192.168.1.2:7946"  
4 ]
```

Declared in: [clanServices/data-mesher/default.nix](#)

extraHostNames

A list of extra hostnames to claim for this machine.

Type: `list of string`

Default:

`[ ]`

Declared in: [clanServices/data-mesher/default.nix](#)

network.hostTTL

The TTL for hosts in the network, in the form of a Go time.Duration

Type: `string`

Default:

`"672h"`

❖ Example

`"24h"`

Declared in: [clanServices/data-mesher/default.nix](#)

network.interface

The interface over which cluster communication should be performed. All the ip addresses associate with this interface will be part of our host claim, including both ipv4 and ipv6.

This should be set to an internal/VPN interface.

Type: `string`

❖ Example

"tailscale0"

Declared in: [clanServices/data-mesher/default.nix](#)

network.port

Port to listen on for cluster communication.

Type: 16 bit unsigned integer; between 0 and 65535 (both inclusive)

Default:

7946

Declared in: [clanServices/data-mesher/default.nix](#)

network.tld

Top level domain to use for the network

Type: string

Default:

"clan"

Declared in: [clanServices/data-mesher/default.nix](#)

Options for the `peer` role

bootstrapNodes

A list of bootstrap nodes that act as an initial gateway when joining the cluster.

Type: `null or (list of string)`

❖ Example

```
1 [
2   "192.168.1.1:7946"
3   "192.168.1.2:7946"
4 ]
```

Declared in: [clanServices/data-mesher/default.nix](#)

extraHostNames

A list of extra hostnames to claim for this machine.

Type: `list of string`

Default:

```
[ ]
```

Declared in: [clanServices/data-mesher/default.nix](#)

network.interface

The interface over which cluster communication should be performed. All the ip addresses associate with this interface will be part of our host claim, including both ipv4 and ipv6.

This should be set to an internal/VPN interface.

Type: `string`

❖ Example

```
"tailscale0"
```

Declared in: [clanServices/data-mesher/default.nix](#)

network.port

Port to listen on for cluster communication.

Type: 16 bit unsigned integer; between 0 and 65535 (both inclusive)

Default:

7946

Declared in: [clanServices/data-mesher/default.nix](#)

Options for the `signer` role

bootstrapNodes

A list of bootstrap nodes that act as an initial gateway when joining the cluster.

Type: null or (list of string)

Example

```
1 [
2   "192.168.1.1:7946"
3   "192.168.1.2:7946"
4 ]
```

Declared in: [clanServices/data-mesher/default.nix](#)

extraHostNames

A list of extra hostnames to claim for this machine.

Type: list of string

Default:

[]

Declared in: [clanServices/data-mesher/default.nix](#)

network.interface

The interface over which cluster communication should be performed. All the ip addresses associate with this interface will be part of our host claim, including both ipv4 and ipv6.

This should be set to an internal/VPN interface.

Type: `string`

Example

```
"tailscale0"
```

Declared in: [clanServices/data-mesher/default.nix](#)

network.port

Port to listen on for cluster communication.

Type: `16 bit unsigned integer; between 0 and 65535 (both inclusive)`

Default:

7946

Declared in: [clanServices/data-mesher/default.nix](#)

← Previous
coredns

Next →
dyndns

Need help? Reach out to [our community](#).